Kiosk Terminal
Setup & Access Guide

How to register a self-service kiosk device, pair it securely, and control who on your team can manage it.

SSVK ERP — Admin Reference
Generated 09 October 2026

Important: This guide covers Phase 1 of the kiosk feature: device registration, pairing, and admin access control only. The customer-facing self-service screen (browse products, add to cart, check out) has not been built yet — pairing a device today proves it is securely registered and authenticated, but there is nothing for a customer to actually order from it until that next phase ships.

1. What is a Kiosk Device?

A **kiosk device** is a tablet or touchscreen computer that will eventually let a customer browse and buy tickets or make a donation on their own, with no staff involvement. Before any of that can happen, the device itself has to be registered and proven trustworthy — that is what this guide covers.

Every kiosk device is set up for exactly one purpose, chosen by an admin at registration time:

- **Tickets** — the device will sell tickets from the Ticket catalogue.
- **Donations** — the device will take donations for one specific event.

A device also has its own card-payment configuration — which already-paired EFT terminal its card payments go through, and which payment methods it offers — set once at setup and editable afterwards by whoever is allowed to manage that device (see Section 5).

> **Note:** A kiosk device never pairs its own EFT terminal. It is only ever pointed at a terminal that has already been paired through the normal EFT Terminal Settings page. If left unset, it falls back to the registry's own default terminal automatically.

2. Before You Start

- You need an account that can manage kiosk devices — System Admin, an admin-tier Ticket Controller, or an admin-tier Event Coordinator (see Section 5 for exactly who can do what).
- If the kiosk will take card payments, make sure the EFT terminal it should use is already paired on the EFT Terminal Settings page first.
- If the kiosk is for Donations, the event it will take donations for must already exist.
- Have the physical tablet/device ready and able to reach this site in a browser — that is where you will enter the pairing code.

3. Register a New Kiosk Device

1. Log in with an account that can manage kiosk devices.
2. Open **Admin** → **Kiosk Devices** from the sidebar.
3. Click **Register New Device**.
4. Fill in the form (see field descriptions below) and click **Register**.
5. The new device appears in the list with a **Pending** status — it cannot be used yet until it is paired (Section 4).

Registration fields

Name — A clear display name for this device, e.g. “Front Lobby Kiosk 1”. Shown everywhere this device is listed.

Label — Optional free-text note for your own bookkeeping, e.g. “Entrance” or “Side Hall”. This is not a real location record — just a reminder.

Module — Tickets or Donations — what this device is for. Can be left unset at registration and decided later, but only a System Admin can configure an unset device.

Event — Only shown when Module is Donations — which event this device takes donations for.

EFT Terminal — Which already-paired terminal this device's card payments use. Leave as “Use registry default” unless you specifically want this device on a particular terminal.

Payment Methods — Which payment methods this device offers. Leave all unchecked to use the system-wide default methods.

4. Pair the Physical Device

Pairing is how a physical device proves it is the one the admin just registered, and receives its own secure credential. It only needs to be done once per device (or again later if the device is ever revoked and needs to start over).

1. On the **Admin** → **Kiosk Devices** page, find the device you just registered and click **Pairing Code**.
2. A one-time code appears (for example **3BA2 36RK**) — it is shown only this once and is valid for **10 minutes**.
3. On the physical kiosk device, open a browser and go to **/kiosk/pair** on this site.
4. Type the code in and tap **Pair Device**.
5. On success, the device shows “Paired as ‘…’” and its status on the admin page flips to **Active**.

Important: The pairing code is shown to the admin exactly once and is never stored anywhere in readable form — if you miss it or it expires before you use it, just click “Pairing Code” again to generate a fresh one. A code can only be used once; a second attempt with the same code is always rejected.

Note: What the device receives after pairing is a long, randomly generated secret — not just a label or an ID it made up itself. It is sent on every request as a special header, and the server only ever stores a hashed, one-way version of it — the same technique used for this system's own POS PIN logins.

5. Who Can Manage a Kiosk Device

Two different things can be controlled, and they follow different rules on purpose:

- **The device's lifecycle** (register, pair, activate, deactivate, revoke, rotate) — this is broad, following the same group already trusted with the EFT terminal registry.
- **The device's configuration** (which module/event/terminal/payment methods it uses) — this is narrower and follows module/event ownership, matching how Ticket Console and Event Console access already work.

Role / Tier	Register, pair, activate, deactivate, revoke, rotate	Configure module / event / terminal / payment methods
System Admin	Yes — every device	Yes — every device, including unassigned ones
Admin-tier Ticket Controller	Yes — every device	Yes, but only devices set to the Tickets module
Admin-tier Event Coordinator	Yes — every device	Yes, but only Donations-module devices for their own event
View / Entry-level Ticket Controller or Event Coordinator	No	No
Any other staff role	No	No

> **Note:** A newly registered device with no Module set yet can only be configured by a System Admin — nobody else “owns” it until its purpose is decided. Once its Module (and Event, for Donations) is set, ownership follows the table above automatically.

6. Managing a Device After It's Paired

Status	Meaning
Pending	Registered but not yet paired — generate a pairing code and enter it on the device to activate it.
Active	Paired and able to reach every /kiosk/* route.
Disabled	Temporarily switched off — the device keeps its credential and can be switched back to Active at any time with no re-pairing needed.
Revoked	Permanently locked out — its credential is deleted outright. A revoked device must be paired again from scratch (a fresh pairing code) to ever work again.

Rotating a credential

If a device's credential may have been exposed but you still trust the physical device itself (for example, you are unsure whether a staff member wrote the pairing token down somewhere insecure), click **Rotate Credential**. This issues a brand-new secret immediately — the old one stops working the instant you do this — and the new one must be entered on the device by hand, the same way a pairing code is.

Revoking a device

If a device is lost, stolen, decommissioned, or you simply no longer trust it, click **Revoke**. This deletes its credential outright (not just a status flag) — it is locked out of every kiosk route immediately, even mid-request. A revoked device has to go through pairing again from scratch, with a fresh pairing code, if it is ever brought back into use.

7. Troubleshooting

“That pairing code is invalid or has expired.”

Either the code was mistyped, it has passed its 10-minute window, or it has already been used once. Generate a fresh code and try again — codes are always single-use.

“Device not registered.” / “Device not authorised.” on the kiosk device itself

The device has no credential yet (it was never paired), or its credential has stopped working because the device was deactivated or revoked. Check its status on the Kiosk Devices admin page; if revoked, it needs to be paired again with a new code.

The Kiosk Devices page itself says “Unauthorized access.”

Your account does not have kiosk management access. See Section 5 — you need to be a System Admin, or admin-tier on the Ticket Controller/Event Coordinator grant that matches the device's module.

You can see a device in the list but cannot edit its Module/Event/Terminal

Configuration access is narrower than general management access (Section 5) — you may be able to pair/activate/deactivate it but not change what it is configured for, if it belongs to a different module or event than the one you are admin-tier on.

Card payments are not showing up as an option on this device

Confirm “EFT Terminal” is included in the device's Payment Methods, and that the terminal it is pointed at (or the registry default, if none is set) is actually paired and online on the EFT Terminal Settings page.

8. What Comes Next

This guide covers everything available today. A paired, active device can authenticate itself and is ready for the next phase of this feature: the actual customer-facing ordering screen — a welcome page, product browsing, a cart, checkout, and a confirmation screen for both ticket sales and donations. That part has not been built yet. Once it is, no re-pairing will be needed — an already-paired device will simply start showing the real ordering screen the next time this guide is updated.