# Virtual memory Paging to disk

M1 MOSIG – Operating System Design

Renaud Lachaize

## Acknowledgments

- Many ideas and slides in these lectures were inspired by or even borrowed from the work of others:
  - Arnaud Legrand, Noël De Palma, Sacha Krakowiak
  - David Mazières (Stanford)
    - (most slides/figures directly adapted from those of the CS140 class)
  - Remzi and Andrea Arpaci-Dusseau (U. Wisconsin)
  - Textbooks (Silberschatz et al., Tanenbaum)

#### Outline


- Principles
- Challenge 1: resuming a process
- Challenge 2: choosing what to fetch
- Challenge 3: choosing what to eject
- Further problems and optimizations

## Paging to disk

 Motivation: use secondary storage (disk) to provide a virtual memory with a larger capacity than the physical memory

The RAM acts like a cache for the disk


## Paging to disk (continued)



## Paging to disk Example

- gcc needs a new page of memory
- The kernel reclaims an idle page from emacs
- If the reclaimed page is clean (i.e., also stored on disk, with the same contents)
  - E.g., page of text from emacs binary on disk
  - This page can always be re-read from disk
  - OK to discard contents and give page (frame) to gcc
- If the reclaimed page is dirty (i.e., is the only valid copy)
  - The kernel must write the page to disk first before giving it to gcc
- Either way:
  - Mark page invalid in emacs's paging information
  - emacs will trigger fault on next access to this virtual page
  - On fault, the kernel reads page data back from disk into a new physical page, maps new page into emacs, resumes execution of emacs

#### Working set model



- The disk is much, much slower than memory
  - Goal: run at memory speed, not disk speed
- 90/10 (or 80/20) rule: 10% of memory gets 90% of memory references
  - So, keep that 10% in real memory, the other 90% on disk
  - How to pick which 10%?

## Paging challenges

- How to resume a process after a fault?
  - Need to save state and resume
  - Process might be in the middle of an instruction
- What to fetch?
  - Just needed page or more?
- What to evict?
  - How to allocate physical pages among processes?
  - Which pages of a particular process to keep in memory?

#### Re-starting instructions


- Hardware provides kernel with info about page fault
  - Faulting virtual address
  - Address of instruction that caused fault
  - Was the access a read or write? Was it an instruction fetch?
  - Was it caused by user access to kernel-only memory?
    (protection fault)
- Hardware must allow resuming after a fault
- Idempotent instructions are easy
  - E.g., simple load or store instruction can be restarted
  - Just re-execute any instruction that only accesses one address

#### What to fetch?

- Bring in page that caused page fault
- Pre-fetch surrounding pages?
  - In many cases, reading two disk blocks is approximately as fast as reading one
  - If application exhibits spatial locality, then big win to store and read multiple contiguous pages


## What to evict? Selecting pages Straw man: FIFO eviction

- Evict oldest page fetched in system
- Example consider the following reference string:
  - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- With a capacity of 3 physical pages: 9 page faults




## What to evict? Selecting pages Straw man: FIFO eviction

- Evict oldest page fetched in system
- Example consider the following reference string:
  - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- With a capacity of 3 physical pages: 9 page faults
- With a capacity of 4 physical pages: 10 page faults




## Selecting physical pages Belady's anomaly



More physical memory does not always mean fewer faults


## Optimal page replacement

- What is optimal (if you knew the future)?
  - Replace page that will not be used for the longest period of time
- Example with reference string
  - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- With 4 physical pages



## LRU page replacement

- Approximate optimal with least recently used
  - Because past often predicts the future
- Example with reference string
  - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- With 4 physical pages: 8 page faults




- Problem 1: can be pessimal example?
  - Looping over memory (then want MRU eviction)
- Problem 2: How to implement?

#### Straw man LRU implementations

- Idea 1: Stamp PTEs with timer value
  - E.g., using the CPU cycle counter
  - Automatically write value to PTE on each page access
  - (When page selection is needed) Scan page table to find oldest counter value = LRU page
  - Problem: would dramatically increase the memory traffic
- Idea 2: Keep doubly-linked list of pages
  - On access, remove page, place at tail of list
  - Problem: again, very expensive
- What to do?
  - Just approximate LRU, don't try to do it exactly


#### Clock algorithm

- Use "accessed" bit supported by most hardware
  - E.g., Pentium (x86) will write 1 to "A" bit in PTE on first access
  - Software managed TLBs like MIPS can do the same
- Do FIFO but skip accessed pages
- Keep pages in circular FIFO list
- Scan:
  - If page's "A" bit == 1, set to 0 and skip
  - Else, if "A" == 0, evict
- A.k.a. "second-chance replacement"



## Clock algorithm (continued)

- Large memory may be a problem
  - Most pages referenced in long interval
  - So we may end up having all pages with A=1
- Add a second clock hand
  - Two hands move in lockstep
  - Leading hand clears "A" bit
  - Trailing hand evicts pages with "A"==0




- Can also take advantage of hardware "dirty bit"
  - Each page can be (unaccessed, clean), (unaccessed, dirty), (accessed, clean) or (accessed, dirty)
  - Consider clean pages for eviction before dirty ones
- Or use n-bit variable count instead of just "A" bit
  - On sweep: count = (A << (n-1)) | (count >> 1)
  - Evict page with lowest count

#### Other replacement algorithms

- Random eviction
  - Very simple to implement
  - Not overly horrible results (avoids Belady and pathological cases)
- LFU (least frequently used) eviction
  - Instead of just "A" bit, count the number of times each page is accessed
  - Least frequently accessed page must not be very useful (or maybe was just brought in and is about to be used)
  - Decay usage counts over time (for pages that fall out of usage)
- MFU (most frequently used) algorithm
  - Idea: page with the smallest count was probably just brought in and has yet to be used (so it should not be evicted)
- Neither LFU nor MFU used very commonly

## Naïve paging



Naïve page replacement: 2 disk I/Os per page fault

## Page buffering

- Idea: reduce number of I/Os on the critical path
- Keep pool of free page frames
  - On fault, still select victim page to evict
  - But read fetched page into already free page
  - Can resume execution while writing out victim page
  - Then add victim page to free pool
- Can also yank pages back from free pool
  - Contains only clean pages, but may still have data
  - If page fault on page still in free pool, recycle

#### Outline

- Introduction to paging
  - Principle
  - Data structures and implementation examples
- Speed considerations
  - The memory wall
  - TLB
- Paging to disk
  - Principles
  - Challenge 1: resuming a process
  - Challenge 2: choosing what to fetch
  - Challenge 3: choosing what to eject
  - Further problems and optimizations

#### Page allocation

- Allocation can be global or local
- Global allocation does not consider page ownership
  - E.g., with LRU, evict least recently used page of any process
  - Works well if P1 needs 10% of memory and P2 needs 70%



- Does not protect you from "memory pigs" (imagine P2 keeps looping through array that is size of mem)
- Local allocation isolates processes (or users)
  - Separately determine how much memory each process should have
  - Then use LRU/clock/etc. to determine which pages to evict within each process

## Thrashing


- Thrashing: processes on system require more memory than it has
  - Each time one page is brought in, another page, whose contents will be soon referenced, is thrown out
  - Processes will spend all of their time blocked, waiting for pages to be fetched from disk
  - I/O devices at 100% utilization but system not getting much useful work done
- What we wanted: virtual memory as large as the disk with access time as low as the one of the physical memory
- What we have: memory with access time of the disk

#### Reasons for thrashing


- Process does not reuse memory, so caching does not work (past != future)
- Process does reuse memory, but it does not "fit"



- Individually, all processes fit and reuse memory, but too many for system
  - At least, this case is possible to address (see next slides)



## Multiprogramming and thrashing



Need to shed load when thrashing

## Dealing with thrashing


#### Approach 1: working set

- Thrashing viewed from a caching perspective: given locality of reference, how big a cache does the process need?
- Or: how much memory does process need in order to make reasonable progress (its working set)?
- Only run processes whose memory requirements can be satisfied

#### Approach 2: page fault frequency (PFF)

- Thrashing viewed as poor ratio of "page fetch" to "useful work"
- PFF = page faults / instructions executed
- If PFF rises above threshold, process needs more memory. If not enough memory on the system, swap out.
- If PFF sinks below threshold, memory can be taken away

#### Working sets



- Working sets changes across phases
  - Baloons during transition

## Calculating the working set

- Working set: all the pages that a process will access in next T time frame
  - Cannot calculate without predicting the future
- Approximate by assuming past predicts future
  - So working set ~ pages accessed in last T interval
- Keep idle time for each page
- Periodically scan all resident pages in the system
  - "A" bit set? Clear it and clear the page's idle time
  - "A" bit clear? Add CPU consumed since last scan to idle time
  - Working set is pages with idle time < T</li>

#### Two-level scheduler

- Divide processes into active and inactive
  - Active means working set resident in memory
  - Inactive working set intentionally not loaded
- Balance set: union of all active working sets
  - Must keep balance set smaller than physical memory
- Use long-term scheduler
  - Moves processes from active to inactive state until balance set is small enough
  - Periodically allows inactive to become active
  - As working set changes, must update balance set
- Complications
  - How to chose idle time threshold T?
  - How to pick processes for active set?
  - How to count shared memory (e.g., libc.so)?

#### Recap

- Paging brings nice benefits
  - Removes the fragmentation issue (in the context of address space management)
  - Enables to offload the RAM (demand paging) and thus to fit more processes in RAM
  - Enables to run processes requiring more memory than the available RAM
- Page replacement issues
  - When the RAM is full, a page must be evicted, stored back on the disk and replaced in RAM by the requested one
  - This content management has similarities with the ones in caches,
    TLB, ... but is implemented in software
  - Good policies build on locality, regularity of memory accesses
  - Workload and speed/size of the different memory/disk components call for different policies, data structures and tradeoffs

#### References

- Bruce Jacob and Trevor Mudge. Virtual memory: issues of implementation. IEEE Computer, June 1998.
- AMD and Intel documentations (see previously mentioned links)
- Replacement policies and working sets: see textbooks