





AAA defines a security architecture that is comprised of three functions referred to as Authentication, Authorization and Accounting. Each of these functions represents a modular component which can be applied as components of the security framework implemented by an enterprise, and often managed through the use of client/server based protocols such as RADIUS and HWTACACS. Implementation of the AAA architecture as a solution for enhanced functionality is introduced to reinforce the overall security framework of the enterprise network.






## Upon completion of this section, trainees will be able to:


- Describe the schemes of the AAA security architecture.
- Successfully configure Authentication and Authorization schemes.

# **AAA** Application



 AAA enables the authentication, authorization and accounting of users attempting to access destination network resources.

## Authentication



User access is managed based on an authentication scheme.



### **Authentication**


Se ci sono più metodi di autenticazione definiti, attenzione al loro ordine:

- è stata configurata prima la autenticazione remota e poi quella locale;
- l'account esiste localmente ma non sul server remoto;
- AR2200 considera l'autenticazione fallita e non prova l'autenticazione locale.

Autenticazione locale è usata solo se il server remoto NON RISPONDE.

La clausola di "non-authentication" deve essere l'ultima opzione disponibile.

## **Authorization**




Device Group	User Group	Time	Privilege
Private	Admin	09:00-12:00	15
Public	Admin	09:00-18:00	15
Public	Staff	09:00-18:00	2

## **Authorization**

Radius non può essere configurato per effettuare solo autorizzazione.

Se sono configurati più metodi di autorizzazione, questi sono eseguiti nell'ordine in cui sono stati impostati.


# Accounting



Login Time	Username	Uptime	Bandwidth Up/Down
May/01/2013 03:20:55	Host A	01:22:15	496.2KB / 21MB
Apr/16/2013 12:40:51	Host X	00:30:12	123KB / 1MB



## **AAA Domains**



• Different schemes can be applied to users in different domains.

### **Dominio**

Se il nome utente non contiene un delimitatore (@ | % ) allora si considera facente parte del dominio locale di default: "default". Viene effettuata local authentication.

Sono disponibili due domini di default:

**default** – global default domain for common access users;

**default\_admin** – global default domain for administrators.

utilizzato per gli amministratori che accedono con


HTTP,SSH,TELNET,TERMINAL.

Autenticazione predefinita: locale.

Massimo 32 domini, inclusi i due locali.



# **AAA Local Configuration**



Authentication and authorization can be applied on the AR2200E.



# AAA Local Configuration Verification

[Huawei]display domain name huawei

Domain-name : huawei

Domain-state : Active

Authentication-scheme-name : auth1

Accounting-scheme-name : default

Authorization-scheme-name : auth2

Service-scheme-name : 
RADIUS-server-template : 
HWTACACS-server-template : 
User-group : -

• Local AAA schemes are associated with individual domains.





- Which two AAA schemes are supported when configuring VRP to support the local mode?
- If no domain is defined for users, what action is taken?



# Thank you

www.huawei.com