




```
6
                                 SIMD Multiplication
 Array * Array
  void
  SimdMul(float *a float *b) float *c, int len )
            c[0:len] = a[0:len] * b[0:len];
  Note that the construct:
            a[ 0 : ArraySize ]
  is meant to be read as:
   "The set of elements in the array a starting at index 0 and going for ArraySize elements".
  "The set of elements in the array a starting at index 0 and going through index ArraySize".
  Array * Array
  void
  SimdMul( float *a float *b) float *c, int len )
            #pragma omp simd
            for( int i= 0; i < len; i++ )
                       c[i] = a[i] * b[i];
Computer Graphics
                                                                                       mjb - March 24, 2020
```







### Requirements for a For-Loop to be Vectorized

11

- If there are nested loops, the one to vectorize must be the inner one.
- There can be no jumps or branches. "Masked assignments" (an if-statement-controlled assignment) are OK, e.g.,

- The total number of iterations must be known at runtime when the loop starts
- There can be no inter-loop data dependencies such as:

• It helps performance if the elements have contiguous memory addresses.



mjb - March 24, 2020

#### **Prefetching**

12

Prefetching is used to place a cache line in memory before it is to be used, thus hiding the latency of fetching from off-chip memory.

There are two key issues here:

- 1. Issuing the prefetch at the right time
- 2. Issuing the prefetch at the right distance

### The right time:

If the prefetch is issued too late, then the memory values won't be back when the program wants to use them, and the processor has to wait anyway.

If the prefetch is issued too early, then there is a chance that the prefetched values could be evicted from cache by another need before they can be used.

#### The right distance:

The "prefetch distance" is how far ahead the prefetch memory is than the memory we are using right now.

Too far, and the values sit in cache for too long, and possibly get evicted.


Oreg Uni Too near, and the program is ready for the values before they have arrived.

mjb - March 24, 2020

```
Array Multiplication
Length of Arrays (NUM): 1,000,000
Length per SIMD call (ONETIME): 256

for( int i = 0; i < NUM; i += ONETIME)
{
    __builtin_prefetch ( &A[i+PD], WILL_READ_ONLY, LOCALITY_LOW );
    __builtin_prefetch ( &B[i+PD], WILL_READ_ONLY, LOCALITY_LOW );
    __builtin_prefetch ( &C[i+PD], WILL_READ_AND_WRITE, LOCALITY_LOW );
    SimdMul(A, B, C, ONETIME);
}

Oregon State
University
Computer Graphics
```



# This all sounds great! What is the catch?

15

The catch is that compilers haven't caught up to producing really efficient SIMD code. So, while there are great ways to express the desire for SIMD in code, you won't get the full potential speedup ... yet.

One way to get a better speedup is to use assembly language. Don't worry – *you* wouldn't need to write it.

Here are two assembly functions:

- 1. SimdMul: C[0:len] = A[0:len] \* B[0:len]
- 2. SimdMulSum: return (  $\sum A[ 0:len ] * B[ 0:len ] )$




Warning – due to the nature of how different compilers and systems handle local variables, these two functions only work on *flip* using gcc/g++, without –O3 !!!

mjb - March 24, 2020

```
16
        Getting at the full SIMD power until compilers catch up
           SimdMul(float *a, float *b, float *c, int len)
               int limit = ( len/SSE_WIDTH ) * SSE_WIDTH;
              __asm
(
                    ".att_syntax\n\t"
                    "movq -24(%rbp), %r8\n\t"
                                                     // a
                    "movq -32(%rbp), %rcx\n\t"
                                                     // b
                    "movq -40(%rbp), %rdx\n\t"
                                                     // c
               for( int i = 0; i < limit; i += SSE_WIDTH)
                        ".att_syntax\n\t"
                        "movups (%r8), %xmm0\n\t"
                                                        // load the first sse register
                        "movups (%rcx), %xmm1\n\t"
                                                        // load the second sse register
                        "mulps %xmm1, %xmm0\n\t"
                                                       // do the multiply
                        "movups %xmm0, (%rdx)\n\t" "addq $16, %r8\n\t"
                                                       // store the result
                        "addq $16, %rcx\n\t"
                         "addq $16, %rdx\n\t"
              }
                                                      This only works on flip using gcc/g++,
               for( int i = limit; i < len; i++ )
                                                                     without -O3 !!!
                    c[i] = a[i] * b[i];
University
                                                                                                     mjb - March 24, 202
```

```
Getting at the full SIMD power until compilers catch up
                                                                                                                                                                                                               17
                             SimdMulSum( float *a, float *b, int len )
                                  float sum[4] = { 0., 0., 0., 0. };
int limit = ( len/SSE_WIDTH ) * SSE_WIDTH;
                                         ".att_syntax\n\t"
                                          "movq -40(%rbp), %r8\n\t"
"movq -48(%rbp), %rcx\n\t"
"leaq -32(%rbp), %rdx\n\t"
"movups (%rdx), %xmm2\n\t"
                                                                                            // a
// &sum[0]
// 4 copies of 0. in xmm2
                                   for( int i = 0; i < limit; i += SSE_WIDTH ) {
                                               ".att_syntaxin\ti"
"movups (%/8), %xmm0\in\ti"
"movups (%/cx), %xmm1\in\ti"
mulps %xmm1, %xmm0\in\ti"
"addps %xmm0, %xmm2\in\ti"
"addq $16, %r8\in\ti"
"addq $16, %rcxin\ti"
                                                                                             // load the first sse register
// load the second sse register
// do the multiply
// do the add
                                                                                                         This only works on flip using gcc/g++,
                                                                                                                                     without -O3 !!!
                                          ".att_syntax\n\t"
"movups %xmm2, (%rdx)\n\t"
                                                                                              // copy the sums back to sum[ ]
                                   for( int i = limit; i < len; i++ )
                                         sum[0] += a[ i ] * b[ i ];
                                   return \; sum[0] + sum[1] + sum[2] + sum[3]; \\
University
Computer Graph
                                                                                                                                                                                              mjb - March 24, 2020
```

```
18
                           Combining SIMD with Multicore
  #define NUM_ELEMENTS_PER_CORE
                                             ARRAYSIZE / NUMT
  . . .
  omp set num threads( NUMT );
  maxMegaMultsPerSecond = 0.;
  for( int t = 0; t < NUM_TRIES; t++)
      double time0 = omp_get_wtime();
      #pragma omp parallel
           int first = omp_get_thread_num() * NUM_ELEMENTS_PER_CORE;
           SimdMul( &A[first], &B[first], &C[first], NUM ELEMENTS PER CORE );
      double time1 = omp_get_wtime();
      double megaMultsPerSecond = (float)ARRAYSIZE / ( time1 - time0 ) / 1000000.;
      if( megaMultsPerSecond > maxMegaMultsPerSecond )
           maxMegaMultsPerSecond = megaMultsPerSecond;
Oregon State
University
Computer Graphics
                                                                               mjb - March 24, 2020
```



## **Avoiding Assembly Language: the Intel Intrinsics**

20

Intel has a mechanism to get at the SSE SIMD without resorting to assembly language. These are called *Intrinsics*.


Intrinsic	Meaning
m128	Declaration for a 128 bit 4-float word
_mm_loadu_ps	Load am128 word from memory
_mm_storeu_ps	Store am128 word into memory
_mm_mul_ps	Multiply twom128 words
_mm_add_ps	Add twom128 words




mjb - March 24, 2020

```
21
                          SimdMul using Intel Intrinsics
   #include <xmmintrin.h>
   #define SSE_WIDTH
   SimdMul( float *a, float *b, float *c, int len )
       int limit = ( len/SSE_WIDTH ) * SSE_WIDTH;
       register float *pa = a;
       register float *pb = b;
       register float *pc = c;
       for(int i = 0; i < limit; i += SSE WIDTH)
           pb += SSE_WIDTH;
           pc += SSE_WIDTH;
       for( int i = limit; i < len; i++ )
           c[i] = a[i] * b[i];
 Oregon State
University
Computer Graphics
                                                                                     mjb - March 24, 2020
```

```
22
                                 SimdMulSum using Intel Intrinsics
     SimdMulSum( float *a, float *b, int len )
           float sum[4] = { 0., 0., 0., 0. };
int limit = ( len/SSE_WIDTH ) * SSE_WIDTH;
           register float *pa = a;
           register float *pb = b;
           \begin{tabular}{ll} $\_$m128 ss = $\_$mm_loadu_ps( \&sum[0] ); \\ for( int i = 0; i < limit; i += SSE_WIDTH ) \end{tabular}
                 ss = _mm_add_ps( ss, _mm_mul_ps( _mm_loadu_ps( pa ), _mm_loadu_ps( pb ) ) );
                 pa += SSE_WIDTH;
                 pb += SSE_WIDTH;
           _mm_storeu_ps( &sum[0], ss );
           for( int i = limit; i < len; i++ )
                 sum[0] += a[i] * b[i];
           return sum[0] + sum[1] + sum[2] + sum[3];
     }
Computer Graphics
                                                                                                                     mjb - March 24, 2020
```





# A preview of things to come: OpenCL and CUDA have SIMD Data Types

When we get to OpenCL, we could compute projectile physics like this:

```
float4 pp;  // p'

pp.x = p.x + v.x*DT;

pp.y = p .y + v.y*DT + .5*DT*DT*G.y;

pp.z = p.z + v.z*DT;
```

But, instead, we will do it like this:

```
float4 pp = p + v*DT + .5*DT*DT*G; // p'
```

We do it this way for two reasons:

- 1. Convenience and clean coding
- 2. Some hardware can do multiple arithmetic operations simultaneously



mjb - March 24, 2020

26

25

# A preview of things to come: OpenCL and CUDA have SIMD Data Types

The whole thing will look like this:

```
= (float4) ( 0., -9.8, 0., 0. );
    constant float4 G
    constant float DT
                                = 0.1;
    kernel
    void
    Particle( global float4 * dPobj, global float4 * dVel, global float4 * dCobj )
                int gid = get_global_id( 0 );
                                                          // particle #
                float4 p = dPobj[gid];
                                                           // particle #gid's position
                                                          // particle #gid's velocity
                float4 v = dVel[gid];
               float4 pp = p + v*DT + .5*DT*DT*G;
                                                                                // p'
               float4 vp = v + G*DT;
                                                                                // v'
               dPobj[gid] = pp;
               dVel[gid] = vp;
Oregon State
University
Computer Graphics
```

13