ExpressQuantumGrid SUITE

PROFESSIONAL

Columns & Bands Reference

Copyright © 2000 Developer Express Inc.

Table of Contents

ExpressQuantumGrid and Tree List Columns 10

TreeListColumns

TdxTreeListColumn 11

- **TdxTreeListColumn Properties** 12
- **TdxTreeListColumn Methods** 23
- **TdxTreeListColumn Events** 28

TdxTreeListMaskColumn 31

- **TdxTreeListMaskColumn Properties** 32
- **TdxTreeListMaskColumn Methods** 34
- **TdxTreeListMaskColumn Events** 35

TdxTreeListDropDownColumn 36

- **TdxTreeListDropDownColumn Properties** 37
- **TdxTreeListDropDownColumn Methods** 40
- **TdxTreeListDropDownColumn Events** 41

TdxTreeListButtonColumn 42

- **TdxTreeListButtonColumn Properties** 43
- **TdxTreeListButtonColumn Methods** 46
- **TdxTreeListButtonColumn Events** 46

TdxTreeListCheckColumn 47

- **TdxTreeListCheckColumn Properties** 48
- **TdxTreeListCheckColumn Methods** 51
- **TdxTreeListCheckColumn Events** 52

TdxTreeListCurrencyColumn 53

- **TdxTreeListCurrencyColumn Properties** 54

Copyright © 2000 Developer Express Inc.

TdxTreeListCurrencyColumn Methods 56

TdxTreeListCurrencyColumn Events 56

TdxTreeListHyperLinkColumn 57

TdxTreeListHyperLinkColumn Properties 58

TdxTreeListHyperLinkColumn Methods 60

TdxTreeListHyperLinkColumn Events 61

TdxTreeListMemoColumn 62

TdxTreeListMemoColumn Properties 63

TdxTreeListMemoColumn Methods 66

TdxTreeListMemoColumn Events 66

TdxTreeListSpinColumn 67

TdxTreeListSpinColumn Properties 68

TdxTreeListSpinColumn Methods 71

TdxTreeListSpinColumn Events 71

TdxTreeListTimeColumn 72

TdxTreeListTimeColumn Properties 73

TdxTreeListTimeColumn Methods 75

TdxTreeListTimeColumn Events 75

TdxTreeListCalcColumn 76

TdxTreeListCalcColumn Properties 77

TdxTreeListCalcColumn Methods 79

TdxTreeListCalcColumn Events 79

TdxTreeListDateColumn 80

TdxTreeListDateColumn Properties 81

TdxTreeListDateColumn Methods 84

TdxTreeListDateColumn Events 84

TdxTreeListImageColumn 86

TdxTreeListImageColumn Properties 87

TdxTreeListImageColumn Methods 91

TdxTreeListImageColumn Events 93

TdxTreeListPickColumn 94

TdxTreeListPickColumn Properties 95

TdxTreeListPickColumn Methods 97

TdxTreeListPickColumn Events 97

TdxTreeListPopupColumn 98

TdxTreeListPopupColumn Properties 99

TdxTreeListPopupColumn Methods 103

TdxTreeListPopupColumn Events 104

TdxTreeListGraphicColumn 106

TdxTreeListGraphicColumn Properties 107

TdxTreeListGraphicColumn Methods 111

TdxTreeListGraphicColumn Events 112

TdxTreeListMRUColumn 114

TdxTreeListMRUColumn Properties 115

TdxTreeListMRUColumn Methods 117

TdxTreeListMRUColumn Events 118

TdxTreeListBlobColumn 119

TdxTreeListBlobColumn Properties 120

TdxTreeListBlobColumn Methods 129

TdxTreeListBlobColumn Events 130

TdxTreeListWrapperColumn 131

TdxTreeListWrapperColumn Properties 132

TdxTreeListWrapperColumn Methods 132

TdxTreeListWrapperColumn Events 133

Copyright © 2000 Developer Express Inc.

Grid Columns

TdxDBGridColumn 134

TdxDBTreeListColumn 135

- **TdxDBTreeListColumn Properties** 136
- **TdxDBTreeListColumn Methods** 145
- **TdxDBTreeListColumn Events** 149

TdxDBGridMaskColumn 153

TdxDBTreeListMaskColumn 154

- **TdxDBTreeListMaskColumn Properties** 155
- **TdxDBTreeListMaskColumn Methods** 156
- **TdxDBTreeListMaskColumn Events** 157

TdxDBGridBlobColumn 158

TdxDBTreeListBlobColumn 160

- **TdxDBTreeListBlobColumn Properties** 161
- **TdxDBTreeListBlobColumn Methods** 169
- **TdxDBTreeListBlobColumn Events** 170

TdxDBGridButtonColumn 172

TdxDBTreeListButtonColumn 173

- **TdxDBTreeListButtonColumn Properties** 174
- **TdxDBTreeListButtonColumn Methods** 178
- **TdxDBTreeListButtonColumn Events** 179

TdxDBGridCalcColumn 180

TdxDBTreeListCalcColumn 181

- **TdxDBTreeListCalcColumn Properties** 182
- **TdxDBTreeListCalcColumn Methods** 185
- **TdxDBTreeListCalcColumn Events** 186

TdxDBGridCheckColumn 187

TdxDBGridCheckColumn Properties 188
TdxDBGridCheckColumn Methods 190
TdxDBGridCheckColumn Events 191
TdxDBTreeListCheckColumn 192
TdxDBTreeListCheckColumn Properties 193
TdxDBTreeListCheckColumn Methods 197
TdxDBTreeListCheckColumn Events 199
TdxDBGridCurrencyColumn 200
TdxDBTreeListCurrencyColumn 201
TdxDBTreeListCurrencyColumn Properties 202
TdxDBTreeListCurrencyColumn Methods 205
TdxDBTreeListCurrencyColumn Events 206
TdxDBGridDateColumn 207
TdxDBTreeListDateColumn 208
TdxDBTreeListDateColumn Properties 209
TdxDBTreeListDateColumn Methods 212
TdxDBTreeListDateColumn Events 213
TdxDBGridDropDownColumn 214
TdxDBTreeListDropDownColumn 215
TdxDBTreeListDropDownColumn Properties 216
TdxDBTreeListDropDownColumn Methods 220
TdxDBTreeListDropDownColumn Events 221
TdxDBGridHyperLinkColumn 222
TdxDBTreeListHyperLinkColumn 223
TdxDBTreeListHyperLinkColumn Properties 224
TdxDBTreeListHyperLinkColumn Methods 226
TdxDBTreeListHyperLinkColumn Events 227

Copyright © 2000 Developer Express Inc.

TdxDBGridImageColumn **228**

TdxDBTreeListImageColumn **229**

TdxDBTreeListImageColumn Properties **230**

TdxDBTreeListImageColumn Methods **234**

TdxDBTreeListImageColumn Events **236**

TdxDBGridLookupColumn **238**

TdxDBTreeListLookupColumn **239**

TdxDBTreeListLookupColumn Properties **240**

TdxDBTreeListLookupColumn Methods **243**

TdxDBTreeListLookupColumn Events **244**

TdxDBGridPickColumn **245**

TdxDBTreeListPickColumn **246**

TdxDBTreeListPickColumn Properties **247**

TdxDBTreeListPickColumn Methods **250**

TdxDBTreeListPickColumn Events **251**

TdxDBGridSpinColumn **252**

TdxDBTreeListSpinColumn **253**

TdxDBTreeListSpinColumn Properties **254**

TdxDBTreeListSpinColumn Methods **257**

TdxDBTreeListSpinColumn Events **258**

TdxDBGridTimeColumn **259**

TdxDBTreeListTimeColumn **260**

TdxDBTreeListTimeColumn Properties **261**

TdxDBTreeListTimeColumn Methods **263**

TdxDBTreeListTimeColumn Events **263**

TdxDBGridMemoColumn **264**

TdxDBTreeListMemoColumn **266**

TdxDBTreeListMemoColumn Properties **267**

TdxDBTreeListMemoColumn Methods **270**

TdxDBTreeListMemoColumn Events **270**

TdxDBGridGraphicColumn **271**

TdxDBTreeListGraphicColumn **272**

TdxDBTreeListGraphicColumn Properties **273**

TdxDBTreeListGraphicColumn Methods **277**

TdxDBTreeListGraphicColumn Events **278**

TdxDBGridPopupColumn **280**

TdxDBTreeListPopupColumn **281**

TdxDBTreeListPopupColumn Properties **282**

TdxDBTreeListPopupColumn Methods **286**

TdxDBTreeListPopupColumn Events **287**

TdxDBGridExtLookupColumn **289**

TdxDBTreeListExtLookupColumn **290**

TdxDBTreeListExtLookupColumn Properties **291**

TdxDBTreeListExtLookupColumn Methods **293**

TdxDBTreeListExtLookupColumn Events **293**

TdxDBGridMRUColumn **294**

TdxDBTreeListMRUColumn **295**

TdxDBTreeListMRUColumn Properties **296**

TdxDBTreeListMRUColumn Methods **298**

TdxDBTreeListMRUColumn Events **299**

TdxDBGridWrapperColumn **300**

TdxDBTreeListWrapperColumn **301**

TdxDBTreeListWrapperColumn Properties **302**

TdxDBTreeListWrapperColumn Methods **303**

Copyright © 2000 Developer Express Inc.

TdxDBTreeListWrapperColumn Events **304**

Bands

TdxTreeListBand **305**

TdxTreeListBand Properties **307**

TdxTreeListBand Methods **312**

TdxTreeListBands **313**

TdxTreeListBands Properties **314**

TdxTreeListBands Methods **316**

Index **318**

ExpressQuantumGrid and ExpressTreeList/DBTreeList Columns

The ExpressQuantumGrid and ExpressTreeList/DBTreeList include a number of columns that can be used to display and modify data of almost any type in grid/tree list cells:

GridColumn	Simple text field.
ButtonColumn	Cells include command buttons.
MaskColumn	Mask edit field.
DateColumn	Date edit field.
TimeColumn	Time edit field.
CheckColumn	Checkbox edit field.
ImageColumn	Image Pick List edit field.
PickColumn	Pick List edit field.
SpinColumn	Spin (Up-Down) edit field.
LookupColumn	Database Lookup edit field.
CalcColumn	Calculator edit field.
BlobColumn	Blob dropdown edit field (Memo and Graphic)
CurrencyColumn	Currency edit field.
HyperLink	Internet Hyperlink edit field.
MemoColumn	Memo edit field.
GraphicColumn	Graphic edit field.
PopupColumn	Complex form popup field.
ExtLookupColumn	Extended database lookup field.
MRUColumn	Most recently used items edit field.
WrapperColumn	Different types edit field.

Note: *The ExpressTreeList supports all columns listed above, except for the Lookup, ExtLookup and Graphic columns.*

Copyright © 2000 Developer Express Inc.

TreeList Columns

TdxTreeListColumn

TdxTreeListNode is a base class for nodes of TdxTreeList and TdxTreeGrid controls.

Unit

dxTL

```
TdxTreeListColumn = class(TComponent);
```

Description

The set of tree list columns is managed by the TdxTreeListColumns object. The TdxTreeListColumn class defines a given column in a tree list. Use these method and properties to customize the appearance of a given column. You can access a given column via its index in the TdxTreeListColumns object.

Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn Properties

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Alignment property — read / write

Specifies the manner in which text is aligned within a list column.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
property Alignment : TAlignment;
```

Description

Use Alignment to specify the horizontal placement of text within a column. A column's text can be aligned either to the right or left or centered. Following values are available:

taLeftJustify	Alignment to the left of a column.
taRightJustify	Alignment to the right.
taCenter	Text is centered within a column.

Note: *This property does not effect column headers.*

See Also

TdxTreeListColumn.DefaultAlignment

AssignedValues property — read only

Indicates which properties have been assigned to a tree list column.

```
type
```

```
  TdxColumnValue = (cvAlignment, cvCaption, cvReadOnly, cvWidth);
TdxColumnValues = set of TdxColumnValue;
property AssignedValues : TdxColumnValues;
```

Description

TColumnValues type defines a set of possible state flags for the AssignedValues property. The component uses assigned values except for default values when showing a column. The following table lists possible values for TColumnValues and the meaning of each flag:

cvAlignment	The Alignment property has been assigned.
cvCaption	The Caption property has been assigned.
cvReadOnly	The ReadOnly property has been assigned.
cvWidth	The Width property has been assigned.

BandIndex property — read / write

Specifies band index.

```
property BandIndex: Integer;
```

Description

Set the BandIndex property to change a band to which a column belongs. If BandIndex is –1, the column doesn't belong to any band and is not displayed within the control.

See Also

TdxTreeListColumn.ColIndex; TdxTreeListColumn.RowIndex

Caption property — read / write

Determines the caption of a tree list column.

```
property Caption : String;
```

Description

Specifies the text that appears at the top of a column. Use Caption to label the type of item that appears within a column.

See Also

TdxTreeListColumn.DefaultCaption

CharCase property — read / write

Specifies text case within a column.

```
property CharCase: TEditCharCase;
```

Description

The possible values of CharCase include:

Value	Meaning
ecLowerCase	Text is converted to lowercase.
ecNormal	Text is unaltered.
ecUpperCase	Text is converted to UPPERCASE.

When the CharCase property is set to **ecLowerCase** or **ecUpperCase**, character case is converted when a user types them into an in-place editor. Setting the CharCase property to **ecLowerCase** or **ecUpperCase** changes the actual contents of the text, not just its appearance. All case information is lost and cannot be recaptured by changing CharCase to **ecNormal**.

By default, the CharCase property for TdxTreeListColumn is set to **ecNormal**.

ColIndex property — read / write

Specifies the column index of a column's object in a band.

```
property ColIndex: Integer;
```

Description

Use the ColIndex property to change the horizontal position of a column within a band. If ColIndex is 0, the column is the first in the band row.



Note: *ColIndex does not affect invisible columns. When you make a column visible, it always appears as the last column in a band.*

See Also

TdxTreeListBand.HeaderColCount; TdxTreeListColumn.BandIndex; TdxTreeListColumn.RowIndex; TdxTreeListColumn.Index

Copyright © 2000 Developer Express Inc.

Color property read / write

Specifies the background color for a column.

```
property Color : TColor;
```

Description

The Color property determines the background color of a given column. You can set Color to one of the constants defined in the Graphics unit (such as clBlue), or to an explicit RGB integer value.

DisableCaption property read / write

Determines whether to display column caption.

```
property DisableCaption : Boolean;
```

Description

Use this property to specify whether to display column caption. If DisableCaption is True, a column's caption is hidden.

See Also

TdxTreeListColumn.Caption; TdxTreeListColumn.HeaderGlyph

DisableCustomizing property read / write

Determines whether a column can be hidden at runtime.

```
property DisableCustomizing  :Boolean;
```

Description

By default, a user can hide a column at runtime. If DisableCustomizing is True, column hiding is unavailable and the column does not appear in the customization tool window when hidden.

If you wish to create a column, which is invisible to users, you should set the column's Visible property to **False** and the DisableCustomizing property to **True**.

See Also

TCustomdxTreeList.CustomizingForm; TCustomdxTreeList.ColumnsCustomizing

DisableDragging property read / write

Determines whether a user can drag a column.

```
property DisableDragging: Boolean;
```

Description

Set the DisableDragging property to True to disable column drag & drop operations.

DisableEditor property read / write

Determines whether a column's data can be edited.

```
property DisableEditor : Boolean;
```

Description

If True, the inplace editor is inactive for a given column.

See Also

TCustomdxTreeList.InplaceEditor

DisableFilter property read / write

Specifies whether the filtering feature is enabled for a specific column.

```
property DisableFilter: Boolean;
```

Description

If the DisableFilter property is set to **True**, a filter is not applied to a column.

The default value is **False**.

Font property read / write

Specifies the font by which a column displays its data.

```
property Font : TFont;
```

Description

The Font property points to a TFont object that determines typographic attributes of text displayed in a column.

See Also

TCustomdxTreeListControl.OnCustomDrawCell

HeaderAlignment property read / write

Specifies header caption alignment.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
property HeaderAlignment : TAlignment;
```

Description

Use Alignment to specify the horizontal placement of a caption within a column header. A column's caption can be aligned either to the right or left or centered. The following values are available:

taLeftJustify	Alignment to the left of a header.
taRightJustify	Alignment to the right.
taCenter	Text is centered within a header.

The default value is taCenter.

See Also

TdxTreeListColumn.Caption

HeaderGlyph property — read / write

Specifies the bitmap drawn on a column header.

```
property HeaderGlyph : TBitmap;
```

Description

Use this property to specify the bitmap that appears on a column's header. Use the Open dialog box that appears in the Object Inspector to choose a bitmap file (with a .BMP extension) or specify a bitmap file at runtime.

HeaderMaxLineCount property — read / write

Specifies the maximum line count of a column.

```
property HeaderMaxLineCount: Integer;
```

Description

Use HeaderMaxLineCount to specify the column line count. If HeaderMaxLineCount is 0, a column uses the maximum allowed space.

Index property — read / write

Determines the index of a column within tree list columns.

```
property Index : integer;
```

Description

The Index property determines the index of a given column in the Columns property of a tree list to which the column belongs. The index of the first column in the tree list Columns property is 0.

See Also

TCustomdxTreeListControl.Columns; TdxTreeListColumn.TreeList; TCustomdxTreeList.GetFocusedVisibleIndex

MaxLength property — read / write

Determines the maximum number of characters a user can enter within a cell editor.

```
property MaxLength: Integer;
```

Description

Use the MaxLength property to limit the number of characters that can be entered within a cell editor. A value of 0 indicates that there is no defined limit on length. By default, the MaxLength property for TdxTreeListColumn is set to 0. This property is in effect only for text columns. For instance, it does not affect check box columns.

***Note**: When the MaxLength property is 0, there may be limitations imposed by the operating system on the number of characters that may be entered into the in-place editor.*

MinWidth property — read / write

Specifies minimum column width.

```
property MinWidth : Integer;
```

Description

Use MinWidth to get or set minimum column width. A column cannot have width less than the MinWidth property.

See Also

TdxTreeListColumn.Width

PasswordChar property — read / write

Indicates the character, if any, to display instead of the actual characters typed within a cell.

```
property PasswordChar: Char;
```

Description

The PasswordChar property is used to display a specific character instead of the entered text within a cell. If the PasswordChar property is set to a null character (ANSI character zero), normal text is displayed. If PasswordChar is set to any other character, the cell displays PasswordChar instead of each entered character. By default, the PasswordChar property for TdxTreeListColumn is set to a null character.

***Note**: This property is in effect only for text columns. For instance, it does not affect check box columns.*

ReadOnly property — read / write

Specifies whether data within a column can be edited.

```
property ReadOnly : Boolean;
```

Description

Use this property to avoid data modification within a column. If ReadOnly is True, column data cannot be changed. Set ReadOnly to False to enable data modification.

Copyright © 2000 Developer Express Inc.

See Also

TdxTreeListColumn.DefaultReadOnly

RowIndex property — read / write

Specifies the row index of a column's object in a band.

```
property RowIndex: Integer;
```

Description

Use the RowIndex property to specify the row index of a column header and column cells in a band. The first row has index 0. The maximum number of rows in a band is determined by the HeaderPanelRowCount property.



See Also

TdxTreeListColumn.ColIndex; TCustomdxTreeListControl.HeaderPanelRowCount; TdxTreeListBand.HeaderRowCount

Sizing property — read / write

Determines whether it is possible to change column width.

```
property Sizing : Boolean;
```

Description

By default, Sizing is True and a user can change column width. Set Sizing to False to avoid column resizing.

Sorted property — read / write

Specifies whether a node is sorted by the column value.

```
type
  TdxTreeListColumnSort = (csNone, csDown, csUp);
property Sorted : TdxTreeListColumnSort;
```

Description

If the Sorted property of a column is csUp, nodes are sorted in ascending order, if Sorted is csDown - in descending order. The csNone value specifies unsorted nodes. You should include aoAutoSort (for TdxTreeList) or egoAutoSort (for TdxDBGrid) flags in the tree list Options property to allow the nodes be sorted by a component. Otherwise, your program must sort manually.

SortedOrder property — read / write

Determines the index of a column in a sorted columns array.

```
property SortedOrder: Integer;
```

Description

The ExpressQuantumGrid/TreeList provide multiple sorting of records in a grid (tree list) control, that is, several columns at a time can be marked as sorted. Once records in a grid (tree list) control are sorted by a column, the column is added to the array of sorted columns. The SortedOrder property is used internally to determine the index of a column in the sorted columns array. Records are first sorted by a column with the 0 index, then by a column with the 1 index, etc.

See Also

TCustomdxTreeListControl.SortedColumns; TCustomdxTreeListControl.SortedColumnsCount; TdxTreeListColumn.Sorted; TdxTreeListColumn.StoredRowIndex

StoredRowIndex property — read / write

```
property StoredRowIndex: Integer;
```

Description

Columns within bands may be placed on several rows (one under another). This property stores the index of a row in which a column is located. If the height of a header area reduces the first row, then all columns are arranged in one row. If the header area height increases, columns occupy the row specified by the StoredRowIndex property.

If the aoAutoHeaderPanelHeight option is active (aoAutoHeaderPanelHeight for the ExpressQuantumGrid), the header area height is set to the maximum value of the given property in all ExpressQuantumGrid/ExpressTreeList columns.

See Also

TCustomdxTreeListControl.SortedColumns; TCustomdxTreeListControl.SortedColumnsCount; TdxTreeListColumn.Sorted; TdxTreeListColumn.SortedOrder

TabStop property — read / write

Determines whether to allow access to a column's cells from the keyboard.

```
property TabStop: Boolean;
```

Copyright © 2000 Developer Express Inc.

Description

Set the TabStop property to False to disallow access a column's cells from the keyboard. The default value is True.

TreeList property read / write

Returns the tree list control to which a given column belongs.

```
property TreeList : TCustomdxTreeListControl;
```

Description

Use the TreeList property to access the tree list control (TdxTreeList or TdxDBGrid) to which a particular column belongs.

See Also

TdxTreeList; TdxDBGrid

VertAlignment property read / write

Specifies the vertical placement of text within a cell.

```
type
 TTextLayout = (tlTop, tlCenter, tlBottom);
property VertAlignment: TTextLayout;
```

Description

Use the VertAlignment property to specify the manner in which text is placed within a cell. The VertAlignment property is the vertical analog of the Alignment property. Possible values include:

Value	Meaning	Example
tlTop	Text is displayed at the top of a cell.	
tlCenter	Text is vertically centered within a cell.	

tlBottom Text is displayed along the bottom of a cell.



The default value is **tlTop**.

Visible property read / write

Determines whether a column is visible.

```
property Visible : Boolean;
```

Description

Use this property to get or set the visibility of a column. If the Visible property is False, a column is hidden. Change the Visible property to True to display it.

Width property read / write

Specifies column width.

```
property Width : Integer;
```

Description

Use this property to get or set the width of a given tree list column. The column width cannot be less than the MinWidth property. If you specify a Width value less than that of MinWidth, Width is automatically enlarged.

See Also

TdxTreeListColumn.DefaultWidth; TdxTreeListColumn.MinWidth

Copyright © 2000 Developer Express Inc.

TdxTreeListColumn Methods

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayText	**protected**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		
Destroy	**public**		

Assign method

Copies the contents of one object to another.

```
procedure Assign(Source: TPersistent);  override;
```

Description

Call Assign to copy properties of a column to another column. The standard form of a call to Assign is

```
Destination.Assign(Source);
```

...which tells Destination to copy the contents of Source to itself.

Create method

Creates an instance of type TdxTreeListColumn.

```
constructor TdxTreeListColumn.Create(AOwner: TComponent); override;
```

Description

Creates and initializes the TdxTreeListColumn object. The AOwner parameter specifies a form, to which the tree list column belongs.

DefaultAlignment method

Returns the default aligment for a column.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
function DefaultAlignment: TAlignment;  virtual;
```

Description

The default alignment for TdxTreeListColumn is taLeftJustify.

See Also

TdxTreeListColumn.Alignment

DefaultCaption method

Returns the default caption for TdxTreeListColumn.

```
function DefaultCaption: String;  virtual;
```

Description

The default caption for TdxTreeListColumn is an empty string. Set text to the Caption property to identify a column to a user.

See Also

TdxTreeListColumn.Caption

DefaultColor method

Returns the default color of a column.

```
function DefaultColor: TColor;
```

Description

Call the DefaultColor function to get the default color of a column.

See Also

TdxTreeListColumn.DefaultFont

DefaultFont method

Returns the default font of a column.

```
function DefaultFont: TFont;
```

Description

Call this function to get the default font of a column.

See Also

TdxTreeListColumn.DefaultColor

DefaultReadOnly method

Returns the default value for the ReadOnly property.

```
function DefaultReadOnly: Boolean;  virtual;
```

Copyright © 2000 Developer Express Inc.

Description

The default value for the TdxTreeListColumn object is False.

See Also

TdxTreeListColumn.ReadOnly

DefaultWidth method

Returns the default width for a column on screen.

```
function DefaultWidth: Integer;  virtual;
```

Description

Returns the default width of TdxTreeListColumn in pixels. If TdxTreeListColumn does not belong to any TdxTreeList object, the method returns 100. Else, the default width is defined by the Caption length calculated in accordance with the current device context.

See Also

TdxTreeListColumn.Width

Destroy method

Destroys an instance of TdxTreeLsitColumn and frees its memory.

```
destructor Destroy;  override;
```

Description

Before calling the inherited method, the Destroy procedure removes values, corresponding to a column from the TdxTreeListNode object.

GetBestFit method

Returns the width of a column used by the ApplyBestFit method for better column layout.

```
function GetBestFit(ACanvas: TCanvas; const AText: String): Integer;
virtual;
```

Description

Descendants override this method to specify proper column width used in the ApplyBestFit method. ACanvas specifies the drawing canvas for a column. The AText string is the column caption.

See Also

TCustomdxTreeListControl.ApplyBestFit

GetDisplayText method

Returns the displayed text for a column.

```
function GetDisplayText(Node: TdxTreeListNode string; virtual;
```

Description

Use this method to get the displayed text for a column. The *Node* parameter determines a node to which the column belongs.

Descendants override this method to specify the text that appears within a particular node.

GetDisplayValue method

Returns the displayed value for a specified column.

```
function GetDisplayValue(Node: TdxTreeListNode; AbsoluteIndex: Integer):
string;
```

Description

Use this method to get the displayed value for a column. The Node parameter determines a node to which the column belongs. AbsoluteIndex is the index of the column among other columns of the tree list (see the TCustomdxTreeListControl Columns property).

GetParentComponent method

Returns the parent component for a given column.

```
function GetParentComponent: TComponent;  override;
```

Description

Returns a tree list to which a column belongs.

HasParent

Indicates whether a component has a parent to handle its filing.

```
function HasParent: Boolean;  override;
```

Description

This method overrides the TComponent HasParent method. HasParent is introduced in a TComponent class for the streaming system that loads and saves components. If the return value is True, then some other object (a parent) is responsible for writing a column to a stream. The HasParent method of TdxDBTreeListColumn returns True.

RestoreDefaults method

Removes all settings of the TdxTreeListColumn property made by a user or in program code.

```
procedure RestoreDefaults; virtual;
```

Description

Resets all TdxTreeListColumn properties to default values. Call this method to give a column the default look.

Copyright © 2000 Developer Express Inc.

RestoreDefaultWidth method

Restores default column width.

```
procedure RestoreDefaultWidth;
```

Description

This method resets column width to its default state.

TdxTreeListColumn Events

OnChanged	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnChange event

Occurs when changing the contents of a specific column cell.

```
type
  TNotifyEvent = procedure (Sender: TObject) of object;
property OnChange: TNotifyEvent;
```

Description

Write an OnChange event handler to perform specific actions when making changes within a specific cell.

OnCustomDrawCell event

Occurs when a column cell needs to be repainted.

```
type
  TdxTLCustomDrawCell = procedure(Sender: TObject; ACanvas: TCanvas; ARect:
TRect; ANode: TdxTreeListNode; AColumn: TdxTreeListColumn; ASelected,
AFocused, ANewItemRow: Boolean; var AText: string; var AColor: TColor;
AFont: TFont; var AAlignment: TAlignment; var ADone: Boolean) of object;
property OnCustomDrawCell: TdxTLCustomDrawCell;
```

Description

Write an OnCustomDrawCell event handler to draw the contents of all or particular cells in a tree list control. Draw the column using TCanvas methods. The ARect parameter indicates location of a cell on the canvas:

ANode and **AColumn**	Node and column of a cell.
AText	Context of a cell, you are able to change it.
AFont and **AColor**	Font and color used to draw a cell, you are able to change it.
Alignment	Specifies Text alignment in a cell.
Aselected	Determines whether a node to which a cell belongs is selected.
Afocused	Specifies whether a node to which a cell belongs is focused.
AnewItemRow	Specifies whether a node is a new row item node.
ADone	Determines whether the OnCustomDraw event handler draws the entire cell. Setting ADone to True means that the event handler performs entire drawing and the default procedure is not called.

Copyright © 2000 Developer Express Inc.

Note: *Changes from ExpressGrid v1: The OnCustomDraw event is now obsolete, instead use the OnCustomDrawCell event.*

See Also

TdxTreeListColumn.OnCustomDrawColumnHeader

OnCustomDrawColumnHeader event

Occurs when a column header needs to be repainted.

```
type
  TdxTLCustomDrawHeader = procedure(Sender: TObject; AColumn:
TdxTreeListColumn; ACanvas: TCanvas; ARect: TRect; var AText: string; var
AColor: TColor; AFont: TFont; var AAlignment: TAlignment; var ASorted:
TdxTreeListColumnSort; var ADone: Boolean) of object;
property OnCustomDrawColumnHeader: TdxTLCustomDrawHeader;
```

Description

Write an OnCustomDrawColumnHeader event handler to draw the contents of a header in a treelist control. Draw a column using the TCanvas method. The ARect parameter indicates location of a header on the canvas:

AColumn	Column object
AText	Header caption. You are able to change it.
AFont and **AColor**	Font and color are used to draw a header. You are able to change it.
AAlignment	Caption alignment.
ASorted	Specifies whether the sort arrow is drawn. You are able to change it.
ADone	Determines whether the OnCustomDraw event handler draws the entire header. Setting ADone to True means that the event handler performs entire drawing and the default procedure is not called.

See Also

TdxTreeListColumn.OnCustomDrawCell

OnCustomDrawColumnHeader event

Occurs when a user confirms data input (by pressing the Enter key, for instance) within a specific column.

```
type
  TdxEditValidateEvent = procedure (Sender: TObject; var ErrorText: string;
var Accept: Boolean) of object;
property OnValidate: TdxEditValidateEvent;
```

Description

Write an OnValidate event handler to validate data changes made within a cell of a specific column before the data is posted. Said differently, this event occurs when a user confirms data input by

pressing the Enter key within a cell or the OK button within a dropdown window. The OnValidate event allows an application to entirely validate data. The Sender parameter determines the column whose cell is being processed. The ErrorText parameter specifies the text displayed when an exception arises. The Accept parameter specifies whether to accept or cancel the changes. If data is accepted, the Accept parameter is **True**. Otherwise; it's **False**.

Copyright © 2000 Developer Express Inc.

TdxTreeListMaskColumn

Unit

dxTL

```
TdxTreeListMaskColumn = class(TdxTreeListColumn)
```

Description

TdxTreeListMaskColumn uses a mask to format data when modifing data in tree list cells. Characters that do not match the mask are ignored.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListMaskColumn

TdxTreeListMaskColumn Properties

TdxTreeListMaskColumn

EditMask	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

EditMask property — read / write

Determines a mask used to format text in TdxTreeListMaskColumn.

```
property EditMask: string;
```

Description

EditMask is a mask that formats text within a TdxTreeListMaskColumn. Use the mask to validate characters entered in a cell. TdxTreeListMaskColumn ignores all characters that do not match the mask.

The mask consists of three parts devided by a semicolon:

1. The mask itself.

2. A character that determines whether the mask is saved as a part of data. Any non-zero value indicates that mask characters will be saved as a part of the edited data. The 0 value indicates that mask symbols will be excluded from the edited data.

3. A symbol that represents blank characters (characters that have not been entered).

A table below describes specific mask characters. Characters that are not included in this table can appear in the mask as literal characters.

Characters	Description
>	All subsequent characters entered are converted to UPPER case.
<	All subsequent characters are converted to lower case.
<>	If the mask includes these two characters, no case formatting is applied to the subsequent charactersentered .
\	Use this symbol to represent special mask characters as literal characters in the mask.
L	Requires any literal character, e.g. A-Z, a-z.
l	Permits any literal character (e.g. A-Z, a-z), but does not require it.
A	Requires any alphanumeric character, e.g. 0-9, A-Z, a-z.
a	Permits any alphanumeric character (e.g. 0-9, A-Z, a-z), but does not require it.
C	Requires any character.
c	Permits any character, but does not require it.
0	Requires a numeric value (0-9).
9	Permits a numeric value (0-9), but does not require it.
#	Permits a numeric value (0-9) or plus or minus signs, but does not require it.
/	Use this character to separate months, days and years in dates. The character that actually appears as the date separator is determined by Regional Settings in Windows.
:	Use this character to separate hours, minutes and seconds in time-formatted data. The character that actually appears as the time separator is determined by Regional Settings in Windows.
;	Separates the three fields of the mask.
_	Inserts spaces in text.

TdxTreeListMaskColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

Copyright © 2000 Developer Express Inc.

TdxTreeListMaskColumn Events

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxTreeListDropDownColumn

TdxTreeListDropDownColumn is an abstract tree list column with a dropdown window.

Unit

dxTLClms

```
TdxTreeListDropDownColumn = class(TdxTreeListColumn);
```

Description

TdxTreeListDropDownColumn provides methods and properties for columns with a custom dropdown window. These columns look like a combo box, when focused.

TdxTreeListDropDownColumn is the base class for TdxTreeListCalcColumn, TdxTreeListImageColumn, TdxTreeListlookupColumn, TdxTreeListPickColumn, TdxTreeListDateColumn, and TdxTreeListBlobColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListDropDownColumn Properties

TdxTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**protected / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

ButtonGlyph property — read / write

Determines button glyph.

```
property ButtonGlyph: TBitmap;
```

Description

Determines the glyph used for the button within a cell.

DropDownRows property — read / write

Determines the total number of rows within a dropdown window.

```
property DropDownRows: Cardinal;
```

Description

Use this property to set the number of visible rows within a dropdown window. If DropDowRows is less than the total number of items to drop down, a verticall scroolbar appears to the right of a dropdown window. The default value for DropDownRows is 7.

DropDownWidth property read / write

Specifies the width of a dropdown window.

```
property DropDownWidth: Integer;
```

Description

Specifies the width of the dropdown window in pixels. The default value of this property for TdxTreeListDropDownColumn is 0.

ImmediateDropDown property read / write

Determines whether a dropdown list is automatically displayed when a user types text within an edited cell.

```
property ImmediateDropDown : Boolean;
```

Description

If this property is True, the dropdown window is automatically displayed if the entered text matches one of the dropdown list items. Otherwise, the dropdown list is not displayed until a user presses the edit button (a button, which activates the dropdown window).

ImmediatePopup property read / write

Determines whether a dropdown window is immediately displayed after a mouse click event.

```
property ImmediatePopup: Boolean;
```

Description

If the ImmediatePopup property is set to **False**, a single mouse click within the cell region activates a dropdown window.

The default value is **False**.

PopupAlignment property read / write

Specifies the manner in which a dropdown window is aligned relative to a cell.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
property PopupAlignment: TAlignment;
```

Description

Use the Alignment property to specify the horizontal placement of a dropdown window relative to a specific cell. It can be aligned either to the right, left, or centered.

Copyright © 2000 Developer Express Inc.

Value	Meaning
taLeftJustify	The dropdown window is aligned to the left.
taCenter	The dropdown window is centered relative to a cell.
taRightJustify	The dropdown window is aligned to the right.

The default value is **taLeftJustify**.

PopupBorder property — read / write

Defines the border style for a dropdown window.

```
type
  TdxPopupBorder = (pbDefault, pbSingle, pbFrame3D);
property PopupBorder: TdxPopupBorder;
```

Description

Use this property to specify one of the following dropdown window border styles:

Value	Meaning
pbDefault	Default border for a dropdown window.
pbSingle	Dropdown window with a single line border.
pbFrame3D	Dropdown window with a 3D appearance.

ShowButtonStyle — read / write

Determines appearance of the edit button.

```
type
  TdxShowButtonStyle = (sbDefault, sbAlways, sbNone);
property ShowButtonStyle: TdxShowButtonStyle;
```

Description

Use this property to determine appearance of the edit button.

Value	Meaning
sbDefault	Edit button is displayed only for the currently focused column.
sbAlways	Edit button is visible for all columns of a current node, not just those with current focus.
sbNone	Edit button is invisible. Doube-click activates a dropdown window.

See Also

TdxTreeListDropDownColumn.IsShowButton

TdxTreeListDropDownColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

Copyright © 2000 Developer Express Inc.

TdxTreeListDropDownColumn Events

TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnEditButtonClick

Occurs when clicking an editor button.

```
type
  TNotifyEvent = procedure(Sender: TObject) of object;
property OnEditButtonClick: TNotifyEvent;
```

Description

TdxTreeListDropDownColumn is an ancestor for all columns which use a dropdown window as an inplace editor. In order to activate this inplace editor you must click the editor button pictured below. The OnEditButtonClick event occurs when a user clicks this button. You can write an OnEditButtonClick event handler to perform actions when a user clicks this button.



See Also

TdxTreeListDropDownColumn.EditButtonClick

TdxTreeListButtonColumn

TdxTreeListButtonColumn represents a column with a custom button.

Unit

dxTLClms

```
TdxTreeListButtonColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListButtonColumn represents a column with a custom button. Use the EditButtonStyle property to customize a button's look. TdxTreeListButtonColumn uses the TdxInplaceTreeListButtonEdit inplace editor for data editing.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListButtonColumn Properties

TdxTreeListButtonColumn

ButtonOnly	**published / read / write**	Glyph	**published / read / write**
Buttons	**published / read / write**	HideEditCursor	**published / read / write**
EditButtonStyle	**published / read / write**		
ClickKey	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
CharCase	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

ButtonOnly property — read / write

Specifies the TdxTreeListButtonColumn style.

```
property ButtonOnly : Boolean;
```

Description

Generally, TdxTreeListButtonColumn consists of two parts: text and button. If the ButtonOnly property is True, then only a button is displayed within TdxTreeListButtonColumn. In order to generate a more pleasant look, set the TdxTreeListButtonColumn ShowButtonStyle property to sbAlways, the Sizing property to False and activate the egoShowButtonAlways option of a tree list.

Buttons property — read / write

Determines a collection of buttons.

```
property Buttons: TdxEditButtons;
```

Description

In-place editors that support button controls can contain several buttons. Use the Buttons property to manage these buttons. At design- or runtime, a user can add or delete edit buttons and modify their appearance.

EditButtonStyle property — read / write

Determines the style of an edit button.

```
type
  TdxEditButtonStyle = (ebsSimple, ebsEllipsis, ebsDown, ebsGlyph);
property EditButtonStyle : TdxEditButtonStyle;
```

Description

Use this property to define edit button style:

ebsSimple	No button appears.
ebsEllisis	Ellipsis ('…') appear on the surface of a button.
ebsDown	Displays a down arrow on the button similar to a combo box.
ebsGlyph	Displays a bitmap, specified by the Glyph property.

See Also

TdxTreeListButtonColumn.Glyph

ClickKey property — read / write

Determines a short cut to activate a button.

```
property ClickKey : TShortCut;
```

Description

Use this property to specify a keyboard short cut that activates a button.

Glyph property — read / write

Determines a bitmap that is drawn on an edit button.

```
property Glyph : TBitmap;
```

Description

Use this property to specify an image that appears on the surface of an edit button when the EditButtonStyle property is equal to ebsGlyph.

Copyright © 2000 Developer Express Inc.

HideEditCursor property read / write

Determines whether to show the cursor within TdxDBTreeListButtonColumn

```
property HideEditCursor: Boolean;
```

Description

If True, the cursor is not displayed within the focused TdxTreeListButtonColumn.

ShowButtonStyle property read / write

Determines appearance of the edit button.

```
type
  TdxShowButtonStyle = (sbDefault, sbAlways, sbNone);
property ShowButtonStyle: TdxShowButtonStyle;
```

Description

Use this property to determine appearance of the edit button.

Value	Meaning
sbDefault	Edit button is displayed only for a currently focused column.
sbAlways	Edit button is visible for all columns of a current node, not just that of a focused node
sbNone	Edit button is invisible. Double-click activates a dropdown window.

See Also

TdxDBTreeListButtonColumn.EditButtonStyle; TCustomdxDBGrid.OptionsEx; TdxDBTreeListButtonColumn.ButtonOnly; TdxDBTreeListButtonColumn.IsShowButton

TdxTreeListButtonColumn Methods

Derived from TdxTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListButtonColumn Events

TdxTreeListButtonColumn

OnButtonClick	**published**

Derived from TdxTreeListColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnButtonClick event

Occurs when clicking an edit button within a cell.

```
type
  TdxEditButtonClickEvent = procedure (Sender: TObject; AbsoluteIndex:
Integer) of object;
property OnButtonClick: TdxEditButtonClickEvent;
```

Description

Write an OnButtonClick event handler to perform specific actions when clicking a cell button. The AbsoluteIndex parameter determines the index of the pressed button. This index is zero-based.

Copyright © 2000 Developer Express Inc.

TdxTreeListCheckColumn

TdxTreeListCheckColumn represents a check column within a tree list.

Unit

dxTLClms

```
TdxTreeListCheckColumn = class(TdxTreeListColumn)
```

Description

TdxTreeListCheckColumn is useful to modify Boolean values within a tree list. It uses TdxInplaceTreeListCheckEdit for data modification.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn

TdxTreeListCheckColumn Properties

TdxTreeListCheckColumn

AllowGrayed	**published / read / write**	ValueChecked	**published / read / write**
Border3D	**published / read / write**	ValueGrayed	**published / read / write**
Glyph	**published / read / write**	ValueUnchecked	**published / read / write**
GlyphCount	**published / read / write**		
ShowNullFieldStyle	**published / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
CharCase	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

AllowGrayed property — read / write

Determines whether a check column has two or three states.

```
property AllowGrayed: Boolean;
```

Description

Determines whether a check editor has two (checked, unchecked) or three (checked, unchecked and grayed) states.

The default value is **False**.

Border3D property — read / write

Determines check box border style.

```
property Border3D : Boolean;
```

Description

Use this property to specify the border style of a check box. If Border3D is True, a check box has a 3D look.

Glyph property read / write

Determines the glyph displayed in place of a standard check box.

```
property Glyph: TBitmap;
```

Description

Use the Glyph property to specify a custom image for a check box. This bitmap can be used for different states of a check column cell based upon the GlyphCount property.

GlyphCount property read / write

Specifies the manner in which an image is used to represent a check box.

```
property GlyphCount: Integer;
```

Description

Use the GlyphCount property to determine the manner in which an image is used in place of a standard check box to display checked states.

Values include:

Value	Description
0	A glyph is not used. The standard check box is displayed.
1	A full size image is displayed instead of the standard check box.
2	The image is divided into two parts: one part indicates the checked state; the other part indicates the unchecked state of the check editor.
3	The glyph is divided into three parts. Each part determines the state of the check editor (grayed, checked, unchecked). Only one part can be dispayed at a time.
6	The glyph is divided into six parts. Each part determines the state of the check editor (grayed, checked, unchecked) when the check button is pressed and released. Only one part can be dispayed at a time.

It is recommended that you use 0,3 or 6.

ShowNullFieldStyle property read / write

Determines the display style for the null state of a check box.

```
type
  TdxShowNullFieldStyle = (nsUnchecked, nsInactive, nsGrayedChecked);
property ShowNullFieldStyle : TdxShowNullFieldStyle;
```

Description

Use this property to specify how a check box is displayed when its value is undetermined. The following values are available:

nsUnchecked	Check box is drawn unchecked.	☐
nsInactive	Check box is drawn as inactive.	■
nsGrayedCheck	Check box is grayed.	☑

ValueChecked property — read / write

```
property ValueChecked: string;
```

Description

Determines the text used as a value of TdxTreeListCheckColumn when it is checked.

See Also

TdxTreeListCheckColumn.GetCheckBoxState; TdxTreeListCheckColumn.GetCheckBoxValue; TdxTreeListCheckColumn.ValueUnchecked

ValueGrayed property — read / write

Specifies the value that corresponds to the grayed state of a check box.

```
property ValueGrayed: string;
```

Description

Use the ValueGrayed property to specify the value represented by the check box when it is grayed.

ValueUnchecked property — read / write

```
property ValueUnchecked: string;
```

Description

Determines the text used as a value of TdxDBTreeListCheckColumn when it is unchecked.

See Also

TdxTreeListCheckColumn.GetCheckBoxState; TdxTreeListCheckColumn.GetCheckBoxValue; TdxTreeListCheckColumn.ValueChecked

Copyright © 2000 Developer Express Inc.

TdxTreeListCheckColumn Methods

TdxTreeListCheckColumn

GetCheckBoxState	**public**
GetCheckBoxValue	**public**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

GetCheckBoxState method

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
function GetCheckBoxState(const AText : String) : TdxCheckBoxState;
```

Description

Returns the check box state using the TdxTreeListCheckColumn value.

See Also

TdxTreeListCheckColumn.GetCheckBoxValue; TdxTreeListCheckColumn.ValueChecked; TdxTreeListCheckColumn.ValueUnchecked

GetCheckBoxValue method

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
function GetCheckBoxValue(AState : TdxCheckBoxState) : String;
```

Description

Returns the TdxTreeListCheckColumn value by its state. The result of the function depends on ValueChecked and ValueUnchecked properties and the state of a check box.

See Also

TdxTreeListCheckColumn.GetCheckBoxState; TdxTreeListCheckColumn.ValueChecked; TdxTreeListCheckColumn.ValueUnchecked

TdxTreeListCheckColumn Events

TdxTreeListCheckColumn

OnToggleClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnToggleClick event

Occurs when clicking a check box within TdxTreeListCheckColumn.

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
  TdxToggleEvent = procedure(Sender : TObject; const Text : String; State :
TdxCheckBoxState) of object;
property OnToggleClick: TdxToggleEvent;
```

Description

Write an OnToggleClick event handler to perform special processing when clicking a check box. The State parameter determines the state of a check box. The Text parameter specifies Text.

Copyright © 2000 Developer Express Inc.

TdxTreeListCurrencyColumn

Unit

dxTLClms

```
TdxTreeListCurrencyColumn = class(TdxTreeListColumn);
```

Description

Used to modify currency format data within a tree list. TdxTreeListCurrencyColumn uses TdxInplaceTreeListCurrencyEdit for data modification.

Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

TdxTreeListCurrencyColumn Properties

TdxTreeLsitCurrencyColumn

DecimalPlaces	**published / read / write**	MinValue	**published / read / write**
DisplayFormat	**published / read / write**	MaxValue	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
CharCase	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

DecimalPlaces property — read / write

```
property DecimalPlaces: Cardinal;
```

Description

Specifies the number of digits following the decimal separator when editing. The default value for DecimalPlaces is 2.

Note: *The DecimalPlaces property is in effect only when editing values within a TdxTreeListCurrencyColumn. It does not affect display format. To change the display format of a TdxTreeListCurrencyColumn, use the OnCustomDrawCell event.*

DisplayFormat property — read / write

Determines the manner in which a currency value is formatted.

```
property DisplayFormat: string;
```

Description

Use the DisplayFormat property to define the format used to display data within a currency cell. This format is applied when the editor loses its focus.

The default format string is ‘$,0.00;-$,0.00’.

MinValue property read / write

```
property MinValue: Double;
```

Description

Determines the minimum value TdxTreeListCurrencyColumn can assume.

See Also

TdxTreeListCurrencyColumn.MaxValue

MaxValue property read / write

```
property MaxValue: Double;
```

Description

Determines the maximum value TdxTreeListCurrencyColumn can assume.

See Also

TdxTreeListCurrencyColumn.MinValue

TdxTreeListCurrencyColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListCurrencyColumn Events

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

Copyright © 2000 Developer Express Inc.

TdxTreeListHyperLinkColumn

TdxDBTreeListHyperLinkColumn represents data as a hyperlink.

Unit

dxTLClms

```
TdxTreeListHyperLinkColumn = class(TdxTreeListColumn);
```

Description

Use TdxTreeListHyperLinkColumn when you need to represent data within a tree list cell as a hyperlink. Double-clicking (or clicking) these hyperlinks generates the OnStartClick event. Write an OnStartClick event handler to process mouse clicks events.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn

TdxTreeListHyperLinkColumn Properties

TdxTreeListHyperLinkColumn

EditBackgroundColor	**published / read / write**	StartKey	**published / read / write**
EditFontColor	**published / read / write**		
SingleClick	**published / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

EditBackgroundColor property — read / write

```
property EditBackgroundColor: TColor;
```

Description

Specifies the background color for text in TdxTreeListHyperLinkColumn. The default value for EditBackgroundColor is clWhite.

See Also

TdxTreeListHyperLinkColumn.EditFontColor

EditFontColor property — read / write

```
property EditFontColor: TColor;
```

Description

Specifies the font color in TdxTreeListHyperLinkColumn. The default value for EditFontColor is clBlue.

See Also

TdxTreeListHyperLinkColumn.EditBackgroundColor

SingleClick property — read / write

```
property SingleClick: Boolean;
```

Description

Determines whether the OnStartClick event is generated by a mouse click. The default value for SingleClick is False, so the OnStartClick event is generated by double-click.

StartKey property — read / write

```
property StartKey: TShortCut;
```

Description

Specifies the short cut that generates the OnStartClick event. In other words, StartKey is a short cut that activates TdxTreeListHyperLinkColumn. By default, TdxTreeListHyperLinkColumn is activated by Ctrl+Enter.

TdxTreeListHyperLinkColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

Copyright © 2000 Developer Express Inc.

TdxTreeListHyperLinkColumn Events

TdxTreeListHyperLinkColumn

OnStartClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnStartClick event

Occurs when a user clicks the text in TdxTreeListHyperLinkColumn.

```
type
  TNotifyEvent = procedure(Sender : TObject) of object;
property OnStartClick: TNotifyEvent;
```

Description

This is a base procedure for TdxTreeListHyperLinkColumn. Write an OnStartClick event handler to activate a hyperlink in accordance with your specific requirements.

The following code is an example of the OnStartClick event handler:

```
uses
  . . . , shellapi;

  . . .

implementation

  . . .

procedure TForm1.dxTreeList1Column1StartClick(Sender: TObject);
var
 URLName : string;
begin
  URLName := dxTreeList1.FocusedNode.Values[dxTreeList1.FocusedColumn];
  ShellExecute(0,'open','iexplore.exe', @URLName[1],'', SW_MAXIMIZE);
end;
```

TdxTreeListMemoColumn

Unit

dxTLClms

```
TdxTreeListMemoColumn = class(TdxTreeListColumn);
```

Description

TdxTreeListMemoColumn is used to display large text strings within a tree list cell. TdxTreeListMemoColumn uses the TdxInplaceTreeListMemoEdit inplace editor to modify data.

Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListMemoColumn Properties

TdxTreeListMemoColumn

HideScrollBars	**published / read / write**	WantReturns	**published / read / write**
MaxDisplayLength	**published / read / write**	WantTabs	**published / read / write**
SelectionBar	**published / read / write**	WordWrap	**published / read / write**
ScrollBars	**published / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

HideScrollBars property — read / write

Determines whether a memo cell displays scroll bars at the edges of its edit box.

```
property HideScrollBars: Boolean;
```

Description

If the HideScrollBars property is set to **False**, scroll bars are displayed within a memo cell when editing its contents. This property does not affect memo cells if the ScrollBars property is set to **ssNone**.

The default value is **True**.

MaxDisplayLength property — read / write

Determines length of a string of characters that are displayed within TdxTreeListMemoColumn.

```
property MaxDisplayLength: Integer;
```

Description

Use this property to specify the number of characters that are displayed within a tree list cell of type TdxTreeListMemoColumn.

SelectionBar property — read / write

Specifies whether the selection bar is displayed at the leftmost edge of a memo cell.

```
property SelectionBar: Boolean;
```

Description

Selection bar is a region at the leftmost edge of a memo cell. It allows a user to select the entire contents of a text line using the mouse. Set the SelectionBar property to True to display it or to False to hide it. When the selection bar is hidden, a user can select text lines on a character-by-character basis only.

The default value is **False**.

ScrollBars property — read / write

Specifies which scroll bars are used within TdxTreeListMemoColumn.

```
type
  TScrollStyle = (ssNone, ssHorizontal, ssVertical, ssBoth);
property ScrollBars: TScrollStyle;
```

Description

Use ScrollBars to specify which scroll bars are displayed within TdxTreeListMemoColumn. ScrollBars can take one of the following values:

Value	Meaning
ssNone	Cell has no scroll bars.
ssHorizontal	Cell has a single scroll bar at the bottom edge.
ssVertical	Cell has a single scroll bar at the right edge.
ssBoth	Cell has a scroll bar on both the bottom and right edges.

WantReturns property — read / write

Specifies whether a user can insert return characters into a memo cell's text.

```
property WantReturns: Boolean;
```

Description

Setting the WantReturns property to **True** enables users to enter return characters into text. If WantReturns is True, pressing the Enter key inserts a return character into text.

The default value is **True**.

Copyright © 2000 Developer Express Inc.

WantTabs property read / write

Specifies whether a user can insert tab characters in text.

```
property WantTabs: Boolean;
```

Description

Setting the WantTabs property to **True** enables users to enter tab characters into text.

The default value is **False**.

WordWrap property read / write

Determines whether to wrap words within TdxTreeListmemoColumn.

```
property WordWrap: Boolean;
```

Description

Set WordWrap to True to make a cell of type TdxTreeListMemoColumn wrap text at the right margin so it fits in the cell area. The wrapping is cosmetic only - the text does not include any return characters that were not explicitly entered.

Note: *There should be no need for a horizontal scroll bar if WordWrap is True.*

TdxTreeListMemoColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListMemoColumn Events

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

Copyright © 2000 Developer Express Inc.

TdxTreeListSpinColumn

Unit

dxTLClms

```
TdxTreeListSpinColumn = class(TdxTreeListColumn);
```

Description

Used when the value of a tree list cell can assume sequential values. TdxTreeListSpinColumn uses TdxInplaceTreeListSpinEdit for data modification.

Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

TdxTreeListSpinColumn Properties

TdxTreeListSpinColumn

EditorEnabled	**published / read / write**	UseCtrlIncrement	**published / read / write**
Increment	**published / read / write**	ValueType	**published / read / write**
MinValue	**published / read / write**		
MaxValue	**published / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

EditorEnabled property — read / write

Determines whether a user can edit data within TdxDBTreeListSpinColumn.

```
property EditorEnabled: Boolean;
```

Description

If EditorEnabled is True, users can change the TdxTreeListSpinColumn value by pressing up/down buttons or using the keyboard. Setting EditorEnabled to False prevents using the keyboard for data modification.

Increment property — read / write

Specifies the amount a TdxTreeListSpinColumn value changes each time the up or down button is pressed.

```
property Increment: Double;
```

Description

Use Increment to control granularity of changes made by a TdxTreeListSpinColumn up-down control. Set Increment to indicate the number of units between MinValue and MaxValue.

See Also

TdxTreeListSpinColumn.MaxValue; TdxTreeListSpinColumn.MinValue

MinValue property — read / write

Specifies the minimum value of TdxTreeListSpinColumn.

```
property MinValue: Double;
```

Description

Use MinValue to provide the lower limit range value which TdxTreeListSpinColumn can assume.

See Also

TdxTreeListSpinColumn.MaxValue; TdxTreeListSpinColumn.Increment

MaxValue property — read / write

Specifies the maximum value of TdxTreeListSpinColumn.

```
property MaxValue: Double;
```

Description

Use MaxValue to provide the upper limit range which TdxTreeListSpinColumn can assume.

See Also

TdxTreeListSpinColumn.MinValue; TdxTreeListSpinColumn.Increment

UseCtrlIncrement — read / write

Determines keyboard keys, used for changing the TdxDBTreeListSpinColumn value.

```
property UseCtrlIncrement: Boolean;
```

Description

If UseCtrlIncrement is False, users can change the TdxTreeListSpinColumn value using Up and Down arrow keys. If True, users should use Ctrl+Up and Ctrl+Down keys for modifying the TdxTreeListSpinColumn value. Pressing Up or Down key when UseCtrlIncrement is True moves focus to the previous/next node.

ValueType property — read / write

Returns the type of a field, associated with TdxDBTreeListSpinColumn.

```
type
```

```
  TdxValueType = (vtInt, vtFloat);
property ValueType: TdxValueType;
```

Description

Specifies the type of data within TdxTreeListSpinColumn. If ValueType is vtFloat, then TdxTreeListSpinColumn is used to edit float values. Otherwise, TdxTreeListSpinColumn is used for integer values.

Copyright © 2000 Developer Express Inc.

TdxTreeListSpinColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListSpinColumn Events

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxTreeListTimeColumn

Unit

dxTLClms

```
TdxTreeListTimeColumn = class(TdxTreeListColumn);
```

Description

Used to modify time format data within a tree list cell. TdxTreeListTimeColumn uses TdxInplaceTreeListTimeEdit for data modification.

Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListTimeColumn Properties

TdxTreeListTimeColumn

TimeEditFormat	**published / read / write**
UseCtrlIncrement	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

TdxTimeEditFormat property — read / write

Specifies the time format of the edited time value.

```
type
  TdxTimeEditFormat = (tfHourMinSec, tfHourMin, tfHour);
property TimeEditFormat: TdxTimeEditFormat;
```

Description

Use the TimeEditFormat property to specify the manner in which time is represented within an editor. Possible values include:

Value	Meaning
tfHourMinSec	Hours, minutes and seconds are displayed within a time cell.
tfHourMin	Hours and minutes are displayed within a time cell.
tfHour	Hours are displayed within a time cell.

The default value is **tfHourMinSec**.

UseCtrlIncrement property read / write

Determines keys used for changing the TdxTreeListSpinColumn value.

```
property UseCtrlIncrement: Boolean;
```

Description

If UseCtrlIncrement is False, users can change the TdxTreeListTimeColumn value using Up and Down arrow keys. If UseCtrlIncrement is True, users must use Ctrl+Up and Ctrl+Down keys to modify the TdxTreeListTimeColumn value. Pressing the Up or Down key when UseCtrlIncrement is True moves focus to the previous/next node.

Copyright © 2000 Developer Express Inc.

TdxTreeListTimeColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListTimeColumn Events

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxTreeListCalcColumn

Provides a column with a dropdown calculator.

Unit

dxTLClms

```
TdxTreeListCalcColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListCalcColumn represents a column with a dropdown calculator. It uses the TdxInplaceTreeListCalcEdit inplace editor (an edit field with a calculator) for data editing.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListCalcColumn Properties

TdxTreeListCalcColumn

BeepOnError	**published / read / write**	ShowButtonFrame	**published / read / write**
ButtonStyle	**published / read / write**	QuickClose	**published / read / write**
Precision	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**published / read / write**	PopupAlignment	**published / read / write**
DropDownRows	**protected / read / write**	PopupBorder	**published / read / write**
DropDownWidth	**protected / read / write**	ShowButtonStyle	**published / read / write**
ImmediateDropDown	**protected / read / write**		
ImmediatePopup	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

BeepOnError property — read / write

Determines whether to make a beep on errors.

```
property BeepOnError : Boolean;
```

Description

If True, a column makes a beep on a calculation errors, e.g. devide overflow.

ButtonStyle property — read / write

Determines calculator button style.

```
type
```

```
  TdxButtonStyle = (bsStandard, bsFlat, bsExtraFlat);
property ButtonStyle : TdxButtonStyle;
```

Description

Use this property to specify the style of calculator buttons:

bsStandard	Standard 3D look.
bsFlat	Flat look.
bsExtraFlat	Flattened look similar to toolbar buttons.

Precision property — read / write

Specifies the number of accuracy digits used to store calculated values.

```
property Precision : Byte;
```

Description

Use this property to specify the total number of digits used during calculations. The default value for Precision is 13.

ShowButtonFrame property — read / write

Determines whether to display a frame around buttons.

```
property ShowButtonFrame : Boolean;
```

Description

If ShowButtonFrame is True, an ellipse is drawn around the caption of a button. The look of a button frame is especially attractive when the ButtonStyle property is of bsExtraFlat style.

QuickClose property — read / write

Determines whether to hide a dropdown calculator when pressing the '=' key.

```
property QuickClose: Boolean;
```

Description

If the QuickClose property is set to **True**, the dropdown calculator closes when a user presses the '=' keyboard button. By default, the QuickClose property is set to **False** and pressing the '=' key does not close it. In any instance, clicking the '=' button of the dropdown calculator DOES NOT close it.

Copyright © 2000 Developer Express Inc.

TdxTreeListCalcColumn Methods

Derived from TdxTreeListColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListCalcColumn Events

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxTreeListDateColumn

Unit

dxTLClms

```
TdxTreeListDateColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListDateColumn works with dates within a tree list. Pressing the edit button of TdxTreeListDateColumn activates a dropdown calendar. TdxTreeListDateColumn uses the TdxInplaceTreeListDateEdit inplace editor.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListDateColumn Properties

TdxTreeListDateColumn

DateButtons	**published / read / write**	SaveTime	**published / read / write**
DateOnError	**published / read / write**	UseEditMask	**published / read / write**
DateValidation	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

DateButtons property — read / write

Determines whether a dropdown calendar contains ‘Today’ or/and ‘Clear’ buttons.

```
type
  TDateButton = (btnToday, btnClear);
  TDateButtons = set of TDateButton;
property DateButtons : TDateButtons;
```

Description

Use this property to control the appearance of ‘Today’ and ‘Clear’ buttons within a dropdown calendar. Press the ‘Today’ button to set the current date to a tree list cell. Pressing ‘Clear’ removes any date from a tree list cell. By default, these buttons are displayed in a calendar.

See Also

sdxGridDatePopupClear; sdxGridDatePopupToday

DateOnError property — read / write

Determines the date, which will be assigned to the date edit in case of invalid date input.

```
type
  TDateOnError = (deToday, deNull);
property DateOnError: TDateOnError;
```

Description

Use the DateOnError property to set the date, which will be assigned to the date edit in case of invalid date input. Assign DateOnError to deToday to set the current date or deNull to set NULL date.

See Also

sdxDateError; TdxTreeListDateColumn.OnDateValidateInput; TdxTreeListDateColumn.DateValidation

DateValidation property — read / write

Specifies whether an exception is displayed in case of invalid date input.

```
property DateValidation: Boolean;
```

Description

Use the DateValidation property to specify whether an exception is displayed in case of invalid date input. Set it to True to show the default exception or to False not to show it.

See Also

TdxDBTreeListDateColumn.DateOnError; TdxTreeListDateColumn.OnDateValidateInput

SaveTime property — read / write

Specifies whether time is stored in a data cell.

```
property SaveTime: Boolean;
```

Description

Date can be entered into a date cell together with time values. If this property is set to **True**, the time value must be explicitly modified when another date is selected within the Calendar.

The default value is **True**.

UseEditMask property — read / write

Determines whether to display an edit mask in a focused cell.

```
property UseEditMask : Boolean;
```

Description

If UseEditMask is True, an edit mask appears in a focused cell in order to simplify date input.

TdxTreeListDateColumn Methods

Derived from TdxTreeListColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListDateColumn Events

TdxTreeListDateColumn

OnDateValidateInput	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnDateValidateInput event

Occurs on invalid date input.

```
type
TdxDateValidateInput = procedure(Sender: TObject; const AText: String; var
ADate: TDateTime; var AMessage: string; var AError: Boolean) of object;
property OnDateValidateInput: TdxDateValidateInput;
```

Description

Write an OnDateValidateInput event handler to perform specific actions when a user enters a date. AText is the input text; ADate is the date after conversion. If TdxTreeListDateColumn is not able to convert text to the date (the AError parameter is True), a value based on the DateOnError property is assigned to the ADate parameter. You can change the ADate parameter within the code of a handler. AMessage is an exception message that is displayed on an error. Set the AError parameter to False to prevent exception display.

See Also

TdxDBTreeListDateColumn.DateOnError; TdxTreeListDateColumn.DateValidation

Copyright © 2000 Developer Express Inc.

TdxTreeListImageColumn

Represents a column with a dropdown image list.

```
TdxTreeListImageColumn = class(TdxTreeListDropDownColumn);
```

Description

Each item of a dropdown list within TdxTreeListColumn contains an image and a description. Data that is placed into a dataset field when closing a dropdown window is specified by the Values property. TdxTreeListImageColumn uses TdxInplaceTreeListImageEdit to modify data.

Hierarchy

TObject

- TPersistent
  - TComponent
  - TdxTreeListColumn
    - TdxTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListImageColumn Properties

TdxTreeListImageColumn

Images	**published / read / write**	Values	**published / read / write**
LargeImages	**published / read / write**	Descriptions	**published / read / write**
ListWidth	**published / read / write**	ShowDescription	**published / read / write**
ImageIndexes	**published / read / write**	DefaultImages	**published / read / write**
Incremental	**published / read / write**		
MultiLineText	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**published / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Incremental property read / write

Specifies whether pressing the Up and Down keys changes the current value.

```
property Incremental: Boolean;
```

Description

This property is effective only if the cell editor is active. If the Incremental property is set to **True**, pressing the Up and Down keys changes the current value within a cell; Otherwise it moves focus to another cell.

The default value is **False**.

Images property read / write

Determines an image list collection associated with TdxTreeListImageColumn.

```
property Images : TImageList;
```

Description

TdxTreeListImageColumn uses pictures from an Images list for drawing the graphical portion of items. An image from Images associates with an item via the ImageIndexes property of TdxTreeListImageColumn.

See Also

TdxTreeListImageColumn.ImageIndexes; TdxTreeListImageColumn.LargeImages

LargeImages property read / write

Specifies a list of large images that appear in the dropdown list.

```
property LargeImages: TImageList;
```

Description

The LargeImages property specifies a list of large images that are drawn for the graphic portion of items in a dropdown list. If TdxTreeListImageColumn has both Images and LargeImages property assigned, then it draws LargeImages in the dropdown list.

See Also

TdxTreeListImageColumn.ImageIndexes; TdxTreeListImageColumn.Images

ListWidth property read / write

Determines the width of a dropdown list.

```
property ListWidth: Integer;
```

Description

Use this property to specify the width of a dropdown list.

ImageIndexes property read / write

Represents items image indexes.

```
property ImageIndexes : TStrings;
```

Description

Use this property to set the image index of an item from a dropdown list. Image index determines a picture from the Images property that is displayed as the graphic portion of an item. The first element

of the ImageIndexes array corresponds to the first item in a dropdown list; the second element corresponds to the second item, etc.

See Also

TdxTreeListImageColumn.Descriptions; TdxTreeListImageColumn.Images; TdxTreeListImageColumn.Values

MultiLineText property read / write

Specifies how description appears within a tree list cell.

```
property MultiLineText: Boolean;
```

Description

By default, MultiLineText is Flase; thus, description is drawn as a single-line text. TdxTreeListImageColumn displays only the part of the description that fits in a tree list cell. If the MultiLineText property is True, then description occupies several lines within TdxTreeListImageColumn.

Values property read / write

Determines values corresponding to dropdown list items.

```
property Values : TStrings;
```

Description

Contains an array of values that are placed in a dataset field, associated with TdxTreeListImageColumn. The first element of the Values array cooresponds to the first item in the dropdown list; the second element corresponds to the second item, etc.

See Also

TdxTreeListImageColumn.Descriptions; TdxTreeListImageColumn.ImageIndexes

Descriptions property read / write

Represents an array of item descriptions.

```
property Descriptions: TStrings;
```

Description

Item description is the text that appears in a dropdown list as the text portion of an item. The first element of the Descriptions array is the description of the first item; the second element corresponds to the description of the second item; etc.

See Also

TdxTreeListImageColumn.ImageIndexes; TdxTreeListImageColumn.Values

ShowDescription read / write

Determines whether to display item descriptions in a dropdown list.

```
property ShowDescription : Boolean;
```

Description

If ShowDescription is True, item descriptions are displayed within a dropdown list.

See Also

TdxTreeListImageColumn.Descriptions

DefaultImages property read / write

Determines image indexes of items.

```
property DefaultImages : Boolean;
```

Description

If DefaultImages is True, the dropdown list items have sequential image indexes. The first item has index 0, the second has index 1, third - 2, etc. If DefaultImages is False, the image indexes of an item are defined by the ImageIndexes property.

See Also

TdxTreeListImageColumn.ImageIndexes

Copyright © 2000 Developer Express Inc.

TdxTreeListImageColumn Methods

TdxTreeListImageColumn

GetImageIndex	**public**
GetIndexes	**public**

Derived from TdxTreeListColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

GetImageIndex method

Returns the image index by the text of an item.

```
function GetImageIndex(const AText : String) : Integer;
```

Description

Use this method to obtain the image index of an item whose value is equal to AText. The value of an item is specified by the Values property. If TdxTreeListImageColumn does not contain an item with a value equal to AText, this method returns -1.

See Also

TdxTreeListImageColumn.ImageIndexes

GetIndexes method

Returns the image index of an item and index of an item description by the item value.

```
procedure GetIndexes(const AText: String; var AImageIndex, ADescIndex:
Integer);
```

Description

Use this method to obtain index of an image associated with an item via the ImageIndexes property and index of item description in the Descriptions property. AImageIndex is the index of an item image and ADescImage is the index of item description. AText specifies the item value. If TdxDBTreeListImageColumn doesn't contain an item with the AText value, GetIndexes returns -1.

See Also

TdxTreeListImageColumn.Descriptions; TdxTreeListImageColumn.ImageIndexes; TdxTreeListImageColumn.Values

Copyright © 2000 Developer Express Inc.

TdxTreeListImageColumn Events

TdxTreeListImageColumn

OnCloseUp	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnCloseUp event

Occurs when closing a dropdown image list.

```
type
  TdxTLImageColumnCloseUp = procedure(Sender: TObject; var Value: string;
var Accept: Boolean) of object;
property OnCloseUp: TdxTLImageColumnCloseUp;
```

Description

Write an OnCloseUp event handler to perform special processing when closing a dropdown image list. The Value parameter determines the value (but not the description) of a selected item from the dropdown image list. The Accept parameter determines whether TdxTreeListImageColumn accepts changes.

TdxTreeListPickColumn

Unit

dxTLClms

```
TdxTreeListPickColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListPickColumn represents a column with a dropdown list.

Pressing the edit button of TdxTreeListPickColumn activates a dropdown list with text items. TdxTreeListPickColumn looks like a combo box. An incremental search is available within it. TdxTreeListPickColumn uses TdxInplaceTreeListPickEdit for data modification.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListPickColumn Properties

TdxTreeListPickColumn

CanDeleteText	**published / read / write**	Revertable	**published / read / write**
Items	**published / read / write**	ItemsSorted	**published / read / write**
DropDownListStyle	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read/ write**
DropDownRows	**published / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protected / read/ write**	PopupBorder	**published / read / write**
ImmediateDropDown	**published / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

CanDeleteText property — read / write

Specifies whether a user can delete the displayed value.

```
property CanDeleteText: Boolean;
```

Description

This property is used when the DropDownListStyle property is set to **True**. If the CanDeleteText property is set to **False**, users cannot delete the selected value from a cell. If the CanDeleteText property is set to **True**, users can delete the selected value without removing this item from the dropdown list.

The default value is **False**.

Items property read / write

Contains strings that appear in a dropdown list box.

```
property Items : TStrings;
```

Description

Use Items to add, insert, delete and move items. Use TStrings methods and properties to manipulate items in a dropdown list.

DropDownListStyle property read / write

Determines whether a user can edit data within a tree list cell or can only select a value from the list.

```
property DropDownListStyle : Boolean;
```

Description

If DropDownListStyle is True, TdxTreeListPickColumn does not allow editing data within a cell, users can only select a value from a dropdown list.

Revertable property read / write

Specifies whether a user can cycle through list values by a double click.

```
property Revertable: Boolean;
```

Description

Set the Revertable property to **True** to allow a user to cycle through list values by double-clicking the appropriate mouse button within a pick editor. When the Revertable property is True, list values are displayed within the editor in their stored order. The display process is circular. When the last item of the list is displayed, a double click displays the first item in the list.

The default value is **False**.

ItemsSorted property read / write

Specifies whether dropdown list values are sorted.

```
property ItemsSorted: Boolean;
```

Description

If the ItemsSorted property is set to **True**, all values are sorted within a pick list.

The default value is **False**.

Copyright © 2000 Developer Express Inc.

TdxTreeListPickColumn Methods

Derived from TdxTreeListColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListPickColumn Events

TdxTreeListPickColumn

OnCloseUp	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnCloseUp event

Occurs when the dropdown list closes.

```
type
  TdxTLPickColumnCloseUp = procedure(Sender: TObject; var Value: Variant;
var Accept: Boolean) of object;
property OnCloseUp: TdxTLPickColumnCloseUp;
```

Description

Write an OnCloseUp event handler to implement special processing that occurs only when the dropdown list closes.

TdxTreeListPopupColumn

TdxTreeListPopupColumn represents a tree list column with a custom dropdown window.

Unit

dxTLClEx

```
TdxTreeListPopupColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListPopupColumn represents a column that can use any control including custom forms as a dropdown window. It allows an application to implement complex dropdown windows to modify data in tree list cells. TdxDBTreeListPopupColumn uses TdxInplaceDBTreeListPopupEdit to edit data.



Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

TdxTreeListPopupColumn Properties

TdxTreeListPopupColumn

PopupAutoSize	**published / read / write**	PopupFormSizeable	**published / read / write**
PopupControl	**published / read / write**	PopupHeight	**published / read / write**
PopupFormBorderStyle	**published / read / write**	PopupMinHeight	**published / read / write**
PopupFormCaption	**published / read / write**	PopupMinWidth	**published / read / write**
PopupFormClientEdge	**published / read / write**	PopupWidth	**published / read / write**
PopupFormFlatBorder	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownRows	**protected / read / write**	PopupBorder	**protected / read / write**
DropDownWidth	**protected / read / write**	ShowButtonStyle	**published / read / write**
ImmediateDropDown	**protected / read / write**		
ImmediatePopup	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

PopupAutoSize property — read / write

Determines whether a dropdown window has the same size as a popup control.

```
property PopupAutoSize: Boolean;
```

Description

If PopupAutoSize is True, the dropdown window has the same size as the control specified as the dropdown control. Otherwise, width and height of the dropdown window are determined by the PopupWidth and PopupHeight properties. By default, PopupAutoSize is True.

PopupControl property read / write

Determines a control to be used as a dropdown window.

```
property PopupControl: TControl;
```

Description

Use this property to determine a control to be used as a dropdown control. A dropdown control can be any component registered in the IDE and derived from TControl. We recommend that you make this control invisible initially, since its position changes when the dropdown window is made active (the control 'jumps' from its previous location to the dropdown window).

PopupFormBorderStyle property read / write

Specifies the border style for a dropdown window.

```
type
  TdxPopupEditFormBorderStyle = (pbsDialog, pbsDialogHelp, pbsSimple,
pbsSysPanel);
property PopupFormBorderStyle: TdxPopupEditFormBorderStyle;
```

Description

Use this property to define the border style of a dropdown window. The following values are available:

Value	Description
pbsDialog	Standard dialog box border.
pbsDialogHelp	Dialog window with a help button on its title.
pbsSimple	A window with a single line border.
pbsSysPanel	If specified, TdxDBTreeListPopupColumn displays a status bar at the bottom of the dropdown window. This status bar includes a resizing grip and a close button.

This property only impacts dropdown window style. By default, PopupFormBorderStyle is pbsDialog.

PopupFormCaption property read / write

Specifies the caption of a dropdown form.

```
property PopupFormCaption: string;
```

Description

Use this property to determine a dropdown window's caption.

Note: *Caption is visible only when PopupFormBorderStyle is equal to pbsDialog or pbsDialogHelp.*

By default, this property is set to pbsDialog.

PopupFormClientEdge property read / write

Determines the style of a dropdown window's border.

```
property PopupFormClientEdge: Boolean;
```

Description

If this property is True, the dropdown window has a border with a sunken edge. By default, PopupFormClientEdge is False.

PopupFormFlatBorder property read / write

Determines the style of a dropdown window's border.

```
property PopupFormFlatBorder: Boolean;
```

Description

If True, the dropdown window has a flat border. If PopupFormFlatBorder is False, the dropdown window has a 3D border. By default, it is True.

PopupFormSizeable porperty read / write

Specifies whether a dropdown window is sizeable.

```
property PopupFormSizeable: Boolean;
```

Description

If True, a user can change the size of a dropdown window. Otherwise, the dropdown window's size is fixed. By default, this property is True.

PopupHeight read / write

Specifies the height of a dropdown window.

```
property PopupHeight: Integer;
```

Description

Use the PopupHeight property to determine the height of a dropdown window that appears when pressing a button within TdxTreeListPopupColumn. This property has no effect when the PopupAutoSize property is True. It cannot be less than the PopupMinHeight property. By default, PopupHeight is equal to 200.

PopupMinHeight property read / write

Specifies the minimum height of a dropdown window.

```
property PopupMinHeight: Integer;
```

Description

Use this property to determine the minimum height of a TdxDBTreeListPopupColumn dropdown window. By default, PopupMinHeight is equal to 100.

PopupMinWidth property read / write

Specifies the minimum width of a dropdown window.

```
property PopupMinWidth: Integer;
```

Description

Use this property to specify the minimum width of a TdxDBTreeListPopupColumn dropdown window. By default, PopupMinWidth is equal to 100.

PopupWidth property read / write

Specifies the width of a dropdown window.

```
property PopupWidth : Integer;
```

Description

Use the PopupWidth property to determine the width of a dropdown window that appears when pressing a button within TdxTreeListPopupColumn. This property has no effect when the PopupAutoSize property is True. It cannot be less than the PopupMinWidth property. By default, PopupWidth is equal to 250.

Copyright © 2000 Developer Express Inc.

TdxTreeListPopupColumn Methods

Derived from TdxTreeListColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	Destroy	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**
DefaultWidth	**public**		

TdxTreeListPopupColumn Events

TdxTreeListPopupColumn

OnCloseQuery	**published**
OnCloseUp	**published**
OnInitPopup	**published**
OnPopup	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**
OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**
OnValidate	**published**

OnCloseQuery event

This event occurs when a dropdown window is about to be closed.

```
type
  TdxPopupEditCloseQueryEvent = procedure (Sender: TObject; var CanClose:
Boolean) of object;
property OnCloseQuery: TdxPopupEditCloseQueryEvent;
```

Description

Write an OnCloseQuery event handler to determine whether a dropdown window can be closed. Set the CanClose parameter within the event handler to False to prevent window closing. The OnCloseQuery event is generated on pressing the Close button or Alt-F4 to close the dropdown form.

OnCloseUp event

This event occurs immediately after a dropdown window has closed.

```
type
  TdxPopupEditCloseUpEvent = procedure (Sender: TObject; var Text: string;
var Accept: Boolean) of object;
property OnCloseUp: TdxPopupEditCloseUpEvent;
```

Description

Write an OnCloseUp event handler to confirm or discard any changes made in grid cells via the dropdown window. The Text parameter specifies text, edited in the active grid cell. Set Accept to True to confirm changes in a grid cell. If Accept is False, all changes are canceled.

Copyright © 2000 Developer Express Inc.

OnInitPopup event

This event occurs when a dropdown window is about to be activated.

```
type
  TNotifyEvent = procedure (Sender: TObject) of object;
property OnInitPopup: TNotifyEvent;
```

Description

Write an OnInitPopup event handler to prepare data for a dropdown window and to determine which control will be displayed as a dropdown control. This feature allows using different dropdown windows for different ExressTreeList items.

OnPopup event

This event occurs before the dropdown form is displayed.

```
type
  TdxPopupEditPopupEvent = procedure (Sender: TObject; const EditText:
string) of object;
property OnPopup: TdxPopupEditPopupEvent;
```

Description

Write an OnPopup event handler to prepare data in the dropdown control before activating the dropdown form. The EditText parameter specifies text displayed in the current cell. Use this text to prepare data in the dropdown control; i.e. To position the cursor to a specific record in the dropdown grid.

TdxTreeListGraphicColumn

Use TdxDBTreeListGraphicColumn to display and edit graphics directly within the ExpressQuantumGrid.

Unit

dxTLClms

```
TdxTreeListGraphicColumn = class(TdxTreeListColumn);
```

Description

TdxTreeListGraphicColumn represents a column with a picture in-place editor. TdxTreeListGraphicColumn derives all TdxTreeListColumn methods and properties and publishes some of them. Unlike TdxTreeListBlobColumn, TdxTreeListGraphicColumn draws pictures within cells; thus it is unnecessary to call an in-place editor to view a picture.



Hierarchy

TObject
TPersistent
TComponent
TdxTreeListColumn

TdxTreeListGraphicColumn Properties

TdxTreeListGraphicColumn

Center	**published / read / write**	PopupToolBar	**published / read / write**
ClipboardFormat	**public / read / write**	PopupToolbarPosStored	**published / read / write**
CustomFilter	**published / read / write**	QuickDraw	**published / read / write**
CustomGraphic	**published / read / write**	ShadowSelection	**published / read / write**
DblClickActivate	**published / read / write**	Stretch	**published / read / write**
GraphicTransparency	**published / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**publi? / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**publi? / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

ClipboardFormat property — read / write

Specifies Clipboard format.

```
property ClipboardFormat: Word;
```

Description

When creating an instance of the TdxTreeListGraphicColumn class, this property sets the format to CF_PICTURE.

Center property — read / write

Determines whether the displayed picture is aligned to the center of a graphic column cell.

```
property Center: Boolean;
```

Description

If the Center property is **True**, a picture is centered; Otherwise it is aligned to the top-left corner of a graphic column cell.

The default value is **True**.

CustomFilter property read / write

Determines the filter used to display specific files in a Files list box when loading graphics.

```
property CustomFilter: string;
```

Description

The CustomFilter property is used to define filters for the Load File Dialog window (Files list box). Enter wildcards and extensions to define your filter. For instance, if this property is set to *.BMP", only files with a .BMP extension are displayed.

CustomGraphic property read / write

Determines whether TdxTreeListGraphicColumn displays custom images.

```
property CustomGraphic: Boolean;
```

Description

Set the CustomGraphic property to **True**, if TdxTreeListGraphicColumn displays non-bitmap images, i.e. JPEG, GIF, ICON, etc. If CustomGraphic is **False** (the default value), images are considered to be TBitmap.

The default value is **False**.

DblClickActivate property read / write

Specifies whether the associated toolbar can be activated by a double click event within the cell of a graphic column.

```
property DblClickActivate: Boolean;
```

Description

The DblClickActivate property is in effect when the IsPopupMenu property is set to **False**. If the DblClickActivate property value is set to **True**, a double click within a cell activates the associated toolbar. If the DblClickActivate property value is set to **False** (and the IsPopupMenu property is set to **False** as well), the associated toolbar is activated by a single click.

The default value is **True**.

GraphicTransparency property read / write

Determines graphic transparency.

```
type
  TdxGraphicEditTransparency = (gtDefault, gtOpaque, gtTransparent);
property GraphicTransparency: TdxGraphicEditTransparency;
```

Description

Use the GraphicTransparency property to specify the manner in which an image is displayed within a cell of a graphic column. Set the GraphicTransparency property to gtDefault (the default value) to use the settings appropriate to the graphic itself (transparent for metafiles, opaque for bitmaps). Set the property to gtOpaque to make the background opaque. Set the property to gtTransparent to make the background transparent.

Value	Description
gtDefault	Graphic settings are used.
gtOpaque	Background is opaque.
gtTransparent	Background is transparent.

The default value is **gtDefault**.

PopupToolBar property — read / write

Defines the ExpressToolBar popup window.

```
property PopupToolBar: TdxPopupToolBarWindow;
```

Description

Use the PopupToolBar property to set up image toolbar properties. This toolbar is only activated when clicking a graphic column.

PopupToolbarPosStored property — read / write

Determines whether the position of an edit toolbar is stored from one individual edit to another.

```
property PopupToolbarPosStored: Boolean;
```

Description

TdxTreeListGraphicColumn implements a toolbar that is used to modify pictures in grid cells. If the PopupToolbarPosStored property is **False**, the edit toolbar appears next to the edited cell each time a user activates it. If PopupToolbarPosStored is **True**, toolbar position is stored between edits.

The default value is **True**.

QuickDraw property — read / write

Specifies whether an image is displayed using a palette.

```
property QuickDraw: Boolean;
```

Description

Set the QuickDraw property to specify whether a customized palette is used when displaying field values. If **False**, the palette is used to provide the best possible image quality at the expense of additional processing time. If **True**, no special palette is used, which results in faster processing, but yields poorer picture quality, especially with 256-color images on a 256-color video driver.

The default value is **False**.

ShadowSelection property read / write

Shadows images for selected nodes.

```
property ShadowSelection: Boolean;
```

Description

Set the ShadowSelection property to **True** to shadow images for selected nodes. Images are shadowed in the same manner as images in the MS ListView control (Large Icons).

The default value is **True**.

Stretch property read / write

Determines whether bitmaps and metafiles assume the size and shape of an image.

```
property Stretch: Boolean;
```

Description

Set the Stretch property to **True** to force a picture to assume the size and shape of an image control. When the image control resizes, the picture also resizes. The Stretch property resizes the height and width of an image independently. Thus, unlike a simple change in magnification, Stretch can distort the image if the image control has a different shape.

The default value is **True**.

Copyright © 2000 Developer Express Inc.

TdxTreeListGraphicColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

TdxTreeListGraphicColumn Events

TdxTreeListGraphicColumn

OnAssignPicture	**published**	OnGetGraphicClass	**published**
OnCustomClick	**published**		

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnAssignPicture event

Occurs when assigning an image.

```
type
  TdxGraphicEditAssignPictureEvent = procedure(Sender: TObject; var
Picture: TPicture) of object;
property OnAssignPicture: TdxGraphicEditAssignPictureEvent;
```

Description

This event is generated each time a user pastes an image to the edited cell. The Picture parameter specifies the pasted image. Write an OnAssignPicture event handler if you need to display specific picture formats (i.e. JPEG or GIF) in grid cells.

OnCustomClick event

Occurs immediately after a user clicks the custom button within an image toolbar window.

```
type
  TNotifyEvent = procedure(Sender : TObject) of object;
property OnCustomClick: TNotifyEvent;
```

Description

Use the OnCustomClick event to perform specific actions when pressing the custom button within an image toolbar window.

OnGetGraphicClass event

Occurs when drawing a grid cell of a graphic column.

```
type
  TdxGraphicEditGetGraphicClassEvent = procedure(Sender: TObject; Node:
TdxTreeListNode; var GraphicClass: TGraphicClass) of object;
property OnGetGraphicClass: TdxGraphicEditGetGraphicClassEvent;
```

Copyright © 2000 Developer Express Inc.

Description

This event is generated when a grid cell of a graphic column is drawn. The Node parameter determines the node to which the drawn cell belongs. The GraphicClass parameter specifies image type.

Write an OnGetGraphicClass event handler if you need to display images of different types in the same graphic column. Use the GraphicClass parameter to specify different image types for different nodes, i.e. JPEG for grouped nodes and ICON for standard nodes.

TdxTreeListMRUColumn

TdxDBTreeListColumn is the common ancestor of all column components in a data-aware grid.

TdxTreeListMRUColumn represents a column that displays and edits a list of most recently used (MRU) items.

Unit

dxTLClms

```
TdxTreeListMRUColumn = class(TdxTreeListPickColumn);
```

Description

TdxTreeListMRUColumn maintains a list of most recently used items. This list is automatically maintained by the column, so no additional coding is necessary. TdxTreeListMRUColumn can be used as a pick column to search for entered values against a list of most recently used items. Cells of this column can include one or two clickable buttons. One of these buttons is always used to activate a dropdown list of items. The other button can be programmed to perform specific operations.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxTreeListDropdownColumn
        - TdxTreeListPickColumn

Copyright © 2000 Developer Express Inc.

TdxTreeListMRUColumn Properties

TdxTreeListMRUColumn

MaxItemCount	**published / read / write**	ShowEllipsis	**published / read / write**

Derived from TdxTreeListPickColumn

CanDeleteText	**published / read / write**	Revertable	**published / read / write**
Items	**published / read / write**	Sorted	**published / read / write**
DropDownListStyle	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**protect / read / write**	ImmediatePopup	**protect / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**protect / read / write**
DropDownWidth	**protect / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**published / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**publi? / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protect / read / write**	TreeList	**publi? / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

MaxItemCount property — read / write

Determines the maximum number of items a dropdown list can contain.

```
property MaxItemCount: Integer;
```

Description

Use the MaxItemCount property to specify the maximum number of items stored in the dropdown list of a MRU column's cell. The new value is stored as a new item within the dropdown list when input is confirmed. The most recently used item is placed at the top of the list. When a new item is placed into the list, it shifts other items down and becomes the first item in the list.

If the number of stored items within a dropdown list is equal to the value of the MaxItemCount property, the following operations are performed when a user enters a new value within a cell. The dropdown list hides its lowest item, all other items are shifted down and a new item is placed at the top of the list. All these changes are made when the editor loses focus.

If the value of the MaxItemCount property is 0, there is no limit to the number of list items. When the number of list items exceeds the value of the DropDownRows property, a vertical scroll bar appears at the right edge of the dropdown window.

The default value is **7**.

ShowEllipsis property read / write

Determines whether an additional button is displayed within a MRU column cell.

```
property ShowEllipsis: Boolean;
```

Description

If this property is **True**, you can write an OnButtonClick event handler to perform specific actions when pressing the custom button. Set the ShowEllipsis property to **False** if you do not wish to use and display this additional button.

The default value is **True**.

Copyright © 2000 Developer Express Inc.

TdxTreeListMRUColumn Methods

Derived from TdxTreeListDropDownColumn

EditButtonClick	**protected**	IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

TdxTreeListMRUColumn Events

TdxTreeListMRUColumn

OnButtonClick	**published**

Derived from TdxTreeListPickColumn

OnCloseUp	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnAssignPicture event

Occurs when assigning an image.

```
type
  TdxGraphicEditAssignPictureEvent = procedure(Sender: TObject; var
Picture: TPicture) of object;
property OnAssignPicture: TdxGraphicEditAssignPictureEvent;
```

Description

This event is generated each time a user pastes an image to the edited cell. The Picture parameter specifies the pasted image. Write an OnAssignPicture event handler if you need to display specific picture formats (i.e. JPEG or GIF) in grid cells.

Copyright © 2000 Developer Express Inc.

TdxTreeListBlobColumn

TdxTreeListBlobColumn represents a column that displays and edits BLOB data. The contents of BLOBs are displayed within a sizeable dropdown window.

Unit

dxTLClms

```
TdxTreeListBlobColumn = class(TdxTreeListDropDownColumn);
```

Description

TdxTreeListBlobColumn introduces specific features to manipulate BLOB data. It supports both the display and the editing of Memo BLOBs and the display of Picture BLOBs. It can automatically determine OLE BLOB data.





Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

TdxTreeListDropDownColumn

TdxTreeListBlobColumn Properties

TdxTreeListBlobColumn

AlwaysSaveText	**published / read / write**	MemoWordWrap	**published / read / write**
BlobEditKind	**published / read / write**	PictureAutoSize	**published / read / write**
BlobPaintStyle	**published / read / write**	PictureClipBoardFormat	**public / read / write**
MaxDisplayLength	**published / read / write**	PictureFilter	**published / read / write**
MemoCharCase	**published / read / write**	PictureGraphicClass	**public / read / write**
MemoHideScrollBars	**published / read / write**	PictureTransparency	**published / read / write**
MemoMaxLength	**published / read / write**	PopupHeight	**published / read / write**
MemoOEMConvert	**published / read / write**	PopupWidth	**published / read / write**
MemoScrollBars	**published / read / write**	ShowExPopupItems	**published / read / write**
MemoSelectionBar	**published / read / write**	ShowPicturePopup	**published / read / write**
MemoWantReturns	**published / read / write**	SizeablePopup	**published / read / write**
MemoWantTabs	**published / read / write**		

Derived from TdxTreeListDropDownColumn

ButtonGlyph	**protect / read / write**	ImmediatePopup	**published / read / write**
DropDownRows	**protect / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protect / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protect / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**publi? / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protect / read / write**	TreeList	**publi? / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Copyright © 2000 Developer Express Inc.

AlwaysSaveText property read / write

Specifies whether modified text within a dropdown window is saved.

```
property AlwaysSaveText: Boolean;
```

Description

Set the AlwaysSaveText property to **True** to save modified text when closing the dropdown window.

The default value is **False**.

BlobEditKind property read / write

Determines the type of BLOB data associated with a BLOB column.

```
type
  TdxBlobEditKind = (bekMemo, bekPict, bekOle, bekBlob);
property BlobEditKind: TdxBlobEditKind;
```

Description

Use the BlobEditKind property to specify BLOB type:

Value	Description
bekMemo	Represents memo data.
bekPict	Represents an image.
bekOle	Represents an OLE object.
bekBlob	Represents BLOB data.

The default value is **bekMemo**.

BlobPaintStyle property read / write

Specifies the type of data displayed within a BLOB column.

```
type
  TdxBlobPaintStyle = (bpsDefault, bpsIcon, bpsText);
property BlobPaintStyle: TdxBlobPaintStyle;
```

Description

Use the BlobPaintStyle property to specify the manner in which BLOB data is displayed within a column cell when a dropdown window is closed:

Value	Description
bpsDefault	Identification text in braces is used: (GRAPHIC) - for an image

	(MEMO) - for a memo
bpsIcon	Identification icon is used.
bpsText	Identification text is used.

The default value is **bpsIcon**.

MaxDisplayLength property — read / write

Determines the text length to display in a grid cell.

```
property MaxDisplayLength: Integer;
```

Description

Applies only to BLOB fields of type bkMemo. Specifies the number of symbols used for BLOB identification if BlobPaintStyle is bpsText.

The default value is **255**.

MemoCharCase property — read / write

Determines text case within a BLOB memo column.

```
type
  TEditCharCase = (ecNormal, ecUpperCase, ecLowerCase);
property MemoCharCase: TEditCharCase;
```

Description

You can use this property to force the contents of a BLOB column cell to assume a certain case. The possible MemoCharCase values include:

Value	Meaning
ecLowerCase	Text is converted to lowercase.
ecNormal	Text appears in mixed case.
ecUpperCase	Text is converted to UPPERCASE.

When the MemoCharCase property is set to ecLowerCase or ecUpperCase, case is converted when a user types characters into a cell. Modifying the MemoCharCase property to ecLowerCase or ecUpperCase changes the actual contents of the text, not just its appearance. Because of this, all case information is lost and cannot be recaptured by changing the MemoCharCase property to ecNormal.

The default value is **ecNormal**.

MemoHideScrollBars property — read / write

Specifies whether scroll bars are displayed in a dropdown window.

```
property MemoHideScrollBars: Boolean;
```

Description

If the MemoHideScrollBars property is set to **True**, scroll bars are hidden when not in use. This property is only in effect when the MemoScrollBars property is not set to ssNone.

The default value is **True**.

MemoMaxLength property — read / write

Determines the maximum length of memo text in characters.

```
property MemoMaxLength: Integer;
```

Description

TdxTreeListBlobColumn is intended to represent large amounts of data, including memo fields, in grid cells. The MemoMaxLength property determines the maximum length of the text edited within an in-place editor.

The default value is **0**.

MemoOEMConvert property — read / write

Determines whether the characters typed in the dropdown window of a BLOB column cell are converted from ANSI to OEM and then back.

```
property MemoOEMConvert: Boolean;
```

Description

To make certain that all characters typed into a BLOB column cell can be converted to the OEM character set, set this property to **True**. This forces all characters to be converted from ANSI to OEM and then back to ANSI. Set the MemoOEMConvert property to **False** to avoid excessive processing when mapping to OEM is not needed in your application.

The default value is **False**.

MemoScrollBars property — read / write

Specifies the scroll bars displayed in a dropdown window.

```
type
  TScrollStyle = (ssNone, ssHorizontal, ssVertical, ssBoth);
property MemoScrollBars: TScrollStyle;
```

Description

Use this property to specify the scroll bars to display within a dropdown window:

Value	Meaning
ssNone	Does not include scroll bars.
ssHorizontal	Includes a horizontal scroll bar.
ssVertical	Includes a vertical scroll bar.
ssBoth	Includes both scroll bars.

The default value is **ssBoth**.

MemoSelectionBar property read / write

Specifies whether the selection bar is displayed at the leftmost edge of a dropdown window.

```
property MemoSelectionBar: Boolean;
```

Description

This property is used when a BLOB column is used as a memo column. The Selection Bar is a region at the leftmost edge of the dropdown window within a BLOB column cell. It allows a user to select the entire contents of the BLOB column using a mouse. Set the MemoSelectionBar property to **True** to display it or to **False** to hide it. When the selection bar is hidden, a user can select text lines on a character-by-character basis only.

The default value is **False**.

MemoWantReturns property read / write

Determines whether the RETURN character is accepted during editing.

```
property MemoWantReturns: Boolean;
```

Description

Determines whether the dropdown window of a BLOB column cell accepts the RETURN character when pressing the Enter key on the keyboard.

The default value is **True**.

MemoWantTabs property read / write

Determines whether the TAB character is accepted during editing.

```
property MemoWantTabs: Boolean;
```

Description

Determines whether the dropdown window of a BLOB column cell accepts the TAB character when pressing the TAB key on the keyboard.

The default value is **True**.

Copyright © 2000 Developer Express Inc.

MemoWordWrap property read / write

Specifies whether to wrap words in a dropdown window.

```
property MemoWordWrap: Boolean;
```

Description

Set the MemoWordWrap property to **True** to wrap words within a dropdown window. This property is of use only when a horizontal scroll bar is not displayed.

The default value is **True**.

PictureAutoSize property read / write

Determines whether the dropdown window assumes the same size as a BLOB.

```
property PictureAutoSize: Boolean;
```

Description

If PictureAutoSize is **True**, the dropdown window size changes its size to match that of the BLOB picture.

The default value is **True**.

PictureClipboardFormat property read / write

Specifies the format of Clipboard data.

```
property PictureClipboardFormat: Word;
```

Description

The possible values for Clipboard format include:

Value	Description
CF_BITMAP	Windows bitmap graphics.
CF_METAFILEPICT	Windows metafile graphics.
CF_PICTURE	TPicture type object.

PictureFilter property read / write

Determines the filter used to display specific files in the Files list box when selecting a picture to load.

```
property PictureFilter: string;
```

Description

Used to define file filters for the Load File Dialog window. Enter wildcards and extensions to define your filter. For instance, if this property is set to "*.BMP", only files with a .BMP extension are displayed.

PictureGraphicClass property — read / write

Determines the type of edited image.

```
property PictureGraphicClass: TGraphicClass;
```

Description

This property contains image type: a bitmap, an icon, etc. If the PictureGraphicClass property is nil (the default value), an image is considered to be a bitmap.

PictureTransparency property — read / write

Determines whether a picture can be transparent.

```
type
  TdxGraphicEditTransparency = (gtDefault, gtOpaque, gtTransparent);
property PictureTransparency: TdxGraphicEditTransparency;
```

Description

Possible values include:

Value	Description
gtDefault	Default value.
gtOpaque	A picture is not transparent.
gtTransparent	A picture is transparent.

The default value is **gtDefault**.

PopupHeight property — read / write

Specifies dropdown window height.

```
property PopupHeight: Integer;
```

Description

Use this property to specify the height of a dropdown window in pixels.

The default value is **140**.

PopupWidth property — read / write

Determines dropdown window width.

```
property PopupWidth: Integer;
```

Description

Use this property to specify the width of a dropdown window in pixels.

The default value is **200**.

ShowExPopupItems property — read / write

Specifies whether extended menu items are displayed within a popup menu.

```
property ShowExPopupItems: Boolean;
```

Description

Set the ShowExPopupItems property to **True** to display extended menu items within a popup menu:

Value	Meaning
Save to a file...	Saves a BLOB to a file.
Load from a file...	Loads a BLOB from a file.



The default value is **False**.

ShowPicturePopup property — read / write

Specifies whether to display a popup menu when a user clicks the right button within a dropdown window.

```
property ShowPicturePopup: Boolean;
```

Description

If **True**, clicking the right mouse button within a dropdown window activates a popup menu.



The default value is **False**.

SizeablePopup property — read / write

Determines whether a dropdown window can be sized.

```
property SizeablePopup: Boolean;
```

Description

If **True**, users can change the size of the dropdown window used to display a BLOB. When set to True, the dropdown window includes a resizing grip in its bottom-right corner.

The default value is **True**.

TdxTreeListBlobColumn Methods

Derived from TdxTreeListDropDownColumn

EditButtonClick	**protected**	IsShowButton	**protected**

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
Create	**public**	GetdxInplaceEditClass	**protected**
DefaultAlignment	**public**	GetEnableEditor	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	RestoreDefaults	**public**
DefaultWidth	**public**	RestoreDefaultWidth	**public**
Destroy	**public**	SetName	**protected**
GetBestFit	**public**		

TdxTreeListBlobColumn Events

TdxTreeListBlobColumn

OnAssignPicture	**published**	OnGetGraphicClass	**published**

Derived from TdxTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnAssignPicture event

Occurs when assigning an image.

```
type
  TdxGraphicEditAssignPictureEvent = procedure(Sender: TObject; var
Picture: TPicture) of object;
property OnAssignPicture: TdxGraphicEditAssignPictureEvent;
```

Description

This event is generated each time a user pastes an image to an edited dropdown window. The Picture parameter specifies the pasted image. Write an OnAssignPicture event handler if you need to display specific picture formats (i.e. JPEG or GIF) within grid cells.

OnGetGraphicClass event

Occurs when drawing a graphic column cell.

```
type
  TdxGraphicEditGetGraphicClassEvent = procedure(Sender: TObject; Node:
TdxTreeListNode; var GraphicClass: TGraphicClass) of object;
property OnGetGraphicClass: TdxGraphicEditGetGraphicClassEvent;
```

Description

This event is generated when a BLOB column grid cell is drawn. The Node parameter determines the node to which the drawn cell belongs. The GraphicClass parameter specifies image type.

Write an OnGetGraphicClass event handler if you need to to display different image types in the same BLOB column. Use the GraphicClass parameter to specify different image types for different nodes, i.e. JPEG for grouped nodes and ICON for ordinary nodes.

Copyright © 2000 Developer Express Inc.

TdxTreeListWrapperColumn

TdxTreeListWrapperColumn represents a column that uses different in-place editors within its cells.

Unit

dxTLClms

```
TdxTreeListWrapperColumn = class(TdxTreeListColumn)
```

Description

TdxTreeListWrapperColumn introduces specific features to manipulate different in-place editors within a single column. Using the OnGetReferenceColumn event, you can assign in-place editors from other columns for different cells of a wrapper column.



Hierarchy

TObject

TPersistent

TComponent

TdxTreeListColumn

TdxTreeListWrapperColumn Properties

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**publi? / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protect / read / write**	TreeList	**publi? / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

TdxTreeListWrapperColumn Methods

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
Create	**public**	GetdxInplaceEditClass	**protected**
DefaultAlignment	**public**	GetEnableEditor	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	RestoreDefaults	**public**
DefaultWidth	**public**	RestoreDefaultWidth	**public**
Destroy	**public**	SetName	**protected**
GetBestFit	**public**		

Copyright © 2000 Developer Express Inc.

TdxTreeListWrapperColumn Events

TdxTreeListWrapperColumn

OnGetReferenceColumn	**published**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnGetReferenceColumn event

Occurs each time wrapper cells are created/displayed.

```
type
  TdxTLGetReferenceColumnEvent = procedure(Sender: TObject; Node:
TdxTreeListNode; var Column: TdxTreeListColumn) of object;
property OnGetReferenceColumn: TdxTLGetReferenceColumnEvent;
```

Description

Write an OnGetReferenceColumn event handler to assign the in-place editors of columns defined for this grid instance to a specific wrapper cell. The Node parameter determines the node to which a specific wrapper cell belongs. The Column parameter specifies which in-place editor to use. In the example below, the wrapper cell of the first node uses a hyperlink in-place editor; the wrapper cell of the second node uses a check in-place editor; all other wrapper cells use a pick in-place editor:

```
procedure TForm1.dxTreeList1Column2GetReferenceColumn(Sender: TObject;
  Node: TdxTreeListNode; var Column: TdxTreeListColumn);
begin
  Column := PickColumn;
  if Node.Index = 0 then
    Column := HyperLinkColumn
  else
  if Node.Index = 1 then
    Column := CheckColumn;
end;
```

Grid Columns

TdxDBGridColumn

Represents a grid column.

Unit

dxDBGrid

```
TdxDBGridColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBGridColumn represents a simple text column within a grid. This class is a published variant of TdxDBTreeListColumn. TdxDBGridColumn publishes some properties and events of TdxDBTreeListColumn, namely:

- GroupIndex
- SummaryType
- SummaryField
- SummaryFormat
- SortBySummary
- SummaryGroupName
- SummaryFooterType
- SummaryFooterField
- SummaryFooterFormat
- OnSummary
- OnSummaryFooter
- OnDrawSummaryFooter

Hierarchy

TObject
  TPersistent
    TComponent
      TdxTreeListColumn
        TdxDBTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListColumn

TdxDBTreeListColumn is the common ancestor of all column components in a data-aware grid.

Unit

dxDBCtrl

```
TdxDBTreeListColumn = class(TdxTreeListColumn);
```

Description

TdxDBTreeListColumn encapsulates the fundamental behavior common to all column components of the ExpressQuantumGrid.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn

TdxDBTreeListColumn Properties

TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**publi? / read only**	MinWidth	**published / read / write**
BandIndex	**published / read / write**	ReadOnly	**published / read / write**
Caption	**publis hed / read / write**	RowIndex	**published / read / write**
ColIndex	**published / read / write**	Sizing	**published / read / write**
Color	**published / read / write**	Sorted	**published / read / write**
DisableCaption	**published / read / write**	SortedOrder	**protected / read / write**
DisableCustomizing	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableDragging	**published / read / write**	TabStop	**published / read / write**
DisableEditor	**published / read / write**	TreeList	**publi? / read / write**
Font	**published / read / write**	Visible	**published / read / write**
HeaderAlignment	**published / read / write**	Width	**published / read / write**
HeaderGlyph	**published / read / write**		
HeaderMaxLineCount	**published / read / write**		

ATreeList property — read only

Determines a tree list to which a column belongs.

```
property ATreeList : TCustomdxDBTreeListControl;
```

Description

Specifies a data aware tree list to which a given column belongs.

DisableGrouping property — read / write

Determines whether a column can be a grouped column.

```
property DisableGrouping : Boolean;
```

Description

Use this property to avoid grouping by a given column. If DisableGrouping is True, grid nodes cannot be grouped by the given column.

See Also

TdxDBTreeListColumn.GroupIndex; TCustomdxDBGrid.GroupColumns

Field property — read / write

Determines the field associated with a column.

```
property Field : TField;
```

Description

Every column in a data-aware grid is associated with a dataset field. This property specifies the field that is associated with a column. Use the following code to access the real field value instead of the display value:

```
... := TdxDBGridNode(ANode).VariantValues[AColumn.Index];
```

See Also

TdxDBTreeListColumn.FieldName; TdxDBGridNode.VariantValues

FieldName property — read / write

Determines the name of a field associated with a column.

```
property FieldName : String;
```

Description

Every column of a data-aware grid is associated with a particular dataset field. This property specifies the name of an associated field.

See Also

TdxDBTreeListColumn.Field

GroupIndex property — read / write

Specifies the index of a column in the list of grouped columns.

```
property GroupIndex : Integer;
```

Description

Determines the index of a column among grouped columns. If a column is not a grouped column, its GroupIndex property is equal to -1. If a column's GroupIndex is 0, the column defines the topmost grouped level.

See Also

TdxDBTreeListColumn.DisableGrouping; TCustomdxDBGrid.GroupColumns; TCustomdxDBGrid.RebuildGroupIndexes; TCustomdxDBGrid.AddGroupColumn; TCustomdxDBGrid.InsertGroupColumn; TCustomdxDBGrid.DeleteGroupColumn

MinWidth property — read / write

Determines the minimum width of a column.

```
property MinWidth : Integer;
```

Description

Use this property to specify the minimum width of a column. If a user resizes column width to a value less than MinWidth at runtime, the column will be restored to MinWidth.

SortBySummary property — read / write

Determines whether grid nodes are sorted by a summary value.

```
property SortBySummary : Boolean;
```

Description

If SortBySummary is True, then grid nodes are sorted by a summary value in ascending order. By default, SortBySummary is False and nodes are not sorted.

See Also

TdxDBTreeListColumn.Sorted; TdxDBTreeListColumn.SummaryField; TdxDBTreeListColumn.SummaryFooterField

SummaryField property — read / write

Specifies the grid field whose value is used for summary calculations.

```
property SummaryField : String;
```

Description

Summary is a value that corresponds to each grouped node. The summary value appears next to the text of a grouped node when the grid is grouped.



Unlike the footer summary, simple summary is calculated for a grouping node by column values of child nodes. Use the SummaryType property to specify how summary is calculated. SummaryFormat allows you to define a specific format for the summary text. Write an OnSummary event handler to calculate the summary in your own way.

See Also

TdxDBTreeListColumn.SummaryFooterField; TdxDBTreeListColumn.SummaryType; TdxDBTreeListColumn.SummaryFormat; TdxDBTreeListColumn.OnSummary

SummaryFooterField property

Specifies the grid field used for calculation of the footer summary.

```
property SummaryFooterField : String;
```

Description

Footer summary, unlike simple summary, is a value that is calculated by column values of all nodes. Footer summary appears at the bottom of the grid.



Use the SummaryFooterType property to specify how the footer summary is calculated. SummaryFooterFormat allows you to define a specific format for text of the footer summary. Write an OnSummaryFooter event handler to calculate the footer summary using your own algorithm.

The footer summary is automatically calculated only when the egoLoadAllRecords option is active or the ExpressQuantumGrid is in grouped mode. Otherwise, you should use the OnDrawSummaryFooter event.

Note: *The footer summary is visible only if a given column is visible.*

See Also

TdxDBTreeeListColumn.OnSummaryFooter; TdxDBTreeeListColumn.OnDrawSummaryFooter

SummaryFooterFormat property read / write

Determines the format of a summary footer.

```
property SummaryFooterFormat : String;
```

Description

Use this property to specify text format of a footer summary. For example, your program may calculate the summary of a given set of fields. Setting the SummaryFooterFormat to 'The total sum is $#####,##' will give it a more pleasant look.

Use the following format specifiers in a format string:

- **0** Digit placeholder. If the formatted value does not contain a digit in this position, '0' is stored.
- **#** Digit placeholder. If the formatted value does not contain a digit in this position, nothing is stored.
- **.** Decimal point. The first '.' character in the formatting sting determines position of the decimal separator in the formatted value; other additional '.' characters are ignored. The decimal separator, actually stored in the output string, is determined by Windows Regional Settings.
- **,** Thousand separator. If the formatting string includes one or more ',' characters, the formatted string includes thousand separators. The thousand separator, actually stored in the output string, is determined by Windows Regional Settings.
- **;** Specifies sections for positive, negative and zero values in a format string.

Note: *The footer summary is calculated only when the egoLoadAllRecords option is active or the ExpressQuantumGrid is in grouped mode. Otherwise, you should use the OnDrawSummaryFooter event.*

See Also

TdxDBTreeListColumn.SummaryFooterField; TdxDBTreeListColumn.SummaryFooterType; TdxDBTreeListColumn.OnDrawSummaryFooter

SummaryFooterText property read only

Determines text of a footer summary.

```
property SummaryFooterText : String;
```

Description

Use this property to obtain the text, which corresponds to the footer summary value.

See Also

TdxDBTreeListColumn.SummaryFooterValue; TdxDBTreeListColumn.SummaryFooterFormat; TdxDBTreeListColumn.SummaryFooterType

SummaryFooterType property read / write

Determines footer summary type.

```
type
  TdxSummaryType = (cstNone, cstSum, cstMin, cstMax, cstCount, cstAvg);
property SummaryFooterType : TdxSummaryType;
```

Description

Use this property to specify the way in which a footer summary is calculated. The following values are available:

cstNone	Footer summary is not used.
cstSum	Sums the values of footer summary fields.
cstMin	Displays the minimum value of a footer summary field.
cstMax	Displays the maximum value of a footer summary field.
cstCount	Displays the count of nodes. You do not need to determine the summary field.
cstAvg	Displays the average value of a footer summary field.

Note: *The footer summary is calculated only when the egoLoadAllRecords option is active or the ExpressQuantumGrid is in grouped mode. Otherwise, you should use the OnDrawSummaryFooter event.*

See Also

TdxDBTreeListColumn.SummaryFooterField; TdxDBTreeListColumn.SummaryFooterFormat; TdxDBTreeListColumn.OnDrawSummaryFooter; TdxDBTreeListColumn.SummaryFooterText

SummaryFooterValue property — read only

Determines the value of the footer summary.

```
property SummaryFooterValue : Extended;
```

Description

Use this property to obtain the value displayed in the footer summary.

Note: *The footer summary is calculated only when the egoLoadAllRecords option is active or the ExpressQuantumGrid is in grouped mode.*

See Also

TdxDBTreeListColumn.SummaryFooterText; TdxDBTreeListColumn.SummaryFooterField; TdxDBTreeListColumn.SummaryFooterType

SummaryFormat property — read / write

Determines summary format.

```
property SummaryFormat : String;
```

Description

Use this property to specify the text format of the footer summary. For example, your program may calculate an average value by a given field. Setting the SummaryFormat to 'The average value is $#####,##' will give a more pleasant look for the summary.

Use the following format specifiers in the SummaryFormat:

0 Digit placeholder. If the formatted value does not contain a digit in this position, '0' is stored.

Digit placeholder. If the formatted value does not contain a digit in this position, nothing is stored.

. Decimal point. The first '.' character in the formatting string determines position of the decimal separator in the formatted value; other additional '.' characters are ignored. The decimal separator, actually stored in the output string, is determined by Windows Regional Settings.

, Thousand separator. If the formatting string includes one or more ',' characters, the formatted string includes thousand separators. The thousand separator, actually stored in the output string, is determined by Windows Regional Settings.

; Specifies sections for positive, negative and zero values in a format string.

See Also

TdxDBTreeListColumn.SummaryField; TdxDBTreeListColumn.SummaryType; TdxDBTreeListColumn.SummaryFooterFormat

SummaryGroup property — read / write

Returns a summary group associated with a column.

```
property SummaryGroup: TdxDBGridSummaryGroup;
```

Description

A column can have an linked summary group that determines row summaries when the ExpressQuantumGrid is grouped by that column. This property returns the summary group accosiated with a column. Use this property to modify summary group items.

See Also

TdxDBTreListColumn.SummaryGroupName; TCustomdxDBGrid.GetSummaryGroupByName; TdxDBSummaryItem

SummaryGroupName property — read / write

Specifies the name of a summary group.

```
property SummaryGroupName: string;
```

Description

Use SummaryGroupName to assign the summary group (TdxDBGridSummaryGroup) to a column. If empty, the default summary group (it may be NULL) is used for the summary (grouped column footer and multiple summary on the grouped node).

Copyright © 2000 Developer Express Inc.

Note: *The default summary group is a summary group with the DefaultGroup value equal to True. Only one default summary group can exist at any given point in time. If the name of a column summary group is empty, then the column uses the default summary group. The default summary group may be NULL.*

See Also

TdxDBGridSummaryGroup; TdxDBTreeListColumn.SummaryGroup; TCustomdxDBGrid.GetSummaryGroupByName

SummaryType property — read / write

Determines summary type.

```
type
  TdxSummaryType = (cstNone, cstSum, cstMin, cstMax, cstCount, cstAvg);
property SummaryType : TdxSummaryType;
```

Description

Use this property to specify the way in which a summary is calculated. The following values are available:

cstNone	Summary is not used.
cstSum	Sums the values of summary fields that belong to a grouped node.
cstMin	Displays the minimum value of summary fields in a grouped node.
cstMax	Displays the maximum value of summary fields in a grouped node.
cstCount	Displays the count of child nodes of a grouped node. You do not need to determine the summary field.
cstAvg	Displays the average value of summary fields in a grouped node.

See Also

TdxDBTreeListColumn.SummaryField; TdxDBTreeListColumn.OnSummary; TdxDBTreeListColumn.SummaryFormat; TdxDBTreeListColumn.SummaryFooterType

VariantType property — read only

Returns the data type of a summary field.

```
property VariantType : Integer;
```

Description

Returns the data type of a summary field. The possible values include:

varUnknown	Unknown or undetermined.
varString	Character or string field, boolean field or fixed number of bytes (binary storage).

varSmallint	16-bit integer field.
varInteger	32-bit integer field or 16-bit unsigned integer field.
varDouble	Floating-point numeric field.
varCurrency	Money field or Binary-Coded Decimal field.
varDate	Date field, Time field or Date and time field.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListColumn Methods

TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

AlwaysStoredValue method

Determines whether an active inplace editor always refreshes when a user changes data in a field.

```
function AlwaysStoredValue: Boolean; virtual;
```

Description

A user can post changes to the dataset via other data-aware conrols when an inplace editor is active in a grid column. If data in the edited field changes, the inplace editor has to refresh itself. If AlwaysStoredValue returns True, the inplace editor redraws regardless of whether data was changed. By default, AlwaysStoredValue returns False. Descendants override this method to provide specific fuctionality for their inplace editors.

DoDrawColumn method

Generates an OnCustomDraw event.

```
procedure DoDrawColumn(ACanvas: TCanvas; ARect : TRect;
ANode:TdxTreeListNode; const AText : String; AFont : TFont; var AColor :
TColor; ASelected, AFocused : Boolean; var ADone : Boolean; AllowCustomDraw
: Boolean);  virtual;
```

Description

This method is called when a cell of a data-aware tree list must be drawn. DoDrawColumn calls the OnCustomDraw event handler, passing to it the ACanvas, ARect, ANode and other parameters. Descendants override this method to draw themselves.

ACanvas and **ARect** specify respectively the surface and rectanlge for drawing.

ANode determines a node to which a cell belongs.

AText determines the text which should be drawn within a cell.

AFont and **AColor** specify font and color.

ASelected determines whether the drawing node is selected.

AFocused specifies whether the drawing cell is focused.

ADone determines whether the drawing procedure paints the entire cell.

AllowCustomDraw is not used currently. It is intended for future use.

See Also

TdxDBTreeListColumn.OnCustomDraw;TdxDBTreeListColumn.OnCustomDrawHeader

GetDisplayText method

Returns the text for a particular cell.

```
function GetDisplayText: String;  virtual;
```

Description

Descendants override this method to specify the text that appears within a particular node.

GetdxInplaceEditClass method

Returns the class of inplace editors for a column.

```
type
  TdxInplaceEditClass = class of TdxInplaceEdit;
function GetdxInplaceEditClass: TdxInplaceEditClass;  virtual;
```

Description

This function is used internally. Each column type includes a specific inplace editor. This method returns the inplace editor class associated with a column. For TdxDBTreeListColumn, the GetdxInplaceEditClass method returns TdxInplaceTextEdit. Descendants override this method to obtain specific inplace editor type. The following list contains columns and their inplace editors:

TdxDBTreeListColumn	-	TdxInplaceTextEdit
TdxDBTreeListButtonColumn	-	TdxInplaceDBTreeListButtonEdit
TdxDBTreeListMaskColumn	-	TdxInplaceDBTreeListMaskEdit
TdxDBTreeListDateColumn	-	TdxInplaceDBTreeListDateEdit
TdxDBTreeListTimeColumn	-	TdxInplaceDBTreeListTimeEdit
TdxDBTreeListCheckColumn	-	TdxInplaceDBTreeListCheckEdit
TdxDBTreeListImageColumn	-	TdxInplaceDBTreeListImageEdit
TdxDBTreeListPickColumn	-	TdxInplaceDBTreeListPickEdit
TdxDBTreeListSpinColumn	-	TdxInplaceDBTreeListSpinEdit
TdxDBTreeListLookupColumn	-	TdxInplaceDBTreeListLookupEdit
TdxDBTreeListCalcColumn	-	TdxInplaceDBTreeListCalcEdit
TdxDBTreeListBlobColumn	-	TdxInplaceDBTreeListBlobEdit

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCurrencyColumn	-	TdxInplaceDBTreeListCurrencyEdit
TdxDBTreeListHyperLinkColumn	-	TdxInplaceDBTreeListhyperLinkEdit
TdxDBTreeListMemoColumn	-	TdxInplaceDBTreeListMemoEdit
TdxDBTreeListGraphicColumn	-	TdxInplaceDBTreeListGraphicEdit
TdxDBTreeListPopupColumn	-	TdxInplaceDBTreeListPopupEdit
TdxDBTreeListExtLookupColumn	-	TdxInplaceDBTreeListExtLookupEdit

GetGroupText method

Returns the text of a grouping node.

```
function GetGroupText(const Value : String): String;  virtual;
```

Description

Descendants override this method to specify the text for a grouping node according to the passed Value.

GetSummaryFooterText method

Returns the text of the footer summary.

```
function GetSummaryFooterText: String;  virtual;
```

Description

This method is used to obtain the text of the footer summary of a column.

GetSummaryText method

Returns the text of the node summary.

```
function GetSummaryText(ANode : TdxTreeListNode): String;  virtual;
```

Description

This method is used to access the text of the node summary. The ANode parameter determines a node from which to obtain summary text.

See Also

TdxDBGridNode.SummaryValue; TdxDBGridNode.SummaryValues

IsBlobColumn method

Determines whether a column can be used for the display of BLOB fields.

```
function IsBlobColumn: Boolean; virtual;
```

Description

Descendants override this method to specify whether a column works with BLOB fields. TdxDBTreeListColumn IsBlobColumn always returns False, since TdxDBTreeListColumn cannot be used for BLOB fields.

See Also

TdxDBTreeListDropDownColumn.Field

Copyright © 2000 Developer Express Inc.

TdxDBTreeListColumn Events

TdxDBTreeListColumn

OnChangeName	**public**	OnGetText	**published**
OnCustomDraw	**published**	OnSummary	**protected**
OnCustomDrawHeader	**published**	OnSummaryFooter	**protected**
OnDrawSummaryFooter	**protected**		

Derived from TdxTreeListColumn

OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**

OnChangeName event

Occurs when changing the name of a column.

```
type
  TNotifyEvent = Procedure(Sender: TObject) of object;
property OnChangeName: TNotifyEvent;
```

Description

Write an OnChange event handler to perform specific actions when chaging the name of a column.

OnCustomDraw event

Occurs when a column needs to be repainted.

```
type
  TCustomDrawEvent = procedure(Sender : TObject; ACanvas : TCanvas; ARect :
TRect; ANode : TdxTreeListNode; AColumn : TdxDBTreeListColumn; const AText
: String; AFont : TFont; var AColor : TColor; ASelected, AFocused :
Boolean; var ADone : Boolean ) of object;
property OnCustomDraw : TCustomDrawEvent;
```

Description

Write an OnCustomDraw event handler to draw the contents of all or particular cells in a data-aware grid. Draw a column using TCanvas methods. The ARect parameter indicates location of a cell on the canvas:

ANode and **AColumn**	Node and column of a cell.
AText	Context of a cell.
AFont and **AColor**	Font and color used to draw a cell.
ASelected	Determines whether a node to which a cell belongs is selected.
AFocused	Specifies whether a node to which a cell belongs is focused.

ADone Determines whether the OnCustomDraw event handler draws the entire cell. Setting ADone to True means that the event handler performs entire drawing and the default procedure is not called.

Note: *OnCustomDraw is obsolete with the release of the ExpressQuantumGrid. Use the OnCustomDrawCell event instead.*

See Also

TdxDBTreeListColumn.OnCustomDrawHeader; TdxDBTreeListColumn.OnDrawsummaryFooter; CustomDrawDBColumn.CustomDrawColumn; TdxTreeListColumn.OnCustomDrawCell

OnCustomDrawHeader event

Occurs when drawing column caption.

```
type
  TCustomDrawHeaderEvent = procedure(Sender : TObject; ACanvas : TCanvas;
var ARect : TRect; AColumn : TdxDBTreeListColumn; var ADone : Boolean) of
object;
property OnCustomDrawHeader : TCustomDrawHeaderEvent;
```

Description

Write an OnCustomDraw event handler to draw a column header yourself. ACanvas determines the canvas for drawing. AColumn determines the column that is drawn. ARect specifies a rectangle where to draw. ADone determines whether the event handler performs full drawing. If the event handler sets ADone to True, the event handler draws the column header entirely and the default drawing procedure is not called.

Note: *This event is obsolete with the release of the ExpressQuantumGrid. Use OnCustomDrawColumnHeader instead.*

See Also

TdxDBTreeListColumn.OnCustomDraw; TdxDBTreeListColumn.OnDrawSummaryFooter; TdxTreeListColumn.OnCustomDrawColumnHeader

OnDrawSummaryFooter event

Occurs when necessary to draw a summary footer.

```
type
  TdxDrawSummaryFooter = procedure(Sender : TObject; ACanvas : TCanvas;
ARect : TRect; var AText : String; var AAlignment: TAlignment; AFont :
TFont; var AColor : TColor; var ADone : Boolean ) of object;
property OnDrawSummaryFooter : TdxDrawSummaryFooter;
```

Description

Write an OnDrawSummaryFooter event handler to draw a summary footer yourself. ACanvas determines a canvas for drawing. ARect specifies a rectangle where to draw. AText is the text that is drawn in the summary footer. AAlignment determines text alignment within the rectangle. AFont and AColor specify respectively the font and color. ADone determines whether the event handler fully

performs drawing. If the event handler sets ADone to True, the event handler entirely draws the column header and the default drawing procedure is not called.

See Also

TdxDBTreeListColumn.OnCustomDraw; TdxDBTreeListColumn.OnCustomDrawHeader; TdxDBTreeListColumn.OnGetText

OnGetText event

Occurs when accessing column text.

```
type
  TColumnGetText = procedure(Sender : TObject; ANode: TdxTreeListNode; var
AText : String) of object;
property OnGetText : TColumnGetText;
```

Description

Write OnGetText to specify the text that appears within a particular cell. ANode determines the node to which a cell belongs. AText determines text within a cell.

See Also

TdxDBGridColumn.OnCustomDraw; TdxDBGridColumn.OncustomDrawHeader; TdxDBGridColumn.OnDrawSummaryFooter

OnSummary

Occurs when calculating the summary value.

```
type
  TdxSummaryEvent = procedure(Sender : TObject; DataSet : TDataSet; var
Value : Extended) of object;
property OnSummary : TdxSummaryEvent;
```

Description

Write an OnSummary event handler to calculate summary on several dataset fields. The Value parameter determines the value that will be used when calculating the summary.

Note: *TdxDBTreeListColumn OnSummary is called before the TCustomdxDBGrid OnSummaryNode event.*

See Also

TdxDBTreeListColumn.OnCustomDraw; TdxDBTreeListColumn.OnCustomDrawHeader; TdxDBTreeListColumn.OnGetText

OnSummaryFooter event

Occurs when calculating the footer summary.

```
type
```

```
  TdxSummaryEvent = procedure(Sender : TObject; DataSet : TDataSet; var
Value : Extended) of object;
property OnSummaryFooter : TdxSummaryEvent;
```

Description

Write an OnSummaryFooter event handler to calculate the footer summary on several dataset fields. The Value parameter determines the value that will be used when calculating the summary.

Note: *This event is generated only when the egoLoadAllRecords option is active or when the ExpressQuantumGrid is in grouped mode. Otherwise, you should use the OnDrawSummaryFooter event to calculate and draw the footer summary.*

See Also

TdxDBTreeListColumn.SummaryFooterField; TdxDBTreeListColumn.SummaryFooterType; TdxDBTreeListColumn.SummaryFooterFormat; TdxDBTreeListColumn.OnSummary; TCustomdxDBgrid.OnSummaryNode; TdxDBtreeListColumn.OnDrawSummaryFooter

Copyright © 2000 Developer Express Inc.

TdxDBGridMaskColumn

Unit

dxDBGrid

```
TdxDBGridMaskColumn = class(TdxDBTreeListMaskColumn);
```

Description

TdxDBGridMaskColumn derives all methods and properties from TdxDBTreeListMaskColumn and publishes some of them. It does not introduce any new methods or properties. TdxDBTGridMaskColumn publishes the following properties and events:

- ? GroupIndex
- ? SummaryType
- ? SummaryField
- ? SummaryFormat
- ? SortBySummary
- ? SummaryGroupName
- ? SummaryFooterType
- ? SummaryFooterField
- ? SummaryFooterFormat
- ? OnSummary
- ? OnSummaryFooter
- ? OnDrawSummaryFooter

Hierarchy

TObject
  TPersistent
    TComponent
      TdxTreeListColumn
        TdxDBTreeListColumn
          TdxDBTreeListMaskColumn

TdxDBTreeListMaskColumn

TdxDBTreeListMaskColumn displays masked text and allows editing of cell data via TdxInplaceDBTreeListMaskEdit.

Unit

dxDBCtrl

```
TdxDBTreeListMaskColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListMaskColumn is directly inherited from TdxDBTreeListColumn. It allows users to interact with a masked inplace editor. TdxDBTreeListMaskColumn contains two properties for the mask inplace editor.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListMaskColumn Properties

TdxDBTreeListMaskColumn

EditMask	**published**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read/ write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read/ write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MinWidth	**published / read / write**
BandIndex	**published / read / write**	ReadOnly	**published / read / write**
Caption	**published / read / write**	RowIndex	**published / read / write**
ColIndex	**published / read / write**	Sizing	**published / read / write**
Color	**published / read / write**	Sorted	**published / read / write**
DisableCaption	**published / read / write**	SortedOrder	**protected / read / write**
DisableCustomizing	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableDragging	**published / read / write**	TabStop	**published / read / write**
DisableEditor	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	Visible	**published / read / write**
HeaderAlignment	**published / read / write**	Width	**published / read / write**
HeaderGlyph	**published / read / write**		
HeaderMaxLineCount	**published / read / write**		

EditMask property — read / write

Specifies the mask that represents valid text for a masked edit column.

```
property EditMask : String;
```

Description

Use EditMask to restrict the characters a user can enter into a masked edit column to valid characters and formats. If a user attempts to enter an invalid character, the edit control does not accept it.

TdxDBTreeListMaskColumn Methods

TdxDBTreeListMaskColumn

DefaultEditMask	**public**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
AssignedDrawCellEvent	**protected**	GetdxInplaceEditClass	**protected**
Create	**public**	GetEnableEditor	**protected**
DefaultAlignment	**public**	GetMaxRowHeight	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	NeedShowButtonEdit	**protected**
DefaultWidth	**public**	RestoreDefaults	**public**
Destroy	**public**	RestoreDefaultWidth	**public**
DoDrawCell	**protected**	SetName	**protected**
GetBestFit	**public**		

DefaultEditMask method

Returns the default editing mask for TdxDBTreeListMaskColumn.

```
function DefaultEditMask: String;
```

Description

If a column has an associated field, the DefaultEditMask method returns the EditMask property of the field. Otherwise, it returns an empty string.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListMaskColumn Events

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnSummary	**protected**
OnCustomDrawHeader	**published**	OnSummaryFooter	**protected**
OnDrawSummaryFooter	**protected**		
OnGetText	**published**		

Derived from TdxTreeListColumn

OnCustomDrawCell	**publis hed**
OnCustomDrawColumnHeader	**published**

TdxDBGridBlobColumn

Unit

dxGrClms

```
TdxDBGridBlobColumn = class(TdxDBTreeListBlobColumn);
```

Description

TdxDBGridBlobColumn represents BLOB fields, such as memo or graphic fields, in the ExpressQuantumGrid.



TdxDBGridBlobColumn derives all the methods and properties of TdxDBTreeListBlobColumn and publishes some of them. This represents the only difference between these classes. TdxDBGridBlobColumn publishes the following properties and events:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListBlobColumn

TdxDBTreeListBlobColumn

TdxDBTreeListBlobColumn represents BLOB fields in the ExpressQuantumGrid.

Unit

dxDBTLCl

```
TdxDBTreeListBlobColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListBlobColumn represents large data such as images or memo fields. TdxDBTreeListBlobColumn uses TdxInplaceDBTreeListBlobEdit for data display.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListBlobColumn Properties

TdxDBTreelistBlobColumn

BlobKind	**published / read / write**	MemoWordWrap	**published / read / write**
BlobPaintStyle	**published / read / write**	PictureAutoSize	**published / read / write**
MaxDisplayLength	**published / read / write**	PictureFilter	**published / read / write**
MemoCharCase	**published / read / write**	PictureTransparency	**published / read / write**
MemoHideScrollBars	**published / read / write**	PopupHeight	**published / read / write**
MemoMaxLength	**published / read / write**	PopupWidth	**published / read / write**
MemoScrollBars	**published / read / write**	ShowPicturePopup	**published / read / write**
MemoSelectionBar	**published / read / write**	ShowExPopupItems	**published / read / write**
MemoWantReturns	**published / read / write**	SizeablePopup	**published / read / write**

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**published / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

BlobKind property read / write

Determines BLOB field kind associated with TdxDBTreeListBlobColumn.

```
type
  TdxBlobKind = (bkAuto, bkBlob, bkMemo, bkPict, bkOle);
property BlobKind : TdxBlobKind;
```

Description

Use this property to identify a BLOB type:

bkAuto	TdxDBTreeListBlobColumn tries to automatically to identify BLOB type.
bkBlob	Represents a BLOB field.
bkMemo	Represents a memo field.
bkPict	Represents an image field.
bkOle	Represents an OLE object.

BlobPaintStyle property read / write

Determines how a BLOB is identified within grid cells.

```
type
  TdxBlobPaintStyle = (bpsDefault, bpsIcon, bpsText);
property BlobPaintStyle : TdxBlobPaintStyle;
```

Description

Use this property to specify identification of BLOBs within ExpressQuantumGrid cells.

bpsDefault	Uses text in braces for identification: (GRAPHIC) - for image (MEMO) - for memo
bpsIcon	Uses an icon for identification
bpsText	Uses text for identification

MaxDisplayLength property read / write

Determines the length of text to display in a grid cell.

```
property MaxDisplayLength : Integer;
```

Description

Applies only to BLOB fields of type bkMemo. Specifies the number of symbols used for BLOB identification if BlobPaintStyle is bpsText.

Copyright © 2000 Developer Express Inc.

See Also

TdxDBTreeListBlobColumn.MemoScrollBars; TdxDBTreeListBlobColumn.MemoWordWrap

MemoCharCase property — read / write

Determines the text case within a BLOB memo column.

```
type
  TEditCharCase = (ecNormal, ecUpperCase, ecLowerCase);
  property MemoCharCase: TEditCharCase;
```

Description

You can use this property to force the contents of a BLOB column to assume a certain case mode. Possible MemoCharCase values include:

Value	Meaning
ecLowerCase	The text is converted to lowercase.
ecNormal	The text appears in mixed case.
ecUpperCase	The text is converted to UPPERCASE.

When the MemoCharCase property is set to ecLowerCase or ecUpperCase, the case is converted when a user types characters into a cell. Modifying the MemoCharCase property to ecLowerCase or ecUpperCase changes the actual contents of the text, not just its appearance on-screen. All case information is lost and cannot be recaptured by changing the MemoCharCase property to ecNormal.

The default value is **ecNormal**.

MemoHideScrollBars property — read / write

Specifies whether scroll bars are displayed in a dropdown window.

```
property MemoHideScrollBars: Boolean;
```

Description

If the MemoHideScrollBars property is set to **True**, scroll bars are hidden when not in use. This property is effective only when the MemoScrollBars property is not set to ssNone.

The default value is **True**.

MemoMaxLength property — read / write

Determines the maximum length of a memo text in characters.

```
property MemoMaxLength: Integer;
```

Description

The intent of TdxDBTreeListBlobColumn is to represent large-sized data including memo fields in grid cells. The MemoMaxLength property determines the maximum length of text edited in an inplace editor.

See Also

TdxDBTreeListBlobColumn.MemoScrollBars

MemoSelectionBar property — read / write

Specifies whether the selection bar is displayed at the leftmost edge of a dropdown window.

```
property MemoSelectionBar: Boolean;
```

Description

This property is used when a BLOB editor is used as a memo editor. Selection bar is a region at the leftmost edge of a dropdown window of a BLOB editor. It allows a user to select entire text lines using the mouse. Set the MemoSelectionBar property to **True** to display it or to **False** to hide it. When the selection bar is hidden, a user can select text lines on a character-by-character basis only.

The default value is **False**.

MemoScrollBars property — read / write

Specifies the scroll bars displayed in a dropdown window.

```
type
  TScrollStyle = (ssNone, ssHorizontal, ssVertical, ssBoth);
property MemoScrollBars : TScrollStyle;
```

Description

Use this property to specify scroll bars for a dropdown window when it displays memo text:

ssNone	Does not include scroll bars.
ssHorizontal	Includes a horizontal scroll bar.
ssVertical	Includes a vertical scroll bar.
ssBoth	Includes both a vertical and horizontal scroll bar.

MemoWantReturns property — read / write

Determines whether the RETURN character is accepted during editing.

```
property MemoWantReturns: Boolean;
```

Description

Determines whether the dropdown window of a BLOB column cell accepts the RETURN character when pressing the Enter key on the keyboard.

The default value is **True**.

MemoWordWrap property read / write

```
property MemoWordWrap : Boolean;
```

Description

Determines whether to wrap words in a dropdown window when it displays a memo.

PictureAutoSize property read / write

Determines whether a dropdown window takes the same size as a BLOB.

```
property PictureAutoSize : Boolean;
```

Description

If PictureAutoSize is True, dropdown window size changes to fit the BLOB picture size.

See Also

TdxDBTreeListBlobColumn.SizeablePopup

PictureFilter property read / write

Determines the filter used to display specific files in the Files list box when selecting a picture to load.

```
property PictureFilter: string;
```

Description

Used to define file filters for the Load File Dialog window. Enter wildcards and extensions to define your filter. For instance, if this property is set to "*.BMP", only files with a .BMP extension are displayed.

PictureTransparency property read / write

Determines whether a picture can be transparent.

```
type
  TdxGraphicEditTransparency = (gtDefault, gtOpaque, gtTransparent);
property PictureTransparency: TdxGraphicEditTransparency;
```

Description

The possible values for the PictureTransparency property include:

Value	Meaning
gtDefault	Default
gtOpaque	A picture is not transparent.

gtTransparent A picture is transparent.

The default value is **gtDefault**.

PopupHeight property read / write

```
property PopupHeight : Integer;
```

Description

Use this property to specify the height of a dropdown window.

See Also

TdxDBTreeListBlobColumn.PopupWidth

PopupWidth property read / write

```
property PopupWidth : Integer;
```

Description

Use this property to specify the width of a dropdown window.

See Also

TdxDBTreeListBlobColumn.PopupHeight

ShowPicturePopup property read / write

Determines whether to display a popup menu when a user clicks the right button within a dropdown window.

```
property ShowPicturePopup : Boolean;
```

Description

If True, clicking the right mouse button on a dropdown window activates a popup menu.

Copyright © 2000 Developer Express Inc.



ShowExPopupItems property — read / write

Specifies whether extended menu items are displayed within the popup menu.

```
property ShowExPopupItems: Boolean;
```

Description

Set the ShowExPopupItems property to True to show extended menu items within the popup menu:

Save to a file ...	Saves a blob to a file
Load from a file...	Loads a blob from a file



SizeablePopup property read / write

Determines whether a dropdown window is sizable.

```
property SizeablePopup : Boolean;
```

Description

If True, users can change the size of a dropdown window used to display a BLOB. If so, the dropdown window includes a grip in its bottom right corner.

See Also

TdxDBTreeListBlobColumn.PictureAutoSize

Copyright © 2000 Developer Express Inc.

TdxDBTreeListBlobColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

TdxDBTreeListBlobColumn Events

TdxDBTreeListBlobColumn

OnAssignedPicture	**published**
OnGetGraphicClass	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**
OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**
OnValidate	**published**

OnAssignedPicture event

This event occurs when a user or a program assigns a new a picture to TdxDBTreeListBlobColumn.

```
type
  TdxGraphicEditAssignPictureEvent = procedure(Sender: TObject; var
Picture: TPicture) of object;
property OnAssignPicture: TdxGraphicEditAssignPictureEvent;
```

Description

The intent of TdxDBTreeListBlobColumn is to represent any blob data including graphics in grid cells. The OnAssignPicture is generated when a user or a program pastes a new graphics to the TdxDBTreeListBlobColumn. The Picture parameter determines the image being pasted.

See Also

TdxDBTreeListBlobColumn.OnGetGraphicClass

OnGetGraphicClass event

```
type
  TGraphicClass = class of TGraphic;
  TdxGraphicEditGetGraphicClassEvent = procedure(Sender: TObject; Node:
TdxTreeListNode; var GraphicClass: TGraphicClass) of object;
property OnGetGraphicClass: TdxGraphicEditGetGraphicClassEvent;
```

Description

The intent of TdxDBTreeListBlobColumn is to represent blob data (including graphics) in grid cells. The OnGetGraphicsClass event is generated when a cell is drawn. The GraphicClass parameter determines the type of image. Write an OnGetGraphicClass event handler if the dataset stores specific image formats.

See Also

TdxDBTreeListBlobColumn.OnAssignedPicture

TdxDBGridButtonColumn

Unit

dxGrClms

```
TdxDBGridButtonColumn = class(TdxDBTreeListButtonColumn);
```

Description

TdxDBGridButtonColumn represents a column with a custom button.



TdxDBGridButtonColumn derives all the methods and properties of TdxDBTreeListButtonColumn and publishes some of them. This represents the only difference between these classes. TdxDBGridButtonColumn publishes the following properties and events:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListButtonColumn

TdxDBTreeListButtonColumn

TdxDBTreeListButtonColumn represents a column with a button.

Unit

dxDBTLCl

```
TdxDBTreeListButtonColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListButtonColumn represents a column with a custom button. Use the EditButtonStyle property to customize the look of the button. TdxDBTreeListButtonColumn uses TdxInplaceDBTreeListButtonEdit for data editing.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListButtonColumn Properties

TdxDBTreeListButtonColumn

ButtonOnly	**published / read / write**	EditButtonStyle	**published / read / write**
Buttons	**published / read / write**	Glyph	**published / read / write**
ClickKey	**published / read / write**	HideEditCursor	**published / read / write**

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read only**	ImmediatePopup	**protected / read only**
DropDownRows	**protected / read only**	PopupAlignment	**protected / read only**
DropDownWidth	**protected / read only**	PopupBorder	**protected / read only**
ImmediateDropDown	**protected / read only**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

ButtonOnly property — read / write

Determines whether a button occupies the entire cell.

Copyright © 2000 Developer Express Inc.

```
property ButtonOnly: Boolean;
```

Description

TdxDBTreeListButtonColumn implements a button that is used to modify data in ExpressQuantumGrid cells. If the ButtonOnly property is True, the edit button occupies the whole area of a grid cell. By default, ButtonOnly is False.

See Also

TCustomdxDBGrid.OptionsEx; TdxDBTreeListButtonColumn.EditButtonStyle; TdxDBTreeListButtonColumn.IsShowButton; TdxDBTreeListButtonColumn.ShowButtonStyle

Buttons property — read / write

Determines a collection of buttons.

```
property Buttons: TdxEditButtons;
```

Description

In-place editors that support button controls can contain several buttons. Use the Buttons property to manage them. At design or runtime, a user can add or delete edit buttons and modify their appearance.

ClickKey property — read / write

Specifies a short cut to activate a button.

```
property ClickKey : TShortCut;
```

Description

Use this property to specify a keyboard short cut which activates a button.

See Also

TdxDBTreeListButtonColumn.OnEditButtonClick

EditButtonStyle property — read / write

Determines the style of the edit button.

```
type
  TdxEditButtonStyle = (ebsSimple, ebsEllipsis, ebsDown, ebsGlyph);
property EditButtonStyle : TdxEditButtonStyle;
```

Description

Use this property to define the edit button style.

ebsSimple No button appears.

ebsEllisis Ellipsis ('…') appear on the button.

ebsDown	Displays a down arrow on the button similar to a combo box.
ebsGlyph	Displays a bitmap, specified by the Glyph property.

See Also

TdxDBTreeListButtonColumn.ButtonOnly; TdxDBTreeListButtonColumn.Glyph; TdxDBTreeListButtonColumn.ShowButtonStyle

Glyph property — read / write

Specifies the bitmap drawn on an editor button.

```
property Glyph : TBitmap;
```

Description

Use this property to specify the image used on the surface of an editor button when EditButtonStyle equals ebsGlyph.

See Also

TdxDBTreeListButtonColumn.EditButtonStyle

HideEditCursor property — read / write

Determines whether to display a cursor within TdxDBTreeListButtonColumn.

```
property HideEditCursor : Boolean;
```

Description

If True, a cursor is not displayed within a focused TdxDBTreeListButtonColumn.

ShowButtonStyle — read / write

Determines the appearance and style of an edit button.

```
type
  TdxShowButtonStyle = (sbDefault, sbAlways, sbNone);
property ShowButtonStyle: TdxShowButtonStyle;
```

Description

TdxDBTreeListButtonColum implements a button that is used to modify data in grid cells. By default, the edit button is displayed if a node, to which a cell belongs, has focus. The ShowButtonStyle determines additional appearance styles for the edit button:

sbDefault	The edit button appears when a node, to which a cell belongs, is focused.
sbAlways	The edit buttons appear within all cells of the button column.
sbNone	The edit button is displayed only within an edited cell.

Copyright © 2000 Developer Express Inc.

Note: *ShowButtonStyle is used only when the egoShowButtonAlways option of the ExpressQuantumGrid is active.*

See Also

TCustomdxDBGrid.OptionsEx; TdxDBTreeListButtonColumn.EditButtonStyle; TdxDBTreeListButtonColumn.IsShowButton; TdxDBTreeListButtonColumn.ButtonOnly

TdxDBTreeListButtonColumn Methods

Derived from TdxDBTreeListDropDownColumn

IsShowButton	**protected**
EditButtonClick	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

Copyright © 2000 Developer Express Inc.

TdxDBTreeListButtonColumn Events

TdxDBTreeListButtonColumn

OnButtonClick	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange		OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	

OnButtonClick event

Occurs when clicking an edit button within a cell.

```
type
  TdxEditButtonClickEvent = procedure (Sender: TObject; AbsoluteIndex:
Integer) of object;
property OnButtonClick: TdxEditButtonClickEvent;
```

Description

Write an OnButtonClick event handler to perform specific actions when clicking a button within a cell. The AbsoluteIndex parameter determines the index of the pressed button. This index is zero-based.

TdxDBGridCalcColumn

Unit

dxGrClms

```
TdxDBGridCalcColumn = class(TdxDBTreeListCalcColumn);
```

Description

TdxDBGridCalcColumn allows you to use a calculator as an inplace editor.



TdxDBGridCalcColumn derives all the methods and properties of TdxDBTreeListCalcColumn and publishes some of them. This represents the only difference between these classes. TdxDBGridCalcColumn publishes the following properties and events:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListCalcColumn

TdxDBTreeListCalcColumn

TdxDBTreeListCalcColumn provides a column with a dropdown calculator.

Unit

dxDBTLCl

```
TdxDBTreeListCalcColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListCalcColumn represents a column with a dropdown calculator. TdxDBTreeListCalcColumn uses the TdxInplaceCalcEdit inplace editor (an edit field with a calculator) for data editing. TdxDBTreeListCalcColumn is the base class for TdxDBGridCalcColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

TdxDBTreeListCalcColumn Properties

TdxDBTreeListCalColumn

BeepOnError	**published / read / write**	QuickClose	**published / read / write**
ButtonStyle	**published / read / write**	ShowButtonFrame	**published / read / write**
Precision	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

BeepOnError proeprty — read / write

Detemrines whether to generate a beep on errors.

Copyright © 2000 Developer Express Inc.

```
property BeepOnError : Boolean;
```

Description

If True, a column beeps on a calculation errors.

ButtonStyle property — read / write

Determines calculator button style.

```
type
  TdxButtonStyle = (bsStandard, bsFlat, bsExtraFlat);
property ButtonStyle : TdxButtonStyle;
```

Description

Use this property to specify the style of calculator buttons:

bsStandard	Standard 3D look.
bsFlat	Flat look.
bsExtraFlat	Flattened look similar to toolbars buttons.

Precision property — read / write

Specifies the number of digits (accuracy) used to store calculated values.

```
property Precision : Byte;
```

Description

Use this property to specify the total number of digits used during calculations. The default value for Precision is 13.

QuickClose property — read / write

Specifies whether the popup calculator window is closed when pressing the '=' key.

```
property QuickClose: Boolean;
```

Description

If the QuickClose property is set to **True**, the dropdown calculator closes when a user presses the '=' keyboard button. By default, the QuickClose property is set to **False** and pressing the '=' key does not close it. In any instance, clicking the '=' button of the dropdown calculator DOES NOT close it.

ShowButtonFrame property — read / write

Specifies whether to display a frame around buttons.

```
property ShowButtonFrame : Boolean;
```

Description

If ShowButtonFrame is True, an ellipse is drawn around the caption of a button. The look of a button frame is especially attractive when ButtonStyle is of bsExtraFlat.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCalcColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

TdxDBTreeListCalcColumn Events

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange		OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	

Copyright © 2000 Developer Express Inc.

TdxDBGridCheckColumn

Unit

dxGrClms

```
TdxDBGridCheckColumn = class(TdxDBTreeListCheckColumn);
```

Description

TdxDBGridCheckColumn represents a column with a check box. This column is used to edit Boolean fields.

TdxDBGridCheckColumn derives all the methods and properties of TdxDBTreeListCheckColumn and publishes some of them, namely:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListCheckColumn

TdxDBGridCheckColumn Properties

TdxDBGridCheckColumn

DisplayChecked	**published / read / write**	DisplayUnChecked	**published / read / write**
DisplayNull	**published / read / write**		

Derived from TdxDBTreeListCheckColumn

AllowGrayed	**published / read / write**	ValueChecked	**published / read / write**
Border3D	**published / read / write**	ValueGrayed	**published / read / write**
Glyph	**published / read / write**	ValueUnchecked	**published / read / write**
GlyphCount	**published / read / write**		
ShowNullFieldStyle	**published / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Copyright © 2000 Developer Express Inc.

DisplayChecked property read / write

Specifies the value of a column when the check box is checked.

```
property DisplayChecked : string;
```

Description

When nodes are grouped by the check column, an expression should be written for the grouped node. The DisplayChecked property determines the text that is used when the check box is checked.

See Also

TdxDBGridCheckColumn.DisplayNull;TdxDBGridCheckColumn.DisplayUnchecked

DisplayNull property read / write

Specifies the value of a column when the check box is neither checked nor unchecked.

```
property DisplayNull : string;
```

Description

When nodes are grouped by the check column, an expression should be written for the grouped node. The DisplayNull property determines text that is used when the check box is neither checked nor unchecked.

See Also

TdxDBGridCheckColumn.DisplayCheckel;TdxDBGridCheckColumn.DisplayUnchecked

DisplayUnChecked property read / write

Specifies the value of a column when the check box is unchecked.

```
property DisplayUnChecked : string;
```

Description

When nodes are grouped by the check column, an expression should be written for the grouped node. The DisplayUnChecked property determines text that is used when the check box is unchecked.

See Also

TdxDBGridCheckColumn.DisplayCheckel;TdxDBGridCheckColumn.DisplayNull

TdxDBGridCheckColumn Methods

Derived from TdxDBTreeListCheckColumn

GetCheckBoxState	**public**
GetCheckBoxValue	**public**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

Copyright © 2000 Developer Express Inc.

TdxDBGridCheckColumn Events

Derived from TdxDBTreeListCheckColumn

OnToggleClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**
OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**
OnValidate	**published**

TdxDBTreeListCheckColumn

TdxDBTreeListCheckColumn represents a check column in the ExpressQuantumGrid.

Unit

dxDBTLCl

```
TdxDBTreeListCheckColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListCheckColumn is appropriate for boolean fields. TdxDBTreeListCheckColumn uses TdxInplaceDBTreeListCheckEdit for data modification.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCheckColumn Properties

TdxDBTreeListCheckColumn

AllowGrayed	**published / read / write**	ValueChecked	**published / read / write**
Border3D	**published / read / write**	ValueGrayed	**published / read / write**
Glyph	**published / read / write**	ValueUnchecked	**published / read / write**
GlyphCount	**published / read / write**		
ShowNullFieldStyle	**published / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

AllowGrayed property — read / write

Determines whether a check column has two or three states.

```
property AllowGrayed: Boolean;
```

Description

Determines whether a check editor has two (checked, unchecked) or three (checked, unchecked and grayed) states.

The default value is **False**.

Border3D property — read / write

Determines check box border style.

```
property Border3D : Boolean;
```

Description

Use this property to specify the border style of a check box. If Border3D is True, a check box has a 3D look.

Glyph property — read / write

Determines the glyph displayed instead of a check box.

```
property Glyph: TBitmap;
```

Description

Use the Glyph property to specify a custom image for a check box. This bitmap can be used for different states of a check column based upon the GlyphCount property value.

GlyphCount property — read / write

Specifies the manner in which an image is used to represent a check box.

```
property GlyphCount: Integer;
```

Description

Use the GlyphCount property to determine the manner in which an image is used in place of the standard check box to display the states of a check column. GlyphCount property values include:

Value	Description
0	A glyph is not used. The standard check box is displayed.
1	A full size image is displayed instead of the standard check box.
2	The image is divided into two parts: One part indicates the checked state; the other part indicates the unchecked state of the check editor.
3	The glyph is divided into three parts. Each part determines the state of the check editor (grayed, checked, unchecked). Only one part can be dispayed at a time.
6	The glyph is divided into six parts. Each part determines the state of the check editor (grayed, checked, unchecked) when the check button is pressed and released. Only one part can be dispayed at a time.

Copyright © 2000 Developer Express Inc.

When using this property, you should use 0, 3, or 6.

The default value is **6**.

ShowNullFieldStyle property — read / write

Determines the display style for the null state of a field.

```
type
  TdxShowNullFieldStyle = (nsUnchecked, nsInactive, nsGrayedChecked);
property ShowNullFieldStyle : TdxShowNullFieldStyle;
```

Description

Use this property to specify how a field is displayed when the value of an underlying field is undetermined. The following values are available:

nsUnchecked	Check box is drawn unchecked.	☐
nsInactive	Check box is drawn as inactive.	■
nsGrayedCheck	Check box is grayed.	☑

ValueChecked property — read / write

```
property ValueChecked : string;
```

Description

Determines the text used as a value of TdxDBTreeListCheckColumn when it is checked.

See Also

TdxDBTreeListCheckColumn.GetCheckBoxState; TdxDBTreeListCheckColumn.GetCheckBoxValue; TdxDBTreeListCheckColumn.ValueUnchecked

ValueGrayed property — read / write

Specifies the value that corresponds to the grayed state of a check box.

```
property ValueGrayed: string;
```

Description

Use the ValueGrayed property to specify the value represented by the check box when it is grayed.

ValueUnchecked proeprty — read / write

```
property ValueUnchecked : string;
```

Description

Determines the text used as a value of TdxDBTreeListCheckColumn when it is unchecked.

See Also

TdxDBTreeListCheckColumn.GetCheckBoxState; TdxDBTreeListCheckColumn.GetCheckBoxValue; TdxDBTreeListCheckColumn.ValueChecked

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCheckColumn Methods

TdxDBTreeListCheckColumn

GetCheckBoxState	**public**
GetCheckBoxValue	**public**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

GetCheckBoxState method

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
function GetCheckBoxState(const AText : String): TdxCheckBoxState;
```

Description

Returns check box state by the TdxDBTreeListCheckColumn value.

See Also

TdxDBTreeListCheckColumn.GetCheckBoxValue; TdxDBTreeListCheckColumn.ValueChecked; TdxDBTreeListCheckColumn.ValueUnchecked

GetCheckBoxValue method

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
Function GetCheckBoxValue(AState : TdxCheckBoxState): String;
```

Description

Returns the TdxDBTreeListCheckColumn value by its state. The result of the function depends on ValueChecked and ValueUnChecked properties and the state of a check box.

See Also

TdxDBTreeListCheckColumn.GetCheckBoxState; TdxDBTreeListCheckColumn.ValueChecked; TdxDBTreeListCheckColumn.ValueUnchecked

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCheckColumn Events

TdxDBTreeListCheckColumn

OnToggleClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**
OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**
OnValidate	**published**

OnToggleClick event

Occurs when clicking a check box within TdxDBTreeListCheckColumn.

```
type
  TdxCheckBoxState = (cbsUnchecked, cbsChecked, cbsGrayed);
  TdxToggleEvent = procedure(Sender : TObject; const Text : String; State :
TdxCheckBoxState) of object;
property OnToggleClick : TdxToggleEvent;
```

Description

Write an OnToggleClick event handler to perform special processing when clicking a check box. The State parameter determines the state of the check box. The Text parameter specifies its Text.

TdxDBGridCurrencyColumn

Unit

dxGrClms

```
TdxDBGridCurrencyColumn = class(TdxDBTreeListCurrencyColumn);
```

Description

TdxDBGridCurrencyColumn represents a currency column in the ExpressQuantumGrid.



TdxDBGridCurrencyColumn derives all the methods and properties of TdxDBTreeListCurrencyColumn and publishes some of them. This represents the only difference between these classes. TdxDBGridCurrencyColumn publishes the following properties and events:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListCurrencyColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCurrencyColumn

TdxDBTreeListCurrencyColumn is used for TCurrencyField.

Unit

dxDBTLCl

```
TdxDBTreeListCurrencyColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListCurrencyColumn uses TdxInplaceDBTreeListCurrencyEdit for data manipulation. TdxDBTreeListCurrencyColumn is the base class for TdxDBGridCurrencyColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListCurrencyColumn Properties

TdxDBTreeListCurrencyColumn

AssignedValues	**public / read only**	MaxValue	**published / read / write**
DecimalPlaces	**published / read / write**	MinValue	**published / read / write**
DisplayFormat	**published / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

AssignedValues property — read only

Indicates which properties have been assigned to TdxDBTreeListSpinColumn.

```
type
  TdxMinMaxColumnValue = (mmcMinValue, mmcMaxValue);
  TdxMinMaxColumnValues = set of TdxMinMaxColumnValue;
property AssignedValues : TdxMinMaxColumnValues;
```

Copyright © 2000 Developer Express Inc.

Description

Used to determine whether TdxDBTreeListCurrencyColumn uses the default or assigned values for MinValue and MaxValue properties.

DecimalPlaces property read / write

```
property DecimalPlaces : Cardinal;
```

Description

Determines the number of digits following a decimal separator. The default value for DecimalPlaces is 2.

The DecimalPlaces property is effective only when a column is edited. Otherwise, the column's format is determined by the dataset field. Write an OnCustomDrawCell event handler to format the currency column based on your specific requirements. For instance, the following code makes the DecimalPlaces property available both when displayng and editing cells:

```
procedure TForm1.dxDBGrid1CurrencyColumn1CustomDrawCell(Sender: TObject;
ACanvas: TCanvas; ARect: TRect; ANode: TdxTreeListNode; AColumn:
TdxTreeListColumn; ASelected, AFocused, ANewItemRow: Boolean; var AText:
String; var AColor: TColor; AFont: TFont; var AAlignment: TAlignment; var
ADone: Boolean);
var
  CurrencyValue : Real;
  Code : integer;
  FormatString, s : string;
begin
  Val(AText, CurrencyValue, Code);
  Str(dxTreeList1Column2.DecimalPlaces, s);
  FormatString := '%0.' + s +'f';
  AText := Format(FormatString, [CurrencyValue]);
  ADone := False;
end;
```

DisplayFormat property read / write

Determines the manner in which currency values are formatted.

```
property DisplayFormat: string;
```

Description

Use the DisplayFormat property to define the format in which a currency value is displayed within a currency column cell. This format is applied when the cell is not focused. The default format string is '$,0.00;-$,0.00'.

MaxValue property read / write

```
property MaxValue : Double;
```

Description

Determines the maximum value TdxDBTreeListCurrencyColumn can assume.

See Also

TdxDBTreeListCurrencyColumn.DefaultMaxValue; TdxDBTreeListCurrencyColumn.DefaultMinValue; TdxDBTreeListCurrencyColumn.MinValue

MinValue property read / write

```
property MinValue : Double;
```

Description

Determines the minimum value TdxDBTreeListCurrencyColumn can assume.

See Also

TdxDBTreeListCurrencyColumn.DefaultMaxValue; TdxDBTreeListCurrencyColumn.DefaultMinValue; TdxDBTreeListCurrencyColumn.MaxValue

Copyright © 2000 Developer Express Inc.

TdxDBTreeListCurrencyColumn Methods

TdxDBTreeListCurrencyColumn

DefaultMaxValue	public
DefaultMinValue	public

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

DefaultMaxValue method

```
function DefaultMaxValue: Double;
```

Description

Returns the maximum value a field, associated with TdxDBTreeListCurrencyColumn, can assume. DefaultMaxValue returns the same value as the MaxValue property of a field.

See Also

TdxDBTreeListCurrencyColumn.DefaultMinValue; TdxDBTreeListCurrencyColumn.MaxValue; TdxDBTreeListCurrencyColumn.MinValue

DefaultMinValue method

```
function DefaultMinValue: Double;
```

Description

Returns the minimum value a field, associated with TdxDBTreeListCurrencyColumn, can assume. DefaultMinValue returns the same value as the MinValue property of a field.

See Also

TdxDBTreeListCurrencyColumn.DefaultMaxValue; TdxDBTreeListCurrencyColumn.MaxValue; TdxDBTreeListCurrencyColumn.MinValue

TdxDBTreeListCurrencyColumn Events

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

Copyright © 2000 Developer Express Inc.

TdxDBGridDateColumn

Unit

dxGrClms

```
TdxDBGridDateColumn = class(TdxDBTreeListDateColumn);
```

Description

TdxDBGridDateColumn allows you to use a calendar as an inplace editor. This column can be used to edit date fields.

It derives all the methods and properties of TdxDBTreeListDateColumn and publishes some of them, namely:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListDateColumn

TdxDBTreeListDateColumn

TdxDBTreeListDateColumn represents a date column.

Unit

dxDBTLCl

```
TdxDBTreeListDateColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListDateColumn is appropriate when working with date fields. Pressing the edit button of TdxDBTreeListDateColumn activates a dropdown calendar. TdxDBTreeListDateColumn uses the TdxInplaceDBTreeListDateEdit inplace editor.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

TdxDBTreeListDateColumn Properties

TdxDBTreeLsistDateColumn

DateButtons	**published / read / write**	SaveTime	**published / read / write**
DateOnError	**published / read / write**	UseEditMask	**published / read / write**
DateValidation	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published read/write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

DateButtons property read / write

Determines whether a dropdown calendar displays the 'Today' and/or 'Clear' buttons.

```
type
  TDateButton = (btnToday, btnClear);
  TDateButtons = set of TDateButton;
property DateButtons : TDateButtons;
```

Description

Use this property to control the display of the 'Today' and 'Clear' buttons within a dropdown calendar. Press the 'Today' button to set the current date in a grid cell. Pressing 'Clear' removes an existing date from a grid cell. By default, these buttons are displayed in a calendar.

See Also

sdxGridDatePopupClear; sdxGridDatePopupToday

DateOnError property read / write

Determines the date, which will be assigned to the date edit in case of invalid date input.

```
type
  TDateOnError = (deToday, deNull);
property DateOnError: TDateOnError;
```

Description

Use the DateOnError property to set the date, which will be assigned to the date edit in case of invalid date input. Assign DateOnError to deToday to set a current date or deNull to set a NULL date.

See Also

sdxDateError; TdxDBTreeListDateColumn.DateValidation; TdxDBTreeListDateColumn.OnDateValidateInput

DateValidation property read / write

Specifies whether an exception is displayed in case of invalid date input.

```
property DateValidation: Boolean;
```

Description

Use the DateValidation property to specify whether an exception is displayed in case of invalid date input. Set it to True to display the default exception or to False to not display it.

See Also

TdxDBTreeListDateColumn.DateOnError; TdxDBTreeListDateColumn.OnDateValidateInput

Copyright © 2000 Developer Express Inc.

SaveTime property read / write

Determines whether to save the time, if a dataset field contains both date and time.

```
property SaveTime : Boolean;
```

Description

If True, the time portion of TDateTime dataset field is combined with the date modification made by an inplace editor. If False, the time portion is reset to 0.

UseEditMask property read / write

Determines whether to display an edit mask in a focused cell.

```
property UseEditMask : Boolean;
```

Description

If UseEditMask is True, an edit mask appears in a focused cell in order to simplify date input.

TdxDBTreeListDateColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

Copyright © 2000 Developer Express Inc.

TdxDBTreeListDateColumn Events

TdxDBTreeListDateColumn

OnDateValidateInput	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnDateValidateInput event

Occurs on invalid date input.

```
type
TdxDateValidateInput = procedure(Sender: TObject; const AText: String; var
ADate: TDateTime; var AMessage: string; var AError: Boolean) of object;
property OnDateValidateInput: TdxDateValidateInput;
```

Description

Write code within OnDateValidateInput handler to perform specific actions on user date input. AText is the input text, ADate is the date after conversion. If TdxDBTreeListDateColumn is not able to convert text to the date (the AError parameter is True), a value based on the DateOnError property is assigned to the ADate parameter. You can change the ADate parameter within the handler. AMessage is an exception message that is displayed on error. Set the AError parameter to False to prevent the display of an exception.

See Also

TdxDBTreeListDateColumn.DateOnError; TdxDBTreeListDateColumn.DateValidation

TdxDBGridDropDownColumn

TdxDBGridDropDownColumn is the 'published' version of TdxDBTreeListDropDownColumn.

Unit

dxGrClms

```
TdxDBGridDropDownColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBGridDropDownColumn does not implement any new methods or properties. It is inherited from TdxDBTreeListDropDownColumn and publishes some of its properties. You cannot create columns of type TdxDBGridDropDownColumn at design time. Override TdxDBGridDropDownColumn to create your own columns with a dropdown window.

TdxDBGridDropDownColumn publishes the following properties and events:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListDropDownColumn

TdxDBTreeListDropDownColumn is an abstract column with a dropdown window.

Unit

dxDBTLCl

```
TdxDBTreeListDropDownColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListDropDownColumn provides methods and properties for columns with a custom dropdown window. These columns look like a combo box, when focused.

TdxDBTreeListDropDownColumn is the base class for TdxDBTreeListCalcColumn, TdxDBTreeListImageColumn, TdxDBTreeListlookupColumn, TdxDBTreeListPickColumn, TdxDBTreeListDateColumn, TdxDBTreeListBlobColumn and TdxDBTreeListPopupColumn.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListDropDownColumn Properties

TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**protected / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

ButtonGlyph property — read / write

Determines button glyph.

```
property ButtonGlyph: TBitmap;
```

Description

Specifies the glyph used for a button within a cell. Use this property to give your applications the desired look & feel.

DropDownRows property read / write

Determines the total number of rows within a dropdown window.

```
property DropDownRows : Cardinal;
```

Description

Use this property to set the number of visible rows within a dropdown window. If DropDowRows is less than the total number of items to drop down, a verticall scroolbar appears to the right of a dropdown window. The default value for DropDownRows is 7.

DropDownWidth property read / write

Specifies the width of a dropdown window.

```
property DropDownWidth: Integer;
```

Description

Specifies the width of the dropdown window in pixels. The default value for this property is 0.

ImmediateDropDown property read / write

Determines whether a dropdown list is automatically displayed when a user types text within an edited cell.

```
property ImmediateDropDown : Boolean;
```

Description

If this property is True, the dropdown window is automatically displayed if the entered text matches one of the dropdown list items. Otherwise, the dropdown list is not displayed until a user presses the edit button (a button, which activates the dropdown window).

ImmediatePopup property read / write

Determines whether the dropdown window is displayed immediately after a mouse click event.

```
property ImmediatePopup: Boolean;
```

Description

If the ImmediatePopup property is set to **False**, a single mouse click within the cell region activates the dropdown window.

The default value is **False**.

PopupAlignment property read / write

Specifies the manner in which a dropdown window is aligned relative to a cell.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
property PopupAlignment: TAlignment;
```

Description

Use the Alignment property to specify the horizontal placement of a dropdown window relative to an appropriate cell. It can be aligned either to the right, left, or centered.

Value	Meaning
taLeftJustify	Dropdown window is aligned to the left.
taCenter	Dropdown window is centered relative to a cell.
taRightJustify	Dropdown window is aligned to the right.

The default value is **taLeftJustify**.

PopupBorder property — read / write

Defines the border style for a dropdown window.

```
type
  TdxPopupBorder = (pbDefault, pbSingle, pbFrame3D);
property PopupBorder : TdxPopupBorder;
```

Description

Use this property to specify one of the following dropdown window border styles:

pbDefault	Default border for a dropdown window.
pbSingle	Dropdown window with a single line border.
pbFrame3D	Dropdown window with a 3D appearance.

ShowButtonStyle property — read / write

Specifies whether an in-place editor button is displayed when the editor is hidden.

```
type
 TdxShowButtonStyle = (sbDefault, sbAlways, sbNone);
property ShowButtonStyle: TdxShowButtonStyle;
```

Description

Set the ShowButtonStyle property to sbAlways to always show an in-place editor button even if the editor is hidden. Set the ShowButtonStyle property to sbNone to hide the in-place editor button if the editor is hidden. If the ShowButtonStyle property is sbDefault, then the behavior is determined by the egoShowButtonAlways option of the ExpressQuantumGrid and aoShowButtonAlways option of ExpressTreeList (the OptionsEx property).

Copyright © 2000 Developer Express Inc.

See Also

TCustomdxDBGrid.OptionsEx

TdxDBTreeListDropDownColumn Methods

TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

EditButtonClick property — read / write

Generates the OnEditButtonClick event.

```
procedure EditButtonClick(Sender: TObject); virtual;
```

Description

Descendants override this method to perform special actions when clicking an edited button withiout writing an OnEditButtonClick event handler.

IsShowButton property — read / write

Determines whether a column displays an edit button.

```
function IsShowButton(ANode: TdxTreeListNode): Boolean; virtual;
```

Description

TdxDBTreeListDropDownColumn uses a button to modify data in a grid cell. The IsShowButton function determines whether the edit button is visible. The value returned by this method depends on:

The ShowButtonStyle property of TdxDBTreeListDropDownColumn;

The egoShowButtonAlways option of the ExpressQuantumGrid;

A focused node.

Descendants can override this method to specify a required value.

TdxDBTreeListDropDownColumn Events

TdxDBTreeLisDropDowColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**
OnCustomDrawHeader	**published**
OnDrawSummaryFooter	**protected**
OnGetText	**published**
OnSummary	**protected**
OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**
OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**
OnValidate	**published**

OnEditButtonClick event

Occurs when clicking an editor button.

```
type
  TNotifyEvent = procedure(Sender: TObject) of object;
property OnEditColumnClick : TNotifyEvent;
```

Description

TdxDBTreeListDropDownColumn is an ancestor for all columns which use a dropdown window as an inplace editor. In order to activate this inplace editor you must click the editor button pictured below. The OnEditButtonClick event occurs when a user clicks this button. You can write an OnEditButtonClick event handler to perform actions when a user clicks this button.



See Also

TdxDBTreeListDropDownColumn.EditButtonClick

TdxDBGridHyperLinkColumn

Unit

dxGrClms

```
TdxDBGridHyperLinkColumn = class(TdxDBTreeListHyperLinkColumn);
```

Description

TdxDBGridHyperLinkColumn represents data from a dataset field as an Internet hyperlink. It allows a user to open web pages directly from a grid cell.

TdxDBGridHyperLinkColumn derives the methods and properties of TdxDBTreeListHyperLinkColumn and publishes some of them:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

This represents the only difference between these classes.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListHyperLinkColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListHyperLinkColumn

Data within TdxDBTreeListHyperLinkColumn appears as an Internet hyperlink.

Unit

dxDBTLCl

```
TdxDBTreeListHyperLinkColumn = class(TdxDBTreeListColumn);
```

Description

Use TdxDBTreeListHyperLinkColumn when you need to represent data from a dataset as a hyperlink. TdxDBTreeListHyperLinkColumn is appropriate if a dataset stores hyperlinks. Double-clicking (or clicking) these hyperlinks generates the OnStartClick event. Write an OnStartClick event handler to process mouse clicks.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListHyperLinkColumn Properties

TdxDBTreeListHyperLinkColumn

EditBackgroundColor	**published / read / write**	SingleClick	**published / read / write**
EditFontColor	**published / read / write**	StartKey	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MinWidth	**published / read / write**
BandIndex	**published / read / write**	ReadOnly	**published / read / write**
Caption	**published / read / write**	RowIndex	**published / read / write**
ColIndex	**published / read / write**	Sizing	**published / read / write**
Color	**published / read / write**	Sorted	**published / read / write**
DisableCaption	**published / read / write**	SortedOrder	**protected / read / write**
DisableCustomizing	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableDragging	**published / read / write**	TabStop	**published / read / write**
DisableEditor	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	Visible	**published / read / write**
HeaderAlignment	**published / read / write**	Width	**published / read / write**
HeaderGlyph	**published / read / write**		
HeaderMaxLineCount	**published / read / write**		

EditBackgroundColor property — read / write

```
property EditBackgroundColor : TColor;
```

Description

Specifies the background color of text in TdxDBTreeListHyperLinkColumn.

See Also

TdxDBTreeListHyperLinkColumn.EditFontColor

Copyright © 2000 Developer Express Inc.

EditFontColor property read / write

```
property EditFontColor : TColor;
```

Description

Specifies the font color in TdxDBTreeListHyperLinkColumn.

See Also

TdxDBTreeListHyperLinkColumn.EditBackgroundColor

SingleClick property read / write

```
property SingleClick : Boolean;
```

Description

Determines whether the OnStartClick event is generated by a mouse click. The default value for SingleClick is False, so the OnStartClick event is generated by a double-click.

TdxDBTreeListHyperLinkColumn.StartKey property read / write

```
property StartKey : TShortCut;
```

Description

Specifies the short cut that generates the OnStartClick event. In other words, StartKey is a short cut that activates TdxDBTreeListHyperLinkColumn.

TdxDBTreeListHyperLinkColumn Methods

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

Copyright © 2000 Developer Express Inc.

TdxDBTreeListHyperLinkColumn Events

TdxDBTreeLisHypeLinkColumnt

OnStartClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**
OnCustomDrawHeader	**published**
OnDrawSummaryFooter	**protected**
OnGetText	**published**
OnSummary	**protected**
OnSummaryFooter	**protecte d**

Derived from TdxTreeListColumn

OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**

OnStartClick event

Occurs when a user clicks the text in TdxDBTreeListHyperLinkColumn.

```
type
  TNotifyEvent = procedure(Sender: TObject) of object;
property OnStartClick : TNotifyEvent;
```

Description

This is the core procedure for TdxDBTreeListHyperLinkColumn. Write an OnStartClick event handler to activate a hyperlink using your own procedure. For instance, the following code activates an URL specified within an edited cell:

```
procedure TForm1.dxDBGrid1HyperLinkColumnStartClick(Sender: TObject);
var
  URLName :string;
begin
  URLName := dxDBGrid1.EditingText;
  ShellExecute(Self.Handle,'open','iexplore.exe', @(URLName[1]), nil,
SW_MAXIMIZE);
end;
```

The OnStartClick event is generated when a user presses the mouse button within an edited cell. If ExpressQunatumGrid is in ReadOnly mode (the egoEditing option is True), OnStartClick is not generated.

See Also

TdxTreeListHyperLinkColumn.OnStartClick

TdxDBGridImageColumn

Unit

dxGrClms

```
TdxDBGridImageColumn = class(TdxDBTreeListImageColumn);
```

Description

TdxDBGridImageColumn allows you to use a dropdown image list as an inplace editor. For instance, this column can be used to represent fields which can assume a limited set of values i.e. Payment method.

TdxDBGridImageColumn derives all the methods and properties of TdxDBTreeListImageColumn and publishes some of them, namely:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListImageColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListImageColumn

Unit

dxDBTLCl

```
TdxDBTreeListImageColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListImageColumn represents a column with a dropdown image list. Each item of a dropdown list within TdxDBtreeListColumn contains an image and a description. Data that is placed into a dataset field when closing a dropdown window is specified by the Values property. TdxDBTreeListImageColumn uses TdxInplaceDBTreeListImageEdit to modify data.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

TdxDBTreeListImageColumn Properties

TdxDBTreeListImageColumn

DefaultImages	**published / read / write**	LargeImages	**published / read / write**
Descriptions	**published / read / write**	ListWidth	**published / read / write**
ImageIndexes	**published / read / write**	MultiLineText	**published / read / write**
Images	**published / read / write**	ShowDescription	**published / read / write**
Incremental	**published / read / write**	Values	**published / read / write**

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**published / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**protected / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

DefaultImages property — read / write

Determines the image index of items.

```
property DefaultImages : Boolean;
```

Description

If DefaultImages is True, dropdown list items have sequential image indexes. The first item has index 0, the second has index 1, etc. If DefaultImages is False, the image indexes of an item are defined by the ImageIndexes property.

See Also

TdxDBTreeListImageColumn.ImageIndexes

Descriptions property — read / write

Represents an array of item descriptions.

```
property Descriptions : TStrings;
```

Description

Item description is the text that appears in a dropdown list. The first element of the Descriptions array is the description of the first item; the second element corresponts to the description of the second item; etc.

See Also

TdxDBTreeListImageColumn.ImageIndexes; TdxDBTreeListImageColumn.Values

ImageIndexes property — read / write

Represents image indexes of items.

```
property ImageIndexes : TStrings;
```

Description

Use this property to set the image index of an item from a dropdown list. Image index determines a picture from the Images property that is displayed as the graphic portion of an item. The first element of the ImageIndexes array corresponds to the first item in a dropdown list; the second element corresponds to the second item, etc.

See Also

TdxDBTreeListImageColumn.Images; TdxDBTreeListImageColumn.Values; TdxDBTreeListImageColumn.Descriptions

Images property — read / write

Determines an image list collection associated with TdxDBTreeListImageColumn.

```
property Images : TImageList;
```

Description

TdxDBTreeListImageColumn uses pictures from an Images list for the display of images. An image from Images is linked with an item via the ImageIndexes property of TdxDBTreeListImageColumn.

See Also

TdxDBTreeListImageColumn.ImageIndexes

Incremental property — read / write

Specifies whether pressing the Up and Down keys changes the current value.

```
property Incremental: Boolean;
```

Description

This property is effective only if an in-place editor is active. If the Incremental property is set to **True**, pressing the Up and Down keys changes the current value within a cell; Otherwise it moves focus to another cell.

The default value is **False**.

LargeImages property — read / write

Specifies the large image list for an image list box.

```
property LargeImages: TImageList;
```

Description

Use the LargeImages property to specify the large image list for a list image column. If the large image list is not NULL, it is used for displaying in the drop down image list box.

See Also

TdxDBTreeListImageColumn.DefaultImages

ListWidth property — read / write

Specifies the width of a drop down image list box.

```
property ListWidth: Integer;
```

Description

Use the ListWidth property to change the width of a drop down image list box.

MultiLineText property — read / write

Specifies whether text wraps when it is too long for the width of a control.

```
property MultiLineText: Boolean;
```

Description

Set MultiLines to True to allow a control to display multiple lines of the text. When MultiLines is True, text which is too long for the item rectangle will be wrapped and continued on additional lines. When MultiLines is False, a text, too long for the item rectangle will appear truncated.

ShowDescription property read / write

Specifies whether to display an item's description in a dropdown list.

```
property ShowDescription : Boolean;
```

Description

If ShowDescription is True, item descriptions are displayed within a dropdown list.

See Also

TdxDBTreeListImageColumn.Descriptions

Values property read / write

Determines values corresponding to dropdown list items.

```
property Values : TStrings;
```

Description

Contains an array of values that are inserted into dataset fields associated with TdxDBTreeListImageColumn. The first element of the Values array cooresponds to the first item in a dropdown list; the second element corresponds to the second item, etc.

See Also

TdxDBTreeListImageColumn.Descriptions; TdxDBTreeListImageColumn.ImageIndexes

TdxDBTreeListImageColumn Methods

TdxDBTreeLisImageColumnt

GetImageIndex	public
GetIndexes	public

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobCo lumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

GetImageIndex method

Returns the image index by the text of an item.

```
function GetImageIndex(const AText : String) : Integer;
```

Description

Use this method to obtain the image index of an item whose value is equal to AText. The value of an item is specified by the Values property. If TdxDBTreeListImageColumn does not contain an item with a value equal to AText, this method returns -1.

See Also

TdxDBTreeListImageColumn.ImageIndexes

TdxDBTreeListImageColumn.GetIndexes method

Returns the image index of an item and index of an item description by the item value.

```
procedure GetIndexes(const AText:String; var AImageIndex, ADescIndex:
Integer);
```

Description

Use this method to obtain the index of an image associated with an item via the ImageIndexes property and index of items description in the Descriptions property. AImageIndex is the index of an item image and ADescImage is the index of item description. AText specifies item value. If TdxDBTreeListImageColumn does not contain an item with the AText value, GetIndexes returns -1.

See Also

TdxDBTreeListImageColumn.ImageIndexes; TdxDBTreeListImageColumn.Values; TdxDBTreeListImageColumn.Descriptions

TdxDBTreeListImageColumn Events

TdxDBTreeListImageColumn

OnCloseUp	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxDBTreeListImageColumn.OnCloseUp

Occurs when closing a dropdown list.

```
type
  TdxImageColumnCloseUp = procedure(Sender: TObject; var Value: string; var
Accept: Boolean) of object;
property OnCloseUp: TdxImageColumnCloseUp;
```

Description

TdxdBTreeListImageColumn uses a dropdown image list to modify data in a grid cell. The OnCloseUp event is generated when the dropdown list is closed: Either a user selects a value from the list or presses the mouse button outside of the list, or a user presses ESC.

The Value parameter specifies data in string format written to a cell. The Accept parameter determines whether to apply changes to a grid cell. Use an OnCloseUp event handler to write specific data in a grid cell or to modify the data written. For instance, the following code allows recording data only for VISA credit card customers:

```
procedure TForm1.dxDBGrid1Column9CloseUp(Sender: TObject; var Value:
String; var Accept: Boolean);
begin
  . . .
  if OnlyVISA = True then
  begin
    if (Value <> 'VISA') then
    begin
      Accept := False;
```

```
        ShowMessage('You can add only VISA card clients!');
      end;
    . . .
    end
    else
      Accept := True;
    . . .
  end;
```

TdxDBGridLookupColumn

Unit

dxGrClms

```
TdxDBGridLookupColumn = class(TdxDBTreeListLookupColumn);
```

Description

TdxDBGridLookupColumn allows you to use a lookup coombo box as an inplace editor.



TdxDBGridLookupColumn derives all the methods and properties of TdxDBTreeListLookupColumn and publishes some of them, namely:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListLookupColumn

TdxDBTreeListLookupColumn

TdxDBTreeListLookupColumn represents a lookup column in the ExpressQuantumGrid.

Unit

dxDBTLCl

```
TdxDBTreeListLookupColumn = class(TdxDBTreeListDropDownColumn);
```

Description

The dropdown list of TdxDBTreeListLookupColumn contains lookup values. TdxDBTreeListLookupColumn uses TdxInplaceDBTreeListLookupEdit for data manipulation. TdxDBTreeListLookupColumn is a base for a TdxDBGridLookupColumn object. In order to use a column of type TdxDBTreeListLookupColumn, the associated field should be defined as a lookup column in a dataset.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

TdxDBTreeListLookupColumn Properties

TdxDBTreeListLookupColumn

CanDeleteText	**published / read / write**	ListFieldName	**published / read / write**
ClearKey	**published / read / write**	ListWidth	**published / read / write**
ListFieldIndex	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**published / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**published / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

CanDeleteText property — read / write

Specifies whether a user can delete the displayed value.

Copyright © 2000 Developer Express Inc.

```
property CanDeleteText: Boolean;
```

Description

This property is used when the DropDownListStyle property is set to **True**. If the CanDeleteText property is set to **False**, users cannot delete the selected value within a cell. If the CanDeleteText property is set to **True**, users can delete the selected value within a cell.

Note: Though users can delete the selected value if this property is set to **True**, the deleted text remains in the dropdown list.

The default value is **False**.

ClearKey property — read / write

```
property ClearKey : TShortCut;
```

Description

Specifies the short cut that clears TdxDBTreeListLookupColumn values.

ListFieldIndex property — read / write

Determines the index of a lookup field among the list of fields, specified in the ListFieldName property.

```
property ListFieldIndex : Integer;
```

Description

The dropdown list of TdxDBTreeListLookupColumn can contain several field names. This property specifies which field, among the specified list, is the lookup field.

See Also

TdxDBTreeListLookupColumn.ListFieldName

ListFieldName property — read / write

Determines fields names in a lookup list.

```
property ListFieldName : string;
```

Description

Use this property to specify fields that appear in a dropdown list. You can specify several field names. In this instance, field names must separated by semicolons.

See Also

TdxDBTreeListLookupColumn.ListFieldIndex

ListWidth property read / write

```
property ListWidth : Integer;
```

Description

Determines the width of a dropdown list.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListLookupColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

TdxDBTreeListLookupColumn Events

TdxDBTreeListLookupColumn

OnCloseUp	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnCloseUp event

This event is generated when closing a dropdown list.

```
type
  TdxPickColumnCloseUp = procedure(Sender: TObject; var Value: Variant; var
Accept: Boolean) of object;
property OnCloseUp: TdxPickColumnCloseUp;
```

Description

TdxDBTreeListLookupColumn uses a dropdown list to modify data in grid cells. An active inplace editor generates the OnCloseup event when the dropdown list is closed:

- When a user selects a value from the list.
- When a user presses the mouse button outside of the list.
- When a user presses ESC.

Write an OnCLoseUp event handler to perform additional processing of data written to a grid cell. The Value parameter specifies data written to the grid cell. The Accept parameter determines whether data will be written to the grid cell. Set Accept to False within the OnCloseUp event handler to prevent writing inadmissible data to a grid cell.

Copyright © 2000 Developer Express Inc.

TdxDBGridPickColumn

Unit

dxGrClms

```
TdxDBGridPickColumn = class(TdxDBTreeListPickColumn);
```

Description

TdxDBGridPickColumn allows you to use a combo box as an inplace editor. Use this column to display and edit fields that can assume a limited range of values.



TdxDBGridPickColumn derives all the methods and properties of TdxDBTreeListPickColumn and publishes some of them. This represents the only difference between these classes. TdxDBGridPickColumn publishes the following properties and events:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListPickColumn

TdxDBTreeListPickColumn

Unit

dxDBTLCl

```
TdxDBTreeListPickColumn = class(TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListPickColumn represents a column with a dropdown list. Pressing the edit button of TdxDBTreeListPickColumn activates a dropdown list with text items. TdxDBTreeListPickColumn looks like a combo box. An incremental search is available when using it. TdxDBTreeListPickColumn uses TdxInplaceDBTreeListPickEdit for data manipulation. TdxDBTreeListPickColumn is a base for TdxDBGridPickColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListPickColumn Properties

TdxDBTreeListPickColumn

CanDeleteText	**published / read / write**	Revertable	**published / read / write**
DropDownListStyle	**published / read / write**	ItemsSorted	**published / read / write**
Items	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**published / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**published / read / write**
DropDownWidth	**published / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**published / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

CanDeleteText property — read / write

Specifies whether a user can delete the displayed value.

```
property CanDeleteText: Boolean;
```

Description

This property is used when the DropDownListStyle property is set to **True**. If the CanDeleteText property is set to **False**, users cannot delete the selected value from a cell. If the CanDeleteText property is set to **True**, users can delete the selected value from a cell.

The default value is **False**.

DropDownListStyle property — read / write

Determines whether a user can edit data within an ExpressQuantumGrid cell or can only select a value form the list.

```
property DropDownListStyle : Boolean;
```

Description

If DropDownListStyle is True, TdxDBTreeListPickColumn prevents data editing within a cell, and forces users to select a value from the dropdown list.

Items property — read / write

Contains the strings that appear in a dropdown list box.

```
property Items : TStrings;
```

Description

Use Items to add, insert, delete and move items. Use TStrings methods and properties to manipulate items in a dropdown list.

Revertable property — read / write

Specifies whether a user can cycle through list values via a double click event.

```
property Revertable: Boolean;
```

Description

Set the Revertable property to **True** to allow a user to cycle through list values by double-clicking an appropriate mouse button within a pick cell. When the Revertable property is **True**, list values are displayed within a cell in their stored order. The display process is cyclical. When the last item of the list is displayed, a double click displays the first item in the list.

The default value is **False**.

ItemsSorted property — read / write

Specifies whether dropdown list values are sorted.

```
property ItemsSorted: Boolean;
```

Copyright © 2000 Developer Express Inc.

Description

If the ItemsSorted property is set to **True**, all values are sorted within a pick list.

The default value is **False**.

TdxDBTreeListPickColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

Copyright © 2000 Developer Express Inc.

TdxDBTreeListPickColumn Events

TdxDBTreeListpickColumn

OnCloseUp	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protecte d**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxDBTreeListPickColumn.OnCloseUp

This event is generated when closing a dropdown list.

```
type
  TdxPickColumnCloseUp = procedure(Sender: TObject; var Value: Variant; var
Accept: Boolean) of object;
property OnCloseUp: TdxPickColumnCloseUp;
```

Description

TdxDBTreeListPickColumn uses a dropdown list to modify values in a grid cell. The OnCloseUp event is generated when the dropdown list is closed:

- When a user selects a value from the list.
- When a user presses the mouse button outside of the list.
- When a user presses ESC.

The Value parameter specifies data written to a grid cell. The Accept parameter determines whether a cell accepts changes. If Accept is False, the cell is not updated. Write an OnCloseUp event handler to modify data written to an edited cell based on your specific requirements.

TdxDBGridSpinColumn

Unit

dxGrClms

```
TdxDBGridSpinColumn = class(TdxDBTreeListSpinColumn);
```

Description

TdxDBGridSpinColumn is useful if a field associated with TdxDBGridSpinColumn includes sequential numbers.



TdxDBGridSpinColumn derives all the methods and properties of TdxDBGridSpinColumn and publishes some of them, namely:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

This represents the only difference between these classes.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListSpinColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListSpinColumn

Unit

dxDBTLCl

```
TdxDBTreeListSpinColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListSpinColumn can be employed when storing sequential values. TdxDBTreeListSpinColumn uses TdxInplaceDBTreeListSpinEdit for data manipulation.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListSpinColumn Properties

TdxDBTreeListSpinColumn

AssignedValues	**public / read only**	MinValue	**published / read / write**
EditorEnabled	**published / read / write**	UseCtrlIncrement	**published / read / write**
Increment	**published / read / write**	ValueType	**public / read only**
MaxValue	**published / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MinWidth	**published / read / write**
BandIndex	**published / read / write**	ReadOnly	**published / read / write**
Caption	**published / read / write**	RowIndex	**published / read / write**
ColIndex	**published / read / write**	Sizing	**published / read / write**
Color	**published / read / write**	Sorted	**published / read / write**
DisableCaption	**published / read / write**	SortedOrder	**protected / read / write**
DisableCustomizing	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableDragging	**published / read / write**	TabStop	**published / read / write**
DisableEditor	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	Visible	**published / read / write**
HeaderAlignment	**published / read / write**	Width	**published / read / write**
HeaderGlyph	**published / read / write**		
HeaderMaxLineCount	**published / read / write**		

AssignedValues property — read only

Indicates which properties are assigned to TdxDBTreeListSpinColumn.

```
type
  TdxMinMaxColumnValue = (mmcMinValue, mmcMaxValue);
  TdxMinMaxColumnValues = set of TdxMinMaxColumnValue;
property AssignedValues : TdxMinMaxColumnValues;
```

Copyright © 2000 Developer Express Inc.

Description

This property is used to determine whether TdxDBTreeListSpinColumn uses the default or assigned values for MinValue and MaxValue properties.

See Also

TdxDBTreeListSpinColumn.MaxValue; TdxDBTreeListSpinColumn.MinValue

EditorEnabled property — read / write

Determines whether a user can edit data within TdxDBTreeListSpinColumn.

```
property EditorEnabled : Boolean;
```

Description

If EditorEnabled is True, users can change the TdxDBTreeListSpinColumn value by pressing up/down buttons or using the keyboard. Setting EditorEnabled to False prevents using the keyboard for data manipulation.

Increment property — read / write

Specifies the change value of TdxDBTreeListSpinColumn each time the up or down button is pressed.

```
property Increment : Double;
```

Description

Use Increment to control the granularity of changes made by TdxDBTreeListSpinColumn. Set Increment to indicate the number of units between MinValue and MaxValue.

See Also

TdxDBTreeListSpinColumn.MaxValue; TdxDBTreeListSpinColumn.MinValue

MaxValue property — read / write

Specifies the maximum value of TdxDBTreeListSpinColumn.

```
property MaxValue : Double;
```

Description

Use MaxValue to specify the upper limit of values for a field.

See Also

TdxDBTreeListSpinColumn.DefaultMaxValue; TdxDBTreeListSpinColumn.Increment; TdxDBTreeListSpinColumn.MinValue

MinValue property — read / write

Specifies the minimum value of TdxDBTreeListSpinColumn.

```
property MinValue : Double;
```

Description

Use MinValue to specify the lower limit of values for a field.

See Also

TdxDBTreeListSpinColumn.DefaultMinValue; TdxDBTreeListSpinColumn.Increment; TdxDBTreeListSpinColumn.MaxValue

UseCtrlIncrement property — read / write

Determines the keyboard keys used for changing TdxDBTreeListSpinColumn values.

```
property UseCtrlIncrement : Boolean;
```

Description

If UseCtrlIncrement is False, users can change TdxDBTreeListSpinColumn values using Up and Down arrow keys. If True, users should use Ctrl+Up and Ctrl+Down keys for modifying TdxDBTreeListSpinColumn values. Pressing the Up or Down key when UseCtrlIncrement is True moves focus to the previous/next node.

ValueType property — read only

Returns the field type associated with TdxDBTreeListSpinColumn.

```
type
  TdxValueType = (vtInt, vtFloat);
property ValueType : TdxValueType;
```

Description

If field type associated with TdxDBTreeListSpinColumn is TFloatField or TBCDField, ValueType returns vtFloat. Otherwise, ValueType is equal to vtInt.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListSpinColumn Methods

TdxDBTreeListSpinColumn

DefaultMaxValue	**public**
DefaultMinValue	**public**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

DefaultMaxValue method

```
function DefaultMaxValue: Double;
```

Description

Returns the maximum value a field can assume. DefaultMinValue returns the same value as the MaxValue property of a field.

See Also

TdxDBTreeListSpinColumn.DefaultMinValue; TdxDBTreeListSpinColumn.MaxValue

DefaultMinValue method

```
function DefaultMinValue: Double;
```

Description

Returns the minimum value a field can assume. DefaultMinValue returns the same value as the MinValue property of a field.

See Also

TdxDBTreeListSpinColumn.DefaultMaxValue; TdxDBTreeListSpinColumn.MinValue

TdxDBTreeListSpinColumn Events

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**
OnCustomDrawHeader	**published**
OnDrawSummaryFooter	**protected**
OnGetText	**published**
OnSummary	**protected**
OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**

Copyright © 2000 Developer Express Inc.

TdxDBGridTimeColumn

Unit

dxGrClms

```
TdxDBGridTimeColumn = class(TdxDBTreeListTimeColumn);
```

Description

TdxDBGridTimeColumn interacts with TDateTimeField via ExpressQuantumGrid and is used to operate against the time portion of TDateTimeField.



TdxDBGridTimeColumn derives all the methods and properties of TdxDBTreeListTimeColumn and publishes some of them:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListTimeColumn

TdxDBTreeListTimeColumn

Unit

dxDBTLCl

```
TdxDBTreeListTimeColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListTimeColumn represents a time column in the ExpressQuantumGrid. TdxDBTreeListTimeColumn uses TdxInplaceDBTreeListTimeEdit for data manipulation. TdxDBTreeListTimeColumn is a base for TdxDBGridTimeColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListTimeColumn Properties

TdxDBTreeListTimeColumn

TimeEditFormat	**published / read / write**
UseCtrlIncrement	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
CharCase	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

TimeEditFormat property — read / write

Specifies the time format used when displaying/editing data.

```
type
  TdxTimeEditFormat = (tfHourMinSec, tfHourMin, tfHour);
property TimeEditFormat: TdxTimeEditFormat;
```

Description

Use the TimeEditFormat property to specify the manner in which time is represented within an editor. The possible values of the time format include:

Value	Meaning
tfHourMinSec	Hours, minutes and seconds are displayed within a time cell.
tfHourMin	Hours and minutes are displayed within a time cell.
tfHour	Hours are displayed within a time cell.

The default value is **tfHourMinSec**.

UseCtrlIncrement property read / write

Determines keys used for changing TdxDBTreeListSpinColumn values.

```
property UseCtrlIncrement : Boolean;
```

Description

If UseCtrlIncrement is False, users can change TdxDBTreeListTimeColumn values using Up and Down arrow keys. If UseCtrlIncrement is True, user should use Ctrl+Up and Ctrl+Down keys for modifying TdxDBTreeListTimeColumn values. Pressing the Up or Down key when UseCtrlIncrement is True moves focus to the previous/next node.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListTimeColumn Methods

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

TdxDBTreeListTimeColumn Events

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxDBGridMemoColumn

Unit

dxGrClms

```
TdxDBGridMemoColumn = class(TdxDBTreeListMemoColumn);
```

Description

TdxDBGridMemoColumn is intended to represent large text strings within ExpressQuantumGrid cells. TdxDBGridMemoColumn uses TdxInplaceDBTreeListMemoEdit as a text inplace editor.



TdxDBGridMemoColumn derives all the methods and properties of TdxDBTreeListMemoColumn and publishes some of them:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Copyright © 2000 Developer Express Inc.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListColumn

TdxDBTreeListMemoColumn

Use TdxDBTreeListMemoColumn to display and edit memo fields directly within ExpressQuantumGrid.

Unit

dxDBTLCl

```
TdxDBTreeListMemoColumn = class(TdxDBTreeListColumn);
```

Description

Represents a column with a memo inplace editor. TdxDBTreeListMemoColumn derives all methods and properties of TdxDBTreeListColumn and publishes some of them. TdxDBTreeListMemoColumn uses the TdxInplaceDBTreeListMemoEdit inplace editor to modify data.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListMemoColumn Properties

TdxDBTreeListMemoColumn

HideScrollBars	**published / read / write**	WantReturns	**published / read / write**
MaxDisplayLength	**published / read / write**	WantTabs	**published / read / write**
ScrollBars	**published / read / write**	WordWrap	**published / read / write**
SelectionBar	**published / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MinWidth	**published / read / write**
BandIndex	**published / read / write**	ReadOnly	**published / read / write**
Caption	**published / read / write**	RowIndex	**published / read / write**
ColIndex	**published / read / write**	Sizing	**published / read / write**
Color	**published / read / write**	Sorted	**published / read / write**
DisableCaption	**published / read / write**	SortedOrder	**protected / read / write**
DisableCustomizing	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableDragging	**published / read / write**	TabStop	**published / read / write**
DisableEditor	**published / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	Visible	**published / read / write**
HeaderAlignment	**published / read / write**	Width	**published / read / write**
HeaderGlyph	**published / read / write**		
HeaderMaxLineCount	**published / read / write**		

HideScrollBars property — read / write

Determines whether a memo cell displays scroll bars at the edges of its edit box.

```
property HideScrollBars: Boolean;
```

Description

If the HideScrollBars property is set to **False**, scroll bars displayed within a memo cell when editing its contents. This property does not affect memo cells if the ScrollBars property is set to **ssNone**.

The default value is **True**.

MaxDisplayLength property read / write

Determines the maximum display length of a memo field.

```
property MaxDisplayLength : Integer;
```

Description

Use MaxDisplayLength to set the length of text displayed in a Memo column. If MaxDisplayLength is 0, all contents are displayed. The default value is 255.

Note: *the MaxDisplayLength property is in effect only when the edgoPreview option is set to False and the edgoRowAutoHeight option is set to True.*

ScrollBars property read / write

Determines whether the memo in-place editor includes scroll bars.

```
type
  TScrollStyle = (ssNone, ssHorizontal, ssVertical, ssBoth);
property ScrollBars: TScrollStyle;
```

Description

Use ScrollBars to give a multiline in-place editor horizontal or vertical scroll bars. ScrollBars can take one of the following values:

Value	Meaning
ssNone	The control has no scroll bars.
ssHorizontal	The control has a single scroll bar on the bottom edge.
ssVertical	The control has a single scroll bar on the right edge.
ssBoth	The control has a scroll bar on the both bottom and right edges.

SelectionBar property read / write

Specifies whether the selection bar is displayed at the leftmost edge of a memo cell.

```
property SelectionBar: Boolean;
```

Description

Selection bar is a region at the leftmost edge of an editor. It allows a user to select entire text lines using the mouse. Set the SelectionBar property to **True** to display it or to **False** to hide it. When the selection bar is hidden, a user can select text lines on a character-by-character basis only.

The default value is **False**.

Copyright © 2000 Developer Express Inc.

WantReturns property read / write

Specifies whether a user can insert return characters into memo cell text.

```
property WantReturns: Boolean;
```

Description

Setting the WantReturns property to **True** enables users to enter return characters into text. If WantReturns is True, pressing the Enter key inserts a return character into the contents of the cell.

The default value is **True**.

WantTabs property read / write

Specifies whether a user can insert tab characters into memo cell text.

```
property WantTabs: Boolean;
```

Description

Setting the WantTabs property to **True** enables users to enter tab characters into text.

The default value is **False**.

WordWrap property read / write

Determines whether an in-place editor inserts soft carriage returns, so text wraps at the right margin.

```
property WordWrap: Boolean;
```

Description

Set WordWrap to True to force the in-place editor to wrap text at the right margin so it fits in the client area. The wrapping is only cosmetic. The text does not include any return characters that were not explicitly entered. Set WordWrap to False to have the edit control show a separate line only where return characters were explicitly entered into the text.

TdxDBTreeListMemoColumn Methods

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetSummaryFooterText	**protected**
GetDisplayText	**protected**	IsBlobColumn	**protected**
GetdxInplaceEditClass	**protected**		
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetBestFit	**public**
Create	**public**	GetDisplayValue	**public**
DefaultAlignment	**public**	GetParentComponent	**public**
DefaultCaption	**public**	HasParent	**public**
DefaultColor	**public**	RestoreDefaults	**public**
DefaultFont	**public**	RestoreDefaultWidth	**public**
DefaultReadOnly	**public**		
DefaultWidth	**public**		

TdxDBTreeListMemoColumn Events

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**
OnCustomDrawHeader	**published**
OnDrawSummaryFooter	**protected**
OnGetText	**published**
OnSummary	**protected**
OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnCustomDrawCell	**published**
OnCustomDrawColumnHeader	**published**

Copyright © 2000 Developer Express Inc.

TdxDBGridGraphicColumn

Unit

dxGrClms

```
TdxDBGridGraphicColumn = class(TdxDBTreeListGraphicColumn);
```

Description

TdxDBGridGraphicColumn represents images within ExpressQuantumGrid cells. Unlike TdxDBGridBlobColumn, TdxDBGridGraphicColumn draws pictures within cells, so it is not necessary to call an inplace editor in order to view the picture.



TdxDBGridGraphicColumn uses TdxInplaceDBTreeListGraphicEdit to modify data. TdxDBGridGraphicColumn derives all method and properties from TdxDBTreeListGraphicColumn and publishes some of them:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListGraphicColumn

TdxDBTreeListGraphicColumn

Use TdxDBTreeListMemoColumn to display and edit graphic fields directly within ExpressQuantumGrid.

Unit

dxDBTLCl

```
TdxDBTreeListGraphicColumn = class(TdxDBTreeListColumn);
```

Description

Represents a column with a picture in-place editor. TdxDBTreeListGraphicColumn derives all methods and properties of TdxDBTreeListColumn and publishes some of them. TdxDBTreeListGraphicColumn uses the TdxInplaceDBTreeListGraphicEdit inplace editor to modify data.

Hierarchy

TObject

- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListGraphicColumn Properties

TdxDBTreeListGraphicColumn

CustomFilter	**published / read / write**	PopupToolbarPos	**protected / read / write**
CustomGraphic	**published / read / write**	PopupToolbarPosStored	**published / read / write**
DblClickActivate	**published / read / write**	QuickDraw	**published / read / write**
GraphicTransparency	**published / read / write**	ShadowSelection	**published / read / write**
PopupToolBar	**published / read / write**	Stretch	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

CustomFilter property — read / write

Determines the filter used to display specific files in a File list box when loading graphics.

```
property CustomFilter: string;
```

Description

The CustomFilter property is used to define filters for the Load File Dialog window. Enter wildcards and extensions to define your filter. For instance, if this property is set to the *.BMP" filter, only files with a .BMP extension are displayed.

CustomGraphic property — read / write

Determines whether TdxDBTreeListGraphicColumn displays custom images.

```
property CustomGraphic: Boolean;
```

Description

Set the CustomGraphic property to True, if TdxDBTreeListGraphicColumn displays non-bitmap images, i.e. JPEG, GIF, ICON, etc. If CustomGraphic is False (the default value), images are considered as TBitmap.

DblClickActivate property — read / write

Specifies whether a toolbar can be activated by a double click event within a graphic column cell.

```
property DblClickActivate: Boolean;
```

Description

The DblClickActivate property is in effect when the IsPopupMenu property is set to **False**. If set to **True**, a double click within a cell activates the associated toolbar. If the DblClickActivate property value is set to **False** (and the IsPopupMenu property is set to **False**), the associated toolbar is activated by a single click.

The default value is **True**.

GraphicTransparency property — read / write

Determines graphic transparency.

```
type
  TdxGraphicEditTransparency = (gtDefault, gtOpaque, gtTransparent);
property GraphicTransparency: TdxGraphicEditTransparency;
```

Description

Use the GraphicTransparency property to specify the manner in which an image is displayed within a graphic column cell. Set the GraphicTransparency property to gtDefault (the default value) to use the settings appropriate to the graphic itself (transparent for metafiles, opaque for bitmaps). Set the property to gtOpaque to make the background opaque. Set the property to gtTransparent to make the background transparent. Possible values include:

Value	Meaning
gtDefault	Graphic settings are used.
gtOpaque	The background is opaque.

gtTransparent The background is transparent.

The default value is **gtDefault**.

PopupToolBar property read / write

Specifies the ExpressToolBar popup window.

```
property PopupToolBar: TdxPopupToolBarWindow;
```

Description

Use the PopupToolBar property to set up image toolbar window properties. It pops up only when a user clicks a graphic column.

See Also

TdxDBTreeListGraphicColumn.OnCustomClick

PopupToolbarPos property read / write

Determines toolbar positon on screen.

```
property PopupToolbarPos: TPoint;
```

Description

The PopupToolbarPos property specifies the positon of the left top corner of the edit toolbar in screen coordiantes.

See Also

TdxDBTreeListGraphicColumn.PopupToolBar;
TdxDBTreeListGraphicColumn.PopupToolbarPosStored

PopupToolbarPosStored property read / write

Determines whether the edit toolbar positon is stored from one edit to the next.

```
property PopupToolbarPosStored: Boolean;
```

Description

TdxDBTreeListGraphicColumn implements a toolbar called that is used to modify pictures in grid cells. If the PopupToolbarPosStored property is False, the edit toolbar appears next to an edited cell every time a user activates an inplace editor. If PopupToolbarPosStored isTrue, the toolbar position is stored between edits.

See Also

TdxDBTreeListGraphicColumn.PopupToolBar; TdxDBTreeListGraphicColumn.PopupToolbarPos

QuickDraw property read / write

Specifies whether an image is displayed using the palette.

```
property QuickDraw: Boolean;
```

Description

Set QuickDraw to specify whether a customized palette is to be used when displaying field values. If False, a palette is used, to provide the best possible image quality at the expense of additional processing time. If True, no special palette is used, which is faster, but results in poorer picture quality, especially with 256-color images on a 256-color video driver.

ShadowSelection property read / write

Shadows images for selected nodes.

```
property ShadowSelection: Boolean;
```

Description

Set ShadowSelection to True to shadow images for selected nodes. Images are shadowed in the same way as images in the MS list view control for large icon view.

Stretch property read / write

Determines whether bitmaps and metafiles assume the size and shape of an image.

```
property Stretch: Boolean;
```

Description

Set Stretch to True to cause a picture to assume the size and shape of an image control. When the image control resizes, the picture also resizes. Stretch resizes an image's height and width independently. Thus, unlike a simple change in magnification, Stretch can distort the image if the image control has a different shape.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListGraphicColumn Methods

TdxDBTreeListGraphicColumn

GetGraphicClass

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	DefaultWidth	**public**
Create	**public**	GetBestFit	**public**
DefaultAlignment	**public**	GetDisplayValue	**public**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	RestoreDefaults	**public**
DefaultReadOnly	**public**	RestoreDefaultWidth	**public**

GetGraphicClass method

Generates an OnGetGraphicClass event.

```
type
  TGraphicClass = class of TGraphic;
function GetGraphicClass(ANode: TdxTreeListNode): TGraphicClass; virtual;
```

Description

This method is called when a grid cell is drawn. GetGraphicClass returns the image drawn in a cell. The ANode parameter specifies the node to which the drawn cell belongs. Use this parameter if necessary to draw different images for different nodes, i.e. GIFs for grouped nodes and ICONs for child nodes.

Descendants can override this method to perform any specific actions before or after generating the OnGetGraphicClass event. When overriding be sure to call the inherited method to generate the OnGetGraphicClass event.

See Also

TdxDBTreeListGraphicColumn.OnGetGraphicClass

TdxDBTreeListGraphicColumn Events

TdxDBTreeListGraphicColumn

OnAssignPicture	**published**
OnCustomClick	**published**
OnGetGraphicClass	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnAssignPicture event

```
type
  TdxGraphicEditAssignPictureEvent = procedure(Sender: TObject; var
Picture: TPicture) of object;
property OnAssignPicture: TdxGraphicEditAssignPictureEvent;
```

Description

This event is generated every time a user pastes an image to an edited cell. The Picture parameter specifies the pasted image. Write an OnAssignPicture event handler if you need to display specific formats (i.e. JPEG or GIF) in grid cells.

See Also

TdxDBTreeListGraphicColumn.OnGetGraphicClass; TdxDBTreeListGraphicColumn.GetGraphicClass

OnCustomClick event

Occurs immediately after a user clicks the custom button within the image toolbar window.

```
type
  TNotifyEvent = procedure(Sender : TObject) of object;
property OnCustomClick: TNotifyEvent;
```

Description

Use an OnCustomClick event to perform a particular operation when pressing the custom button within the image toolbar window.

See Also

TdxDBTreeListGraphicColumn.PopupToolBar

Copyright © 2000 Developer Express Inc.

OnGetGraphicClass event

```
type
  TGraphicClass = class of TGraphic;
  TdxGraphicEditGetGraphicClassEvent = procedure(Sender: TObject; Node:
TdxTreeListNode; var GraphicClass: TGraphicClass) of object;
property OnGetGraphicClass: TdxGraphicEditGetGraphicClassEvent;
```

Description

This event is generated when a grid cell of a graphic column is drawn. The Node parameter determines the node to which the drawn cell belongs. The GraphicClass parameter specifies image type.

Write an OnGetGraphicClass event handler if it is necessary to display images of different types in the same graphics column. Use the Node parameter to specify different image types for different nodes, i.e. JPEG for grouping nodes and ICON for ordinary nodes.

See Also

TdxDBTreeListGraphicColumn.OnAssignPicture; TdxDBTreeListGraphicColumn.GetGraphicClass

TdxDBGridPopupColumn

TdxDBGridPopupColumn is a grid column that can use any control as a dropdown window.

Unit

dxGrClEx

```
TdxDBGridPopupColumn = class (TdxDBTreeListPopupColumn);
```

Description

Use this column to create a complex custom dropdown window. For instance, it can be used to display master-detail relationships. Assume, ExpressQuantumGird displays master data, whereas another grid (it can be a standard TDBGid) displays detail records. Specify this standard grid as a popup control for TdxDBGridPopupColumn and users will be able to view detail records on a button press event within the TdxDBGridPopupColumn dropdown window.



TdxDBGridPopupColumn derives all the methods and properties of TdxDBTreeListPopupColumn and publishes some of them:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListPopupColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListPopupColumn

TdxDBTreeListPopupColumn is a column with a custom dropdown window.

Unit

dxGrClEx

```
TdxDBTreeListPopupColumn = class (TdxDBTreeListDropDownColumn);
```

Description

TdxDBTreeListPopupColumn is a column that can use any control including custom forms or grids presented as a dropdown window. With it, an application can employ complex dropdown windows to edit data within a grid's cell. TdxDBTreeListPopupColumn uses TdxInplaceDBTreeListPopupEdit to modify its data.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn

TdxDBTreeListPopupColumn Properties

TdxDBTreeListPopupColumn

PopupAutoSize	**published / read / write**	PopupFormSizeable	**published / read / write**
PopupControl	**published / read / write**	PopupHeight	**published / read / write**
PopupFormBorderStyle	**published / read / write**	PopupMinHeight	**published / read / write**
PopupFormCaption	**published / read / write**	PopupMinWidth	**published / read / write**
PopupFormClientEdge	**published / read / write**	PopupWidth	**published / read / write**
PopupFormFlatBorder	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**protected / read / write**
ImmediateDropDown	**protected / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterFormat	**protected / read / write**
DisableGrouping	**published / read / write**	SummaryFooterText	**public / read / write**
Field	**public / read / write**	SummaryFooterType	**protected / read / write**
FieldName	**published / read / write**	SummaryFooterValue	**public / read / write**
GroupIndex	**protected / read / write**	SummaryFormat	**protected / read / write**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read / write**

Derived from TdxTreeListColumn

Alignment	**published / read / write**	HeaderMaxLineCount	**published / read / write**
AssignedValues	**public / read only**	Index	**public / read / write**
BandIndex	**published / read / write**	MaxLength	**published / read / write**
Caption	**published / read / write**	MinWidth	**published / read / write**
CharCase	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
DisableCaption	**published / read / write**	RowIndex	**published / read / write**
DisableCustomizing	**published / read / write**	Sizing	**published / read / write**
DisableDragging	**published / read / write**	Sorted	**published / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**

PopupAutoSize property — read / write

Determines whether a dropdown window is of the same size as a popup control.

Copyright © 2000 Developer Express Inc.

```
property PopupAutoSize: Boolean;
```

Description

If True, the dropdown window is of the same size as the control, specified as the dropdown control. Otherwise, width and height of the dropdown window are determined by the PopupWidth and PopupHeight properties. By default, PopupAutoSize is True.

PopupControl property read / write

Determines a control to be used as a dropdown window.

```
property PopupControl: TControl;
```

Description

Use this property to determine a control that will be used as a dropdown control. The dropdown control can be any component registered in the IDE and derived from TControl. It is recommended to make this control initially invisible, since its position changes when the dropdown window activates (the control 'jumps' from its previous location to the dropdown window).

PopupFormBorderStyle property read / write

Specifies the border style for a dropdown window.

```
type
  TdxPopupEditFormBorderStyle = (pbsDialog, pbsDialogHelp, pbsSimple,
pbsSysPanel);
property PopupFormBorderStyle: TdxPopupEditFormBorderStyle;
```

Description

Use this property to specify the border style of a dropdown window. The following values are available:

Value	Description
pbsDialog	Standard dialog box border.
pbsDialogHelp	Dialog window with a help button in its title.
pbsSimple	A window with a single line border.
pbsSysPanel	If specified, TdxDBTreeListPopupColumn displays a status bar at the bottom of the dropdown window. This status bar includes a resizing grip and close button.

This property impacts only the dropdown window style. By default, PopupFormBorderStyle is pbsDialog.

PopupFormCaption property read / write

Specifies the dropdown form caption.

```
property PopupFormCaption: string;
```

Description

Use this property to determine the dropdown window caption. By default, this property is set to pbsDialog.

Note: *Caption is visible only when PopupFormBorderStyle is equal to pbsDialog or pbsDialogHelp*

PopupFormClientEdge property read / write

Determines the style of the dropdown window border.

```
property PopupFormClientEdge: Boolean;
```

Description

If True, the dropdown window has a border with a sunken edge. By default, PopupFormClientEdge is False.

PopupFormFlatBorder property read / write

Determines the style of the dropdown window border.

```
property PopupFormFlatBorder: Boolean;
```

Description

If True, the dropdown window has a flat border. If PopupFormFlatBorder is False, the dropdown window has a 3D border. By default, it is True.

PopupFormSizeable property read / write

Specifies whether the dropdown window is sizeable.

```
property PopupFormSizeable: Boolean;
```

Description

If True, a user can change a dropdown window's size. Otherwise, the size is fixed. By default, this property is True.

PopupHeight property read / write

Specifies the height of a dropdown window.

```
property PopupHeight: Integer;
```

Description

Use the PopupHeight property to determine the height of a dropdown window that appears when a user presses a button within TdxDBTreeListPopupColumn. This property has no effect when the

PopupAutoSize property is True and it cannot be less than the PopupMinHeight property. By default, it is equal to 200.

PopupMinHeight property read / write

Specifies the minimum height of a dropdown window.

```
property PopupMinHeight: Integer;
```

Description

Use this property to determine the minimum height of the TdxDBTreeListPopupColumn dropdown window. By default, PopupMinHeight equals 100.

PopupMinWidth property read / write

Specifies the minimum width of a dropdown window.

```
property PopupMinWidth: Integer;
```

Description

Use this property to determine the minimum width of the TdxDBTreeListPopupColumn dropdown window. By default, PopupMinWidth equals 100.

PopupWidth property read / write

Specifies the width of a dropdown window.

```
property PopupWidth : Integer;
```

Description

Use the PopupWidth property to determine the width of a dropdown window that appears when a user presses a button within TdxDBTreeListPopupColumn. This property has no effect when the PopupAutoSize property is True and it cannot be less than the PopupMinWidth property. By default, it is equal to 250.

TdxDBTreeListPopupColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
Create	**public**	GetdxInplaceEditClass	**protected**
DefaultAlignment	**public**	GetEnableEditor	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	RestoreDefaults	**public**
DefaultWidth	**public**	RestoreDefaultWidth	**public**
Destroy	**public**	SetName	**protected**
GetBestFit	**public**		

Copyright © 2000 Developer Express Inc.

TdxDBTreeListPopupColumn Events

TdxDBTreeListPopupColumn

OnCloseQuery	**published**	OnInitPopup	**published**
OnCloseUp	**published**	OnPopup	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnChangeName	**public**	OnGetText	**published**
OnCustomDraw	**published**	OnSummary	**protected**
OnCustomDrawHeader	**published**	OnSummaryFooter	**protected**
OnDrawSummaryFooter	**protected**		

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

OnCloseQuery event

This event occurs when a dropdown window is about to be closed.

```
type
  TdxPopupEditCloseQueryEvent = procedure (Sender: TObject; var CanClose:
Boolean) of object;
property OnCloseQuery: TdxPopupEditCloseQueryEvent;
```

Description

Write an OnCloseQuery event handler to determine whether a dropdown window can close. Set the CanClose parameter within the event handler to False to prevent window closing. The OnCloseQuery event is generated when a user presses the Close button or Alt-F4 to close the dropdown form.

OnCloseUp event

This event occurs immediately after a dropdown window has closed.

```
type
  TdxPopupEditCloseUpEvent = procedure (Sender: TObject; var Text: string;
var Accept: Boolean) of object;
property OnCloseUp: TdxPopupEditCloseUpEvent;
```

Description

Write an OnCloseUp event handler to confirm or discard any changes made in a grid cell via the dropdown window. The Text parameter specifies text, edited in the active grid cell. Set Accept to True to commit changes in a grid cell. If Accept is False, all changes are canceled.

OnInitPopup event

This event occurs when a dropdown window is about to be activated.

```
type
  TNotifyEvent = procedure (Sender: TObject) of object;
property OnInitPopup: TNotifyEvent;
```

Description

Write an OnInitPopup event handler to prepare data for a dropdown window and to determine which control will be displayed as a dropdown control. This feature provides using of different dropdown windows for different ExpressQuantumGrid rows. For instance, the following code displays different controls in different ExpressQuantumGrid modes: The first DBGrid is displayed when nodes of ExpressQuantumGrid are not grouped, the second – when the nodes are grouped:

```
procedure TForm1.dxDBGrid1VendorNameInitPopup(Sender: TObject);
begin
  . . .
  if dxDBGrid1.GroupColumnCount = 0 then
    dxDBGrid1PopupColumn1.PopupControl := DBGrid1
  else
    dxDBGrid1PopupColumn1.PopupControl := DBGrid2;
 . . .
end;
```

OnPopup event

This event occurs before a dropdown form will be displayed.

```
type
  TdxPopupEditPopupEvent = procedure (Sender: TObject; const EditText:
string) of object;
property OnPopup: TdxPopupEditPopupEvent;
```

Description

Write an OnPopup event handler to prepare data in a dropdown control before activating the dropdown form. The EditText parameter specifies text, displayed in the current cell. Use this text to prepare data in the dropdown control, i.e. To position the cursor to a specific record within the dropdown grid.

Copyright © 2000 Developer Express Inc.

TdxDBGridExtLookupColumn

TdxDBGridExtLookupColumn represents a column that uses an ExpressQuantumGrid in its dropdown window.

Unit

dxGrClEx

```
TdxDBGridExtLookupColumn = class (TdxDBTreeListExtLookupColumn);
```

Description

Use TdxDBGridExtLookupColumn to create an extended lookup column. Since the dropdown window of this column contains a TdxDBGrid object, a user can employ all functionality provided by the ExpressQuantumGrid to search for records.



TdxDBGridExtLookupColumn derives all the methods and properties of TdxDBTreeListExtLookupColumn and publishes some of them:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
  TPersistent
    TComponent
      TdxTreeListColumn
        TdxDBTreeListColumn
          TdxDBTreeListDropDownColumn
            TdxDBTreeListPopupColumn
              TdxDBTreeListExtLookupColumn

TdxDBTreeListExtLookupColumn

TdxDBTreeListExtlookupColumn represents a column whose dropdown window includes the ExpressQuantumGrid.

Unit

dxGrClEx

Description

Use TdxDBTreeListExtLookupColumn to create an extended lookup column. When activating the dropdown window, the extended lookup column displays a TdxDBGrid object, which can implement all ExpressQuantumGrid features. The dropdown grid automatically supports incremental search.

TdxDBTreeListExtLookupColumn applies TdxDBGridLayout objects to define the appearance of a grid within the dropdown window.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListPopupColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListExtLookupColumn Properties

TdxDBTreeListExtLookupColumn

ClearKey	**published / read / write**	PickListField	**published / read / write**
DBGridLayout	**published / read / write**	UseDefaultSettings	**published / read / write**

Derived from TdxDBTreeListPopupColumn

PopupAutoSize	**published / read / write**	PopupFormSizeable	**published / read / write**
PopupControl	**published / read / write**	PopupHeight	**published / read / write**
PopupFormBorderStyle	**published / read / write**	PopupMinHeight	**published / read / write**
PopupFormCaption	**published / read / write**	PopupMinWidth	**published / read / write**
PopupFormClientEdge	**published / read / write**	PopupWidth	**published / read / write**
PopupFormFlatBorder	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**protected / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**protected / read / write**
ImmediateDropDown	**protected / read / write**		

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read / write**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read / write**	SummaryFooterValue	**public / read / write**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroupName	**protected / read / write**
SortBySummary	**protected / read / write**	SummaryType	**protected / read / write**
SummaryField	**protected / read / write**	VariantType	**public / read / write**
SummaryFooterField	**protected / read / write**		
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	HeaderMaxLineCount	**published / read / write**
AssignedValues	**public / read only**	Index	**public / read / write**
BandIndex	**published / read / write**	MaxLength	**published / read / write**
Caption	**published / read / write**	MinWidth	**published / read / write**
CharCase	**published / read / write**	PasswordChar	**published / read / write**
ColIndex	**published / read / write**	ReadOnly	**published / read / write**
DisableCaption	**published / read / write**	RowIndex	**published / read / write**
DisableCustomizing	**published / read / write**	Sizing	**published / read / write**
DisableDragging	**published / read / write**	Sorted	**published / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**

ClearKey property read / write

Specifies the shortcut used to clear a field.

```
property ClearKey: TShortCut;
```

Description

When a user starts editing in a grid cell, he can press this shortcut to quickly clear data in an edited cell.

DBGridLayout property read / write

Determines the grid layout used for a dropdown window.

```
property DBGridLayout: TdxDBGridLayout;
```

Description

TdxDBTreeListExtLookupColumn employs a specific layout to create a grid in a dropdown window. Use this property to specify the layout of a grid for the dropdown window.

See Also

TdxDBGridLayout

PickListField property read / write

Specifies the field whose data will be added to the current cell of a grid.

```
property PickListField: string;
```

Description

Generally, a grid in the dropdown window includes several columns, but only one of them can be used to add data to an edited cell. The PickListField property specifies which column in the dropdown grid will be used to modify current cell data.

UseDefaultSettings property read / write

Determines dropdown grid style.

```
property UseDefaultSettings: Boolean;
```

Description

The Grid layout editor allows you to customize the characteristics of a dropdown grid to meet specific application needs. If UseDefaultSettings is True, the grid in the dropdown window uses default settings for grid properties.

Copyright © 2000 Developer Express Inc.

TdxDBTreeListExtLookupColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected**
IsShowButton	**protected**

Derived from TdxDBTreeListColumn

GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**
GetGroupText	**protected**		

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
Create	**public**	GetdxInplaceEditClass	**protected**
DefaultAlignment	**public**	GetEnableEditor	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	RestoreDefaults	**public**
DefaultWidth	**public**	RestoreDefaultWidth	**public**
Destroy	**public**	SetName	**protected**
GetBestFit	**public**		

TdxDBTreeListExtLookupColumn Events

Derived from TdxDBTreeListPopupColumn

OnCloseQuery	**published**	OnInitPopup	**published**
OnCloseUp	**published**	OnPopup	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnChangeName	**public**	OnGetText	**published**
OnCustomDraw	**published**	OnSummary	**protected**
OnCustomDrawHeader	**published**	OnSummaryFooter	**protected**
OnDrawSummaryFooter	**protected**		

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**published**
OnCustomDrawCell	**published**	OnValidate	**published**

TdxDBGridMRUColumn

TdxDBGridMRUColumn represents a column that displays and edits a list of the most recently used (MRU) items.

Unit

dxGrClms

```
TdxDBGridMRUColumn = class(TdxDBTreeListMRUColumn);
```

Description

TdxDBGridMRUColumn maintains a list of the most recently used items. This list is automatically maintained by the column, so no additional coding is necessary.

TdxTreeListMRUColumn can be used as a pick column to search for entered values against a list of most recently used items. Cells of this column can include one or two clickable buttons. One of these buttons is always used to activate the dropdown list of items. The other button can be programmed by a user to perform specific operations.

TdxDBGridMRUColumn derives all the methods and properties of TdxDBTreeListMRUColumn and publishes some of them:

? DisableFilter
? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListPickColumn
            - TdxDBTreeListMRUColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListMRUColumn

TdxDBTreeListMRUColumn represents a column that displays and edits a list of the most recently used (MRU) items.

Unit

dxDBTLCl

```
TdxDBTreeListMRUColumn = class(TdxDBTreeListPickColumn);
```

Description

TdxDBTreeListMRUColumn maintains a list of most recently used items. This list is automatically maintained by the column, so no additional coding is necessary to employ it.

TdxDBTreeListMRUColumn can be used as a pick column to search for entered values against a list of most recently used items. Cells of this column can include one or two clickable buttons. One of these buttons is always used to activate the dropdown list of items. The other button can be programmed by a user to perform specific operations. TdxDBTreeListMRUColumn uses TdxInplaceDBTreeListMRUEdit for data manipulation. TdxDBTreeListMRUColumn is a base for TdxDBGridMRUColumn.

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListDropDownColumn
          - TdxDBTreeListPickColumn

TdxDBTreeListMRUColumn Properties

TdxDBTreeListMRUColumn

MaxItemCount	**published / read / write**	ShowEllipsis	**published / read / write**

Derived from TdxDBTreeListPickColumn

CanDeleteText	**published / read / write**	Revertable	**published / read / write**
DropDownListStyle	**published / read / write**	Sorted	**published / read / write**
Items	**published / read / write**		

Derived from TdxDBTreeListDropDownColumn

ButtonGlyph	**protected / read / write**	ImmediatePopup	**protected / read / write**
DropDownRows	**published / read / write**	PopupAlignment	**protected / read / write**
DropDownWidth	**protected / read / write**	PopupBorder	**published / read / write**
ImmediateDropDown	**published / read / write**	ShowButtonStyle	**published / read / write**

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Copyright © 2000 Developer Express Inc.

MaxItemCount property read / write

Determines the maximum number of items a dropdown list can contain.

```
property MaxItemCount: Integer;
```

Description

Use the MaxItemCount property to specify the maximum number of items stored in the dropdown list of a MRU column's cell. The new value is stored as a new item within the dropdown list when input is confirmed. The most recently used item is placed at the top of the list. When a new item is placed into the list, it shifts other items down and becomes the first item in the list.

If the number of stored items within a dropdown list is equal to the value of the MaxItemCount property, the following operations are performed when a user enters a new value within a cell. The dropdown list hides its lowest item, all other items are shifted down and a new item is placed at the top of the list. All these changes are made when the editor loses focus.

If the value of the MaxItemCount property is 0, there is no limit to the number of list items. When the number of list items exceeds the value of the DropDownRows property, a vertical scroll bar appears at the right edge of the dropdown window.

The default value is **7**.

ShowEllipsis property read / write

Determines whether an additional button is displayed within a MRU column cell.

```
property ShowEllipsis: Boolean;
```

Description

If this property is **True**, you can write an OnButtonClick event handler to perform specific actions when pressing the custom button. Set the ShowEllipsis property to **False** if you do not wish to use and display this additional button.

The default value is **True**.

TdxDBTreeListMRUColumn Methods

Derived from TdxDBTreeListDropDownColumn

EditButtonClick	**protected / read / write**	IsShowButton	**protected / read / write**

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**	GetDisplayValue	**public**
AssignedDrawCellEvent	**protected**	GetdxInplaceEditClass	**protected**
Create	**public**	GetEnableEditor	**protected**
DefaultAlignment	**public**	GetMaxRowHeight	**protected**
DefaultCaption	**public**	GetParentComponent	**public**
DefaultColor	**public**	HasParent	**public**
DefaultFont	**public**	IsColumnMultiLine	**protected**
DefaultReadOnly	**public**	NeedShowButtonEdit	**protected**
DefaultWidth	**public**	RestoreDefaults	**public**
Destroy	**public**	RestoreDefaultWidth	**public**
DoDrawCell	**protected**	SetName	**protected**
GetBestFit	**public**		

Copyright © 2000 Developer Express Inc.

TdxDBTreeListMRUColumn Events

TdxDBTreeListMRUColumn

OnButtonClick	**published**

Derived from TdxDBTreeListPickColumn

OnCloseUp	**published**

Derived from TdxDBTreeListDropDownColumn

OnEditButtonClick	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxDBTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**protected**
OnCustomDrawCell	**published**	OnValidate	**published**

OnButtonClick event

Occurs when clicking a button within a cell.

```
type
  TNotifyEvent = procedure(Sender : TObject) of object;
property OnButtonClick: TNotifyEvent;
```

Description

Write an OnButtonClick event handler to perform specific actions when clicking the additional (ellipsis) button.

TdxDBGridWrapperColumn

TdxDBGridWrapperColumn represents a column that uses different in-place editors within its cells.

Unit

dxGrClms

```
TdxDBGridWrapperColumn = class(TdxDBTreeListWrapperColumn);
```

Description

TdxDBTreeListWrapperColumn introduces specific features to manipulate different in-place editors within a single column. Using the OnGetReferenceColumn event, users can assign in-place editors from other columns for different cells of a wrapper column. For correct data manipulation, the FieldName property of the referenced column should be the same as the FieldName property of the wrapper column.

TdxDBGridWrapperColumn derives all the methods and properties of TdxDBTreeListWrapperColumn and publishes some of them:

? GroupIndex
? SummaryType
? SummaryField
? SummaryFormat
? SortBySummary
? SummaryGroupName
? SummaryFooterType
? SummaryFooterField
? SummaryFooterFormat
? OnSummary
? OnSummaryFooter
? OnDrawSummaryFooter

Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn
        - TdxDBTreeListWrapperColumn

Copyright © 2000 Developer Express Inc.

TdxDBTreeListWrapperColumn

TdxDBTreeListWrapperColumn represents a column that uses different in-place editors within its cells.

Unit

dxDBTLCL

```
TdxDBTreeListWrapperColumn = class(TdxDBTreeListColumn);
```

Description

TdxDBTreeListWrapperColumn introduces specific features to manipulate different in-place editors within a single column. Using the OnGetReferenceColumn event, you can assign in-place editors from other columns for different cells of a wrapper column. For correct data manipulation the FieldName property of the referenced column should be the same as the FieldName property of the wrapper column.



Hierarchy

TObject
- TPersistent
  - TComponent
    - TdxTreeListColumn
      - TdxDBTreeListColumn

TdxDBTreeListWrapperColumn Properties

Derived from TdxDBTreeListColumn

ATreeList	**public / read / write**	SummaryFooterText	**public / read only**
DisableGrouping	**published / read / write**	SummaryFooterType	**protected / read / write**
Field	**public / read only**	SummaryFooterValue	**public / read only**
FieldName	**published / read / write**	SummaryFormat	**protected / read / write**
GroupIndex	**protected / read / write**	SummaryGroup	**public / read only**
SortBySummary	**protected / read / write**	SummaryGroupName	**protected / read / write**
SummaryField	**protected / read / write**	SummaryType	**protected / read / write**
SummaryFooterField	**protected / read / write**	VariantType	**public / read only**
SummaryFooterFormat	**protected / read / write**		

Derived from TdxTreeListColumn

Alignment	**published / read / write**	Index	**public / read / write**
AssignedValues	**public / read only**	MaxLength	**published / read / write**
BandIndex	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	PasswordChar	**published / read / write**
CharCase	**published / read / write**	ReadOnly	**published / read / write**
ColIndex	**published / read / write**	RowIndex	**published / read / write**
Color	**published / read / write**	Sizing	**published / read / write**
DisableCaption	**published / read / write**	Sorted	**published / read / write**
DisableCustomizing	**published / read / write**	SortedOrder	**protected / read / write**
DisableDragging	**published / read / write**	StoredRowIndex	**protected / read / write**
DisableEditor	**published / read / write**	TabStop	**published / read / write**
DisableFilter	**protected / read / write**	TreeList	**public / read / write**
Font	**published / read / write**	VertAlignment	**published / read / write**
HeaderAlignment	**published / read / write**	Visible	**published / read / write**
HeaderGlyph	**published / read / write**	Width	**published / read / write**
HeaderMaxLineCount	**published / read / write**		

Copyright © 2000 Developer Express Inc.

TdxDBTreeListWrapperColumn Methods

Derived from TdxDBTreeListColumn

AlwaysStoredValue	**protected**	GetGroupText	**protected**
GetDisplayText	**protected**	GetSummaryFooterText	**protected**
GetdxInplaceEditClass	**protected**	IsBlobColumn	**protected**

Derived from TdxTreeListColumn

Assign	**public**
AssignedDrawCellEvent	**protected**
Create	**public**
DefaultAlignment	**public**
DefaultCaption	**public**
DefaultColor	**public**
DefaultFont	**public**
DefaultReadOnly	**public**
DefaultWidth	**public**
Destroy	**public**
DoDrawCell	**protected**
GetBestFit	**public**
GetDisplayValue	**public**
GetdxInplaceEditClass	**protected**
GetEnableEditor	**protected**
GetMaxRowHeight	**protected**
GetParentComponent	**public**
HasParent	**public**
IsColumnMultiLine	**protected**
NeedShowButtonEdit	**protected**
RestoreDefaults	**public**
RestoreDefaultWidth	**public**
SetName	**protected**

TdxDBTreeListWrapperColumn Events

TdxDBTreeListWrapperColumn

OnGetReferenceColumn	**published**

Derived from TdxDBTreeListColumn

OnCustomDraw	**published**	OnGetText	**published**
OnCustomDrawHeader	**published**	OnSummary	**protected**
OnDrawSummaryFooter	**protected**	OnSummaryFooter	**protected**

Derived from TdxTreeListColumn

OnChange	**published**	OnCustomDrawColumnHeader	**protected**
OnCustomDrawCell	**published**	OnValidate	**published**

Copyright © 2000 Developer Express Inc.

Bands

TdxTreeListBand

Unit

dxTL

```
TdxTreeListBand = class(TCollectionItem);
```

Description

Bands allow you to add the following features into the ExpressTreeList/DBTreeList and ExpressQuantumGrid:

Divide columns into logical categories, for example, Client Name and ID, Address, Description and Picture).

Multiple rows, for example, I band: FirstName, Middle – first row, LastName – second row; II band: Country, State, City – first row, Address1/Address2 – second/third row(s); III band – Description and Picture occupy third rows together. This feature allows you to use screen space in the most efficient manner possible. See below



Allows you to fix any number of columns. You can fix a column both at the left and right edge of a control.

Note: *By default ExpressTreeList/DBTreeList and ExpressQuantumGrid have one invisible band (the ShowBands property of ExpressTreeList/DBTreeList and ExpressQuantumGrid is False).*

Hierarchy

TObject

TPersistent

TCollectionItem

Copyright © 2000 Developer Express Inc.

TdxTreeListBand Properties

Alignment	**published / read / write**	MinWidth	**published / read / write**
Caption	**published / read / write**	OnlyOwnColumns	**published / read / write**
DisableCustomizing	**published / read / write**	Sizing	**published / read / write**
DisableDragging	**published / read / write**	Visible	**published / read / write**
Fixed	**published / read / write**	VisibleIndex	**public / read only**
HeaderColCount	**public / read only**	Width	**published / read / write**
HeaderColumn	**public / read only**		
HeaderRowCount	**public / read only**		

Alignment property — read / write

Specifies the manner in which caption is aligned within a band.

```
type
  TAlignment = (taLeftJustify, taRightJustify, taCenter);
property Alignment : TAlignment;
```

Description

Use Alignment to specify the horizontal placement of the caption within a band. A band's caption can be aligned either to the right or left or centered. The available values are as follows:

taLeftJustify	Alignment to the left of a band.
taRightJustify	Alignment to the right.
taCenter	Text is centered within a band.

See Also

TdxTreeListBand.Caption

Caption property — read / write

Determines the caption of a tree list column.

```
property Caption: string;
```

Description

Specifies text that appears on a band. Use Caption to label the band.

See Also

TdxTreeListBand.Alignment

DisableCustomizing property read / write

Determines whether a band can be customized at runtime.

```
property DisableCustomizing : Boolean;
```

Description

By default, a user can customize a band at runtime, for instance he can change a column's size, move and hide the band. If DisableCustomizing is True, band customization is unavailable.

DisableDragging property read / write

```
property DisableDragging: Boolean;
```

Description

Determines whether users can move bands. By default, DisableDragging is True, so the end-user can move a band to a new location. If False, users cannot drag a band within a tree list (grid) control, but can drag it to the customizing form.

Fixed property read / write

Determines whether a band is a fixed.

```
type
  TdxGridBandFixed = (bfNone, bfLeft, bfRight);
property Fixed: TdxGridBandFixed;
```

Description

By default, users can horizontally scroll a band. You can fix a band to the left or right edge of a control by assigning the Fixed property to bfLeft or bfRight values accordingly.

See Also

TCustomdxTreeList.FixedBandLineColor

HeaderColCount property read only

Returns the number of columns in a band row.

```
property HeaderColCount[RowIndex: Integer]: Integer;
```

Description

Columns within a band can be arranged in several rows. A specific row can include one or more column headers. Use HeaderColCount to get the total number of columns in a band row. RowIndex specifies the row index.

Copyright © 2000 Developer Express Inc.



See Also

TdxTreeListColumn.ColIndex; TdxTreeListBand.HeaderColumn; TdxTreeListBand.HeaderRowCount

HeaderColumn property — read only

Returns a column, which belongs to a band by row and column indexes.

```
property HeaderColumn[RowIndex, ColIndex: Integer]: TdxTreeListColumn;
```

Description

Use HeaderColumn to get a column, which belongs to a band by row and column indexes.

See Also

TdxTreeListBand.HeaderColCount; TdxTreeListBand.HeaderRowCount

HeaderRowCount property — read only

Returns the number of column rows in a band.

```
property HeaderRowCount: Integer;
```

Description

Column headers can be arranged one under another within a band. The HeaderRowCount property returns the total number of column header rows within a band.

See Also

TdxTreeListBand.HeaderColCount; TdxTreeListBand.HeaderColumn; TdxTreeListColumn.RowIndex

MinWidth property — read / write

Determines the minimum width of a band.

```
property MinWidth : Integer;
```

Description

Use this property to specify the minimum width of a band. If a user resizes band width to a value less than MinWidth at runtime, the band will be restored to MinWidth.

See Also

TdxTreeListBand.Width

OnlyOwnColumns property — read / write

Determines whether a user can drag columns to/from a band.

```
property OnlyOwnColumns: Boolean;
```

Description

By default, this property is False, so users can drag columns to/from a band. Otherwise, users can move columns only within a band, but not between bands.

Note: *Users can drag a column to/from the customizing form regardless of the OnlyOwnColumns value.*

Sizing property — read / write

Determines whether it is possible to change band width.

```
property Sizing : Boolean;
```

Description

By default, Sizing is True and a user can change band width. Set Sizing to False to avoid band resizing.

Visible — read / write

Determines whether a band is visible.

```
property Visible : Boolean;
```

Description

Use this property to get or set the visibility of a band. If the Visible property is False, a band is hidden. Change the Visible property to True to display it.

VisibleIndex property — read only

Returns position of a band within the ExpressTreeList/DBTreeList and ExpressQuantumGrid controls.

```
property VisibleIndex: Integer
```

Description

Use VisibleIndex to obtain position of a band within the ExpressTreeList/DBTreeList and ExpressQuantumGrid controls.

Width property read / write

Specifies band width.

```
property Width: Integer;
```

Description

Use this property to get or set the width of a given tree list band. The band width cannot be less than the MinWidth property.

See Also

TdxTreeListBand.MinWidth; TdxTreeListBand.Sizing

TdxTreeListBand Methods

RestoreDefaults **public**

RestoreDefaults method

Restores the default value of a band.

```
procedure RestoreDefaults;
```

Description

Call the RestoreDefaults method to restore the default property values of a band.

Copyright © 2000 Developer Express Inc.

TdxTreeListBands

Contains a collection of TdxTreeListBand objects.

Unit

dxTL

```
TdxTreeListBands = class(TCollection);
```

Description

TdxTreeListBands represents a set of tree list bands. You can access a given band via its index in a TdxTreeListBands object.

Hierarchy

TObject

TPersistent

TCollection

TdxTreeListBands Properties

Items	**public / read / write**	VisibleItems	**public / read / write**
TreeList	**public / read only**		
VisibleCount	**public / read only**		

Items property — read / write

Defines a list of TdxTreeListBand objects a given collection owns.

```
property Items[Index:Integer] : TdxTreeListBand;
```

Description

The Item property specifies a list of all bands in the TdxTreeListBands object. The Items property includes both visible and hidden bands. You can access a given band via its index in the Items array.

See Also

TdxTreeListBands.VisibleItems

TreeList property — read only

Returns a custom TreeList control (ExpressTreeList/DBTreeList and ExpressQuantumGrid) to which a particular band belongs.

```
property TreeList: TCustomdxTreeListControl;
```

Description

Use the TreeList property to access the custom TreeList control (TdxTreeList, TdxDBGrid) to which a particular band belongs.

VisibleCount property — read only

Determines the number of visible bands in a TdxTreeListBands object.

```
property VisibleCount : Integer;
```

Description

Use this property to access the total number of visible bands. The visibility of a particular band is defined by the TdxTreeListBand Visible property. Band numeration in the TdxTreeListBands array begins with 0, thus the index of the last visible band is one less than the number, returned by the VisibleCount property.

See Also

TdxTreeListBands.VisibleItems; TdxTreeListBands.Items

Copyright © 2000 Developer Express Inc.

VisibleItems property read / write

Defines a list of visible TdxTreeListBand objects a given collection owns.

```
property VisibleItems[Index: Integer]: TdxTreeListBand;
```

Description

Specifies a list of visible bands in a TdxTreeListBands object. Unlike the Items property, the VisibleItems array includes only hidden bands. The visibility of a particular band is defined by the TdxTreeListBand Visible property. Use the VisibleCount property to get the visible band count.

See Also

TdxTreeListBands.Items

TdxTreeListBands Methods

Add	**public**	GetAbsoluteIndex	**public**
Create	**public**	GetVisibleIndex	**public**
RestoreDefaults	**public**		

Add method

Creates a new TdxTreeListBand instance and adds it to the Items array.

```
function Add: TdxTreeListBand;
```

Description

Call Add to create a band for TdxTreeListBands. A new TdxTreeListBand object is placed at the end of the Items array. Add returns the newly created TdxTreeListBand.

See Also

TdxTreeListBands.Items

Create method

```
type
  TdxTreeListBandClass = class of TdxTreeListBand;
constructor Create(ATreeList: TCustomdxTreeListControl; BandClass:
TdxTreeListBandClass);
```

Description

Creates a TdxTreeListBands instance and initializes its properties.

RestoreDefaults method

Sets the default value for properties of every TdxTreeListBand within a collection.

```
procedure RestoreDefaults;
```

Description

Use this method to reset properties of all TdxTreeListBands within a collection to their default values.

See Also

TdxTreeListBand.RestoreDefaults

GetAbsoluteIndex method

Returns index of a visible band in the TdxTreeListBands Items array.

Copyright © 2000 Developer Express Inc.

```
function GetAbsoluteIndex(VisibleIndex: Integer): Integer;
```

Description

Returns the TdxTreeListBand index in the Items array by its index in the VisibleItems array. The Index parameter specifies index of a TdxTreeListBand object in the VisibleItems array.

See Also

TdxTreeListBands.GetVisibleIndex; TdxTreeListBands.Items

GetVisibleIndex method

Returns index of a band in the TdxTreeListBands Items array.

```
function GetVisibleIndex (AbsoluteIndex: Integer): Integer;
```

Description

Returns the TdxTreeListBand index in the Items array by its index in the VisibleItems array. The Index parameter specifies index of a TdxTreeListBand object in the VisibleItems array. If a band is invisible, GetVisibleIndex returns –1.

See Also

TdxTreeListBands.GetAbsoluteIndex; TdxTreeListBands.Items

Index

A

Add....316
Alignment.... 12, 307
AllowGrayed.... 48, 193
AlwaysSaveText....121
AlwaysStoredValue 145
Assign 23
AssignedValues.... 12, 13, 202, 254
ATreeList 136

B

BandIndex.... 13
BeepOnError.... 77, 182, 183
BlobEditKind....121
BlobKind....162
BlobPaintStyle....121, 162
Border3D.... 48, 49, 189, 194
ButtonGlyph.... 37, 216
ButtonOnly 43, 174, 175
Buttons.... 43, 44, 175
ButtonStyle.... 77, 78, 183

C

CanDeleteText 95, 240, 241, 247, 248
Caption.... 13, 307
Center....107, 108
CharCase 13, 14
ClearKey 241
ClearKey 292
ClickKey 44, 175
ClipboardFormat 107
ColIndex.... 14
Color.... 15
Create.... 23, 316
CustomFilter 108, 273
CustomGraphic....108, 274

D

DateButtons.... 81, 210
DateOnError.... 82, 210
DateValidation 82, 210
DBGridLayout 292
DblClickActivate....108, 274
DecimalPlaces.... 54, 203
DefaultAlignment.... 23
DefaultCaption.... 24
DefaultColor 24
DefaultEditMask....156
DefaultFont.... 24
DefaultImages.... 90, 230, 231
DefaultMaxValue 205, 257
DefaultMinValue....205, 257
DefaultReadOnly 24
DefaultWidth.... 25
Descriptions.... 89, 231
Destroy.... 25
DisableCaption.... 15
DisableCustomizing.... 15, 308
DisableDragging.... 15, 308
DisableEditor 16
DisableFilter.... 16
DisableGrouping....136, 137
DisplayFormat....54, 55, 203
DoDrawColumn 145
DropDownListStyle.... 96, 248
DropDownRows 37, 217
DropDownWidth.... 38, 217

E

EditBackgroundColor.... 58, 224
EditButtonStyle.... 44, 175
EditFontColor.... 58, 225
EditMask 32, 155
EditorEnabled.... 68, 255

F

Field....137
FieldName 137
Fixed....308
Font 16

G

GetAbsoluteIndex....316
GetBestFit.... 25
GetCheckBoxState.... 51, 197
GetCheckBoxValue 51, 197
GetDisplayText 25, 146
GetDisplayValue 26
GetdxInplaceEditClass....146
GetGraphicClass....277
GetGroupText 147
GetImageIndex.... 91, 234
GetIndexes.... 91, 234, 235
GetParentComponent.... 26
GetSummaryFooterText 147
GetSummaryText....147
GetVisibleIndex....317
Glyph....44, 49, 176, 194
GlyphCount 49, 194
GraphicTransparency 108, 109, 274
GroupIndex....137

H

HasParent 26
HeaderAlignment.... 16
HeaderColCount....308
HeaderColumn 309
HeaderGlyph.... 17
HeaderMaxLineCount.... 17
HeaderRowCount 309
HideEditCursor.... 45, 176
HideScrollBars.... 63, 267

I

ImageIndexes....88, 89, 231
Images.... 88, 231, 232
ImmediateDropDown.... 38, 217
ImmediatePopup.... 38, 217
Increment....68, 69, 255
Incremental.... 87, 232
Index 17
IsBlobColumn....147, 148
Items.... 96, 248, 314
ItemsSorted.... 96, 248

L

LargeImages 88, 232
ListFieldIndex....241
ListFieldName....241
ListWidth.... 88, 232, 242

M

MaxDisplayLength 63, 122, 162, 268

Copyright © 2000 Developer Express Inc.

MaxItemCount....115, 116, 297
MaxLength.... 17, 18
MaxValue.... 55, 69, 204, 255
MemoCharCase....122, 163
MemoHideScrollBars....122, 123, 163
MemoMaxLength....123, 163, 164
MemoOEMConvert....123
MemoScrollBars....123, 163, 164
MemoSelectionBar....124, 164
MemoWantReturns....124, 164
MemoWantTabs....124
MemoWordWrap....125, 165
MinValue....55, 69, 204, 255, 256
MinWidth.... 18, 138, 309, 310
MultiLineText....89, 232

O

OnAssignedPicture....170
OnAssignPicture....112, 118, 130, 278
OnButtonClick.... 46, 116, 179, 297, 299
OnChange....28, 149
OnChangeName....149
OnCloseQuery....104, 287
OnCloseQuery....287
OnCloseUp....93, 97, 104, 236, 244, 251, 287
OnCloseUp....287
OnCustomClick....278
OnCustomDraw....149, 150
OnCustomDrawCell.... 28, 29
OnCustomDrawColumnHeader....29
OnCustomDrawHeader....150
OnDateValidateInput....84, 213
OnDrawSummaryFooter....150
OnEditButtonClick....41, 221
OnGetGraphicClass.... 112, 113, 130, 170, 171, 277, 279
OnGetReferenceColumn....131, 133, 300, 301
OnGetText....151
OnInitPopup....105, 288
OnlyOwnColumns....310
OnPopup....105, 288
OnPopup....288
OnStartClick....61, 227
OnSummary....151
OnSummaryFooter....151, 152
OnToggleClick....52, 199
OnValidate....29

P

PasswordChar....18
PickListField....292
PickListField....292
PictureAutoSize....125, 165
PictureFilter....125, 165
PictureGraphicClass....126
PictureTransparency....126, 165
PopupAlignment....38, 217
PopupAutoSize....99, 283
PopupAutoSize....282
PopupBorder....39, 218
PopupControl....100
PopupControl....283
PopupFormBorderStyle....100, 283
PopupFormCaption....100
PopupFormCaption....283
PopupFormClientEdge....101, 284
PopupFormClientEdge....284
PopupFormFlatBorder....101, 284
PopupFormFlatBorder....284
PopupFormSizeable....101
PopupFormSizeable....284
PopupHeight....101, 126, 166, 284
PopupHeight....284
PopupMinHeight....101, 102, 285
PopupMinHeight....285
PopupMinWidth....102, 285
PopupMinWidth....285
PopupToolBar....109, 275
PopupToolbarPos....275
PopupToolbarPosStored....109, 275
PopupWidth....102, 126, 166, 285
PopupWidth....285
Precision....78, 183

Q

QuickClose....78, 183
QuickDraw....109, 110, 276

R

ReadOnly....18
RestoreDefaults....26, 312, 316
RestoreDefaultWidth....27
Revertable....96, 248
RowIndex....19

S

SaveTime....82, 211
ScrollBars....64, 268
SelectionBar....64, 268
ShadowSelection....110, 276
ShowButtonFrame....78, 183, 184
ShowButtonStyle....39, 45, 176, 177, 218
ShowDescription....90, 233
ShowEllipsis....116, 297
ShowEllipsis property....116, 297
ShowExPopupItems....127, 167
ShowNullFieldStyle....49, 189, 195
ShowPicturePopup....127, 166
SingleClick....59, 225
SizeablePopup....128, 168
Sizing....19, 310
SortBySummary....138
Sorted....19, 20, 96
SortedOrder....20
StartKey....59, 225
StoredRowIndex....20
Stretch....110, 276
SummaryField....138
SummaryFooterField....139
SummaryFooterFormat....140
SummaryFooterText....140
SummaryFooterType....140, 141
SummaryFooterValue....141
SummaryFormat....141, 142
SummaryGroup....142
SummaryGroupName....142
SummaryType....143

T

TabStop.... 20, 21
TdxDBGridBlobColumn....158
TdxDBGridButtonColumn....172
TdxDBGridCalcColumn....180
TdxDBGridCheckColumn....187
TdxDBGridCheckColumn Events....191
TdxDBGridCheckColumn Methods....190
TdxDBGridCheckColumn Properties....188
TdxDBGridColumn....134
TdxDBGridCurrencyColumn....200
TdxDBGridDateColumn....207
TdxDBGridDropDownColumn....214
TdxDBGridExtLookupColumn....289
TdxDBGridGraphicColumn....271
TdxDBGridHyperLinkColumn....222
TdxDBGridImageColumn....228
TdxDBGridLookupColumn....238
TdxDBGridMaskColumn....153
TdxDBGridMemoColumn....264

TdxDBGridMRUColumn 294
TdxDBGridPickColumn 245
TdxDBGridPopupColumn 280
TdxDBGridSpinColumn 252
TdxDBGridTimeColumn 259, 264, 280, 289
TdxDBGridWrapperColumn 300
TdxDBTreeListBlobColumn 160
BlobKind 162
BlobPaintStyle 162
MaxDisplayLength 162
MemoCharCase 122, 163
MemoHideScrollBars 122, 123, 163
MemoMaxLength 163
MemoScrollBars 164
MemoSelectionBar 124, 164
MemoWantReturns 124, 164
MemoWordWrap 165
OnAssignedPicture 170
OnGetGraphicClass 170
PictureAutoSize 165
PictureFilter 125, 165
PictureTransparency 126, 165
PopupHeight 166
PopupWidth 166
ShowExPopupItems 167
ShowPicturePopup 166
SizeablePopup 168
TdxDBTreeListBlobColumn Events 170
TdxDBTreeListBlobColumn Methods 169
TdxDBTreeListBlobColumn Properties 161
TdxDBTreeListButtonColumn 173
ButtonOnly 174
Buttons 43, 44, 175
ClickKey 175
EditButtonStyle 175
Glyph 176
HideEditCursor 176
OnButtonClick 46, 116, 179, 297, 299
ShowButtonStyle 176
TdxDBTreeListButtonColumn Events 179
TdxDBTreeListButtonColumn Methods 178
TdxDBTreeListButtonColumn Properties 174
TdxDBTreeListCalcColumn 181
BeepOnError 182
ButtonStyle 183
Precision 183
QuickClose 183
ShowButtonFrame 183
TdxDBTreeListCalcColumn Methods 185
TdxDBTreeListCalcColumn Properties 182
TdxDBTreeListCheckColumn 192
AllowGrayed 48, 193
Border3D 189, 194
GetCheckBoxState 197
GetCheckBoxValue 197
Glyph 44, 49, 176, 194
GlyphCount 49, 194
OnToggleClick 199
ShowNullFieldStyle 189, 195
ValueChecked 195
ValueGrayed 50, 195
ValueUnchecked 195
TdxDBTreeListCheckColumn Events 199
TdxDBTreeListCheckColumn Methods 197
TdxDBTreeList CheckColumn Properties 193
TdxDBTreeListColumn 114, 135
AlwaysStoredValue 145
ATreeList 136
DisableGrouping 136
DoDrawColumn 145
Field 137
FieldName 137
GetDisplayText 146
GetdxInplaceEditClass 146
GetGroupText 147
GetSummaryFooterText 147
GetSummaryText 147
GroupIndex 137
IsBlobColumn 147
MinWidth 138
OnChangeName 149
OnCustomDraw 149
OnCustomDrawHeader 150
OnDrawSummaryFooter 150
OnGetText 151
OnSummary 151
OnSummaryFooter 151
SortBySummary 138
SummaryField 138
SummaryFooterField 139
SummaryFooterFormat 140
SummaryFooterText 140
SummaryFooterType 140
SummaryFooterValue 141
SummaryFormat 141
SummaryGroup 142
SummaryGroupName 142
SummaryType 143
VariantType 143
TdxDBTreeListCurrencyColumn 201
AssignedValues 202
DecimalPlaces 203
DefaultMaxValue 205
DefaultMinValue 205
DisplayFormat 54, 55, 203
MaxValue 204
MinValue 204
TdxDBTreeListCurrencyColumn Events 206
TdxDBTreeListCurrencyColumn Methods 205
TdxDBTreeListCurrencyColumn Properties 202
TdxDBTreeListDateColumn 208
DateButtons 210
DateOnError 210
Date eValidation 210
OnDateValidateInput 213
SaveTime 211
UseEditMask 211
TdxDBTreeListDateColumn Events 213
TdxDBTreeListDateColumn Methods 212
TdxDBTreeListDateColumn Properties 209
TdxDBTreeListDropDownColumn 215
ButtonGlyph 37, 216
DropDownRows 217
DropDownWidth 38, 217
ImmediateDropDown 217
ImmediatePopup 38, 217
OnEditButtonClick 221
PopupAlignment 38, 217
PopupBorder 218
ShowButtonStyle 218
TdxDBTreeListDropDownColumn Events 221
TdxDBTreeListDropDownColumn Methods 220
TdxDBTreeListDropDownColumn Properties 216
TdxDBTreeListExtLookupColumn 290
ClearKey 292
DBGridLayout 292
PickListField 292
UseDefaultSettings 292
TdxDBTreeListGraphicColumn 272
CustomFilter 108, 273
CustomGraphic 274
DblClickActivate 108, 274
GetGraphicClass 277
GraphicTransparency 108, 109, 274
OnAssignPicture 278
OnCustomClick 278
OnGetGraphicClass 279
PopupToolBar 275
PopupToolbarPos 275
PopupToolbarPosStored 275

QuickDraw....276
ShadowSelection....276
Stretch....276
TdxDBTreeListGraphicColumn Events....278
TdxDBTreeListGraphicColumn Methods....277
TdxDBTreeListGraphicColumn Properties....273
TdxDBTreeListHyperLinkColumn....223
EditBackgroundColor....224
EditFontColor....225
OnStartClick....227
SingleClick....225
StartKey....225
TdxDBTreeListHyperLinkColumn Events....227
TdxDBTreeListHyperLinkColumn Methods....226
TdxDBTreeListHyperLinkColumn Properties....224
TdxDBTreeListImageColumn....229
DefaultImages....230
Descriptions....231
GetImageIndex....234
GetIndexes....234
ImageIndexes....231
Images....231
Incremental....87, 232
LargeImages....232
ListWidth....232
MultiLineText....232
OnCloseUp....236
ShowDescription....233
Values....233
TdxDBTreeListImageColumn Events....236
TdxDBTreeListImageColumn Methods....234
TdxDBTreeListImageColumn Properties....230
TdxDBTreeListLookupColumn....239
CanDeleteText....95, 240, 241, 247, 248
ClearKey....241
ListFieldIndex....241
ListFieldName....241
ListWidth....242
OnCloseUp....244
TdxDBTreeListLookupColumn Events....244
TdxDBTreeListLookupColumn Methods....243
TdxDBTreeListLookupColumn Properties....240
TdxDBTreeListMaskColumn....154
DefaultEditMask....156
EditMask....155
TdxDBTreeListMemoColumn....266
HideScrollBars....63, 267
MaxDisplayLength....268
ScrollBars....268
SelectionBar....64, 268
WantReturns....64, 269
WantTabs....65, 269
WordWrap....269
TdxDBTreeListMemoColumn Events....270
TdxDBTreeListMemoColumn Methods....270
TdxDBTreeListMemoColumn Properties....267
TdxDBTreeListMRUColumn....295
MaxItemCount....115, 116, 297
OnButtonClick....46, 116, 179, 297, 299
ShowEllipsis....116, 297
TdxDBTreeListMRUColumn Events....299
TdxDBTreeListMRUColumn Methods....298
TdxDBTreeListMRUColumn Properties....296
TdxDBTreeListPickColumn....246
CanDeleteText....95, 240, 241, 247, 248
DropDownListStyle....248
Items....248
ItemsSorted....96, 248
OnCloseUp....251
Revertable....96, 248
Sorted....19, 20
TdxDBTreeListPickColumn Events....251
TdxDBTreeListPickColumn Methods....250
TdxDBTreeListPickColumn Properties....247
TdxDBTreeListPopupColumn....281
OnCloseQuery....287
OnCloseUp....287
OnInitPopup....288
OnPopup....288
PopupAutoSize....282
PopupControl....283
PopupFormBorderStyle....283
PopupFormCaption....283
PopupFormClientEdge....284
PopupFormFlatBorder....284
PopupFormSizeable....284
PopupHeight....284
PopupMinHeight....285
PopupMinWidth....285
PopupWidth....285
TdxDBTreeListSpinColumn....253
AssignedValues....254
DefaultMaxValue....257
DefaultMinValue....257
EditorEnabled....255
Increment....255
MaxValue....255
MinValue....255
UseCtrlIncrement....256
ValueType....256
TdxDBTreeListSpinColumn Events....258
TdxDBTreeListSpinColumn Methods....257
TdxDBTreeListSpinColumn Properties....254
TdxDBTreeListTimeColumn....260
TimeEditFormat....73, 261
UseCtrlIncrement....262
TdxDBTreeListTimeColumn Events....263
TdxDBTreeListTimeColumn Methods....263
TdxDBTreeListTimeColumn Properties....261
TdxDBTreeListWrapperColumn....301
OnGetReferenceColumn....131, 133, 300, 301
TdxDBTreeListWrapperColumn Events....304
TdxDBTreeListWrapperColumn Methods....303
TdxDBTreeListWrapperColumn Properties....302
TdxTreeListBand....305
Alignment....307
Caption....307
DisableCustomizing....308
DisableDragging....308
Fixed....308
HeaderColCount....308
HeaderColumn....309
HeaderRowCount....309
MinWidth....309
OnlyOwnColumns....310
RestoreDefaults....312
Sizing....310
Visible....310
VisibleIndex....310
Width....311
TdxTreeListBand Methods....312
TdxTreeListBand Properties....307
TdxTreeListBands....313
Add....316
Create....316
GetAbsoluteIndex....316
GetVisibleIndex....317
Items....314
RestoreDefaults....316
TreeList....314
VisibleCount....314
VisibleItems....315
TdxTreeListBands Methods....316
TdxTreeListBands Properties....314
TdxTreeListBlobColumn....119
AlwaysSaveT ext....121
BlobEditKind....121
BlobPaintStyle....121, 162
MaxDisplayLength....63, 122, 162, 268
MemoCharCase....122, 163

MemoHideScrollBars 122, 123, 163
MemoMaxLength 123, 163, 164
MemoOEMConvert 123
MemoScrollBars 123, 163, 164
MemoSelectionBar 124, 164
MemoWantReturns 124, 164
MemoWantTabs 124
MemoWordWrap 125, 165
OnAssignPicture 112, 118, 130, 278
OnGetGraphicClass 112, 113, 130, 170, 171, 277, 279
PictureAutoSize 125, 165
PictureFilter 125, 165
PictureGraphicClass 126
PictureTransparency 126, 165
PopupHeight 101, 126, 166, 284
PopupWidth 102, 126, 166, 285
ShowExPopupItems 127, 167
ShowPicturePopup 127, 166
SizeablePopup 128, 168
TdxTreeListBlobColumn Events 130
TdxTreeListBlobColumn Methods 129
TdxTreeListBlobColumn Properties 120
TdxTreeListButtonColumn 42
ButtonOnly 43
Buttons 43, 44, 175
ClickKey 44
EditButtonStyle 44
Glyph 44
HideEditCursor 45
OnButtonClick 46, 116, 179, 297, 299
ShowButtonStyle 45
TdxTreeListButtonColumn Events 46
TdxTreeListButtonColumn Methods 46
TdxTreeListButtonColumn Properties 43
TdxTreeListCalcColumn 76
BeepOnError 77
ButtonStyle 77
Precision 78
QuickClose 78
ShowButtonFrame 78
TdxTreeListCalcColumn Events 79
TdxTreeListCalcColumn Methods 79
TdxTreeListCalcColumn Properties 77
TdxTreeListCheckColumn 47
AllowGrayed 48
Border3D 48
GetCheckBoxState 51
GetCheckBoxValue 51
Glyph 44, 49, 176
GlyphCount 49
OnToggleClick 52
ShowNullFieldStyle 49
ValueChecked 50
ValueGrayed 50
ValueUnchecked 50
TdxTreeListCheckColumn Events 52
TdxTreeListCheckColumn Methods 51
TdxTreeListCheckColumn Properties 48
TdxTreeListColumn 11
Alignment 12
Assign 23
AssignedValues 12
BandIndex 13
Caption 13
CharCase 13, 14
ColIndex 14
Color 15
Create 23
DefaultAlignment 23
DefaultCaption 24
DefaultColor 24
DefaultFont 24
DefaultReadOnly 24
DefaultWidth 25
Destroy 25
DisableCaption 15
DisableCustomizing 15
DisableDragging 15
DisableEditor 16
DisableFilter 16
Font 16
GetBestFit 25
GetDisplayText 25
GetDisplayValue 26
GetParentComponent 26
HasParent 26
HeaderAlignment 16
HeaderGlyph 17
HeaderMaxLineCount 17
Index 17
MaxLength 17, 18
MinWidth 18
OnChange 28, 149
OnCustomDrawCell 28
OnCustomDrawColumnHeader 29
OnValidate 29
PasswordChar 18
ReadOnly 18
RestoreDefaults 26
RestoreDefaultWidth 27
RowIndex 19
Sizing 19
Sorted 19
SortedOrder 20
StoredRowIndex 20
TabStop 20
TreeList 21
VertAlignment 21
Visible 22
Width 22
TdxTreeListColumn Events 28
TdxTreeListColumn Methods 23
TdxTreeListColumn Properties 12
TdxTreeListCurrencyColumn 53
DecimalPlaces 54
DisplayFormat 54, 55
MaxValue 55
MinValue 55
TdxTreeListCurrencyColumn Events 56
TdxTreeListCurrencyColumn Methods 56
TdxTreeListCurrencyColumn Properties 54
TdxTreeListDateColumn 80
DateButtons 81
DateOnError 82
DateValidation 82
OnDateValidateInput 84
SaveTime 82, 211
UseEditMask 82
TdxTreeList DateColumn Events 84
TdxTreeListDateColumn Methods 84
TdxTreeListDateColumn Properties 81
TdxTreeListDropDownColumn 36
ButtonGlyph 37, 216
DropDownRows 37
DropDownWidth 38, 217
ImmediateDropDown 38
ImmediatePopup 38, 217
OnEditButtonClick 41
PopupAlignment 38, 217
PopupBorder 39
ShowButtonStyle 39
TdxTreeListDropDownColumn Events 41
TdxTreeListDropDownColumn Methods 40
TdxTreeListDropDownColumn Properties 37
TdxTreeListGraphicColumn 106
Center 107, 108
ClipboardFormat 107
CustomFilter 108, 273
CustomGraphic 108, 274
DblClickActivate 108, 274

GraphicTransparency....108, 109, 274
PopupToolBar....109, 275
PopupToolbarPosStored....109, 275
QuickDraw....109, 110, 276
ShadowSelection....110, 276
Stretch....110, 276
TdxTreeListGraphicColumn Events....112
TdxTreeListGraphicColumn Methods....111
TdxTreeListGraphicColumn Properties....107
TdxTreeListHyperLinkColumn....57
EditBackgroundColor....58
EditFontColor....58
OnStartClick....61
SingleClick....59
StartKey....59
TdxTreeListHyperLinkColumn Events....61
TdxTreeListHyperLinkColumn Methods....60
TdxTreeListHyperLinkColumn Properties....58
TdxTreeListImageColumn....86
DefaultImages....90
Descriptions....89
GetImageIndex....91
GetIndexes....91
ImageIndexes....88
Images....88
Incremental....87, 232
LargeImages....88
ListWidth....88
MultiLineText....89
OnCloseUp....93
ShowDescription....90
Values....89
TdxTreeListImageColumn Events....93
TdxTreeListImageColumn Methods....91
TdxTreeListImageColumn Properties....87
TdxTreeListMaskColumn....31
EditMask....32
TdxTreeListMaskColumn Events....35
TdxTreeListMaskColumn Methods....34
TdxTreeListMemoColumn....62
HideScrollBars....63, 267
MaxDisplayLength....63
ScrollBars....64
SelectionBar....64, 268
WantReturns....64, 269
WantTabs....65, 269
WordWrap....65
TdxTreeListMemoColumn Events....66
TdxTreeListMemoColumn Methods....66
TdxTreeListMemoColumn Properties....63
TdxTreeListMRUColumn....114
MaxItemCount....115, 116, 297
OnButtonClick....46, 116, 179, 297, 299
ShowEllipsis....116, 297
TdxTreeListMRUColumn Events....118
TdxTreeListMRUColumn Methods....117
TdxTreeListMRUColumn Properties....115
TdxTreeListPickColumn....94
CanDeleteText....95, 240, 241, 247, 248
DropDownListStyle....96
Items....96
ItemsSorted....96, 248
OnCloseUp....97
Revertable....96, 248
Sorted....19, 20
TdxTreeListPickColumn Events....97
TdxTreeListPickColumn Methods....97
TdxTreeListPickColumn Properties....95
TdxTreeListPopupColumn....98
OnCloseQuery....104
OnCloseUp....104
OnInitPopup....105
OnPopup....105
PopupAutoSize....99
PopupControl....100
PopupFormBorderStyle....100
PopupFormCaption....100
PopupFormClientEdge....101
PopupFormFlatBorder....101
PopupFormSizeable....101
PopupHeight....101
PopupMinHeight....101
PopupMinWidth....102
PopupWidth....102
TdxTreeListPopupColumn Events....104
TdxTreeListPopupColumn Methods....103
TdxTreeListPopupColumn Properties....99
TdxTreeListSpinColumn....67
EditorEnabled....68
Increment....68
MaxValue....69
MinValue....69
UseCtrlIncrement....69
ValueType....69
TdxTreeListSpinColumn Events....71
TdxTreeListSpinColumn Methods....71
TdxTreeListSpinColumn Properties....68
TdxTreeListTimeColumn....72
TimeEditFormat....73
UseCtrlIncrement....74
TdxTreeListTimeColumn Events....75
TdxTreeListTimeColumn Methods....75
TdxTreeListTimeColumn Properties....73
TdxTreeListWrapperColumn....131
OnGetReferenceColumn....131, 133, 300, 301
TdxTreeListWrapperColumn Events....133
TdxTreeListWrapperColumn Methods....132
TdxTreeListWrapperColumn Properties....132
TimeEditFormat....73, 261
TreeList....21, 314

U

UseCtrlIncrement....69, 74, 256, 262
UseDefaultSettings....292
UseDefaultSettings....292
UseEditMask....82, 83, 211

V

ValueChecked....50, 195
ValueGrayed....50, 195
Values....89, 233
ValueType....69, 70, 256
ValueUnchecked....50, 195
VariantType....143
VertAlignment....21
Visible....22, 310
VisibleCount....314
VisibleIndex....310
VisibleItems....315

W

WantReturns....64, 269
WantTabs....65, 269
Width....22, 311
WordWrap....65, 269