本科生实验报告

实验课程: 操作系统原理实验

任课教师: 刘宁

实验题目: Lab5 可变参数机制与内核线程

专业名称: 计算机科学与技术

学生姓名: 孙凯

学生学号: 23336212

实验地点: 实验中心B202

实验时间: 2025.4.28

一、实验要求:

在本次实验中,我们将会学习到C语言的可变参数机制的实现方法。在此基础上,我们会揭开可变参数背后的原理, 进而实现可变参数机制。实现了可变参数机制后,我们将实现一个较为简单的printf函数。此后,我们可以同时使用 printf和gdb来帮助我们debug。

本次实验另外一个重点是内核线程的实现,我们首先会定义线程控制块的数据结构——PCB。然后,我们会创建PCB,在PCB中放入线程执行所需的参数。最后,我们会实现基于时钟中断的时间片轮转(RR)调度算法。在这一部分中,我们需要重点理解 asm_switch_thread 是如何实现线程切换的,体会操作系统实现并发执行的原理。

具体内容如下:

- 1. 可变参数机制的实现
- 2. 实现printf函数
- 3. 内核线程的创建和调度

二、预备知识和实验环境:

预备知识: qemu+gdb调试方法,线程调度算法, C++语法

实验环境:

1. 虚拟机版本/处理器型号: Ubuntu 20.04 LTS

2. 代码编辑环境: Vscode+nasm+C/C++插件+qemu仿真平台

3. 代码编译工具: gcc/g++ (64位)

重要三方库信息: 无
 代码程序调试工具: gdb

三、实验任务:

• Assignment 1 printf的实现

- Assignment 2 线程的实现
- Assignment 3 时钟中断的实现
- Assignment 4 调度算法的实现

四、实验步骤和实验结果:

Assignment 1: printf函数的实现

代码在 lab5/assignment1

• 任务要求:

学习可变参数机制,然后实现printf函数,你可以在材料中 (src/3)的printf上进行改进,或者从头开始实现自己的printf 函数。结果截图保存并说说你是怎么做的。

- 实验思路: 仿照实验操作仓库的步骤, 搭建 printf 函数
 - o 在原基础的 printf 函数上,添加八进制输出格式 ‰,无符号整数输出格式 ‰ 和浮点数输出格式 ‰ 三种功能。
- 实验步骤:
- 1. 修改 stdio.cpp 文件, 添加 %o %u %f 三种输出格式。

%o 的实现思路和前面的输出格式基本相同,只需要修改一下 itos 函数的格式参数8;

%u 的实现思路和 %d 相似, 只需要删除一下负号的输出逻辑;

%f 的实现思路为将浮点数分解为整数部分和小数部分, 然后分别处理, 这里保留了6位小数的精度。

```
case 'u':
            unsigned int temp = va_arg(ap, unsigned int);
            itos(number, temp, 10);
            for (int j = 0; number[j]; ++j)
            {
                counter += printf_add_to_buffer(buffer, number[j], idx, BUF_LEN);
            }
            break;
case 'o':
            unsigned int temp = va_arg(ap, unsigned int);
            itos(number, temp, 8);
            for (int j = 0; number[j]; ++j)
                counter += printf_add_to_buffer(buffer, number[j], idx, BUF_LEN);
            break;
case 'f':
            double temp = va_arg(ap, double);
            int int_part = (int)temp;
```

```
double frac_part = temp - int_part;
    if (temp < 0)
        counter += printf_add_to_buffer(buffer, '-', idx, BUF_LEN);
        int_part = -int_part;
       frac_part = -frac_part;
    }
    itos(number, int_part, 10);
    for (int j = 0; number[j]; ++j)
    {
        counter += printf_add_to_buffer(buffer, number[j], idx, BUF_LEN);
    }
    counter += printf_add_to_buffer(buffer, '.', idx, BUF_LEN);
    // 保留6位小数
    for (int k = 0; k < 6; ++k)
        frac_part *= 10;
       int digit = (int)frac_part;
        counter += printf_add_to_buffer(buffer, '0' + digit, idx, BUF_LEN);
       frac_part -= digit;
    break;
}
```

2. 在 setup.cpp 文件中添加测例

3. make && make run 构建运行

实验结果如下:

可以看到输出最大无符号数 4294967295 ,十进制数 123 输出八进制格式为 173 ,输出浮点数 3.141592

```
| Mill |
```

Assignment 2 线程的实现

代码在 lab5/assignment2

- 任务要求: 自行设计PCB, 可以添加更多的属性, 如优先级等, 然后根据你的PCB来实现线程, 演示执行结果。
- 实验思路:在 PCB 结构体中加入相应的属性,然后在 ProgramManager 添加相应属性的处理。
- 实验步骤:
- 1. 修改 thread.h 文件,添加创建时间 createTime,等待时间 waitTime 和调度策略 schedulingPolicy

这里创建了一个枚举结构、用于说明对应的线程调度策略。

```
enum SchedulingPolicy
{
   SCHEDULED_RR,
   SCHEDULED_SJF,
   SCHEDULED_PRIORITY,
   SCHEDULED FCFS
};
struct PCB
                               // 栈指针,用于调度时保存esp
   int *stack;
   char name[MAX_PROGRAM_NAME + 1]; // 线程名
   enum ProgramStatus status; // 线程的状态
                               // 线程优先级
   int priority;
                               // 线程pid
   int pid;
   int ticks;
                               // 线程时间片总时间
                               // 线程已执行时间
   int ticksPassedBy;
   ListItem tagInGeneralList; // 线程队列标识
   ListItem tagInAllList;
                                // 线程队列标识
   unsigned long createTime; // 线程创建时间
   unsigned long waitTime; // 线程等待时间
   enum SchedulingPolicy schedulingPolicy; // 线程调度策略
};
```

2. 修改 program.cpp 文件,给 ProgramManager 类中添加 schedulingPolicy 的成员,用于对应线程调度策略。

```
thread->createTime = time_counter++;
thread->waitTime = 0;
// 设置线程的调度策略
// 0:RR, 1:SJF, 2:PRIORITY, 3:FCFS
if(schedulingPolicy == 0)
    thread->schedulingPolicy = SchedulingPolicy::SCHEDULED_RR;
else if(schedulingPolicy == 1)
    thread->schedulingPolicy = SchedulingPolicy::SCHEDULED_SJF;
else if(schedulingPolicy == 2)
    thread->schedulingPolicy = SchedulingPolicy::SCHEDULED_PRIORITY;
else if(schedulingPolicy == 3)
    thread->schedulingPolicy = SchedulingPolicy::SCHEDULED_FCFS;
else
    thread->schedulingPolicy = SchedulingPolicy::SCHEDULED_RR;
```

3. 修改 setup.cpp 文件,添加两个进程,然后在打印函数中添加 scheduling policy 和 creatTime 两个输出内容,用于查看对应 PCB 的属性。

添加一个辅助函数 get_scheduling_policy_name ,将调度策略枚举转换为字符串。

```
printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :Hello World!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
// 添加一个辅助函数, 将调度策略枚举转换为字符串
const char* get_scheduling_policy_name(enum SchedulingPolicy policy) {
    switch (policy) {
        case SCHEDULED_RR:
            return "Round Robin";
       case SCHEDULED_SJF:
            return "Shortest Job First";
        case SCHEDULED_PRIORITY:
            return "Priority";
        case SCHEDULED_FCFS:
            return "First Come First Served";
        default:
           return "Unknown";
   }
}
```

4. make && make run 构建运行

实验结果如下:

可以看到对应的输出。

```
Source of the control of the control
```

Assignment 3 时钟中断的实现

代码在 lab5/assignment3

• 任务要求:

编写若干个线程函数,使用gdb跟踪c_time_interrupt_handler、 asm_switch_thread(eg: b c_time_interrupt_handler)等函数,观察线程切换前后栈、寄存器、PC等变化,结合gdb、材料中"线程的调度"的内容来跟踪并说明下面两个过程。

- 1. 一个新创建的线程是如何被调度然后开始执行的。
- 2. 一个正在执行的线程是如何被中断然后被换下处理器的,以及换上处理机后又是如何从被中断点开始执行的。

通过上面这个练习,同学们应该能够进一步理解操作系统是如何实现线程的并发执行的。

- 实验思路:通过 gdb 调试查看 first thread 的创建调度和 third thread 如何中断之后换上 first thread。
- 实验步骤:
- 1. 打断点到 first thread 创建语句,然后单步执行,进入 executeThread 函数,然后再进入 allocatePCB 函数,查看当前分配的 PCB 地址。

```
Terminal
      /src/kernel/program.cpp
    64
    65
                                                  1 % % / ^
                           // ^%^ &^ %^ '^
    66
                                                               (^ ^ %^ )^
    67
                           if (isNameSame) {
    68
                                return -1;
    69
    70
    72
73
                       (allPrograms.size() >= MAX_PROGRAM_AMOUNT)
    74
    75
76
77
                           return -1;
    78
    79
                       // ^%^ $^ &^ /^ )^ &^ %^ %^ '^ ^^'^ '^ (^ ^^ '^ (^ &^ &^
    80
                      bool status = interruptManager.getInterruptStatus();
                      interruptManager.disableInterrupt();
    83
                               )^ $^ \^)^ $^ $^
    84
                      PCB *thread = allocatePCB();
 B+><mark>85</mark>
    86
    87
                      if (!thread)
    88
                           return -1;
    89
remote Thread 1.1 In: ProgramManager::executeThread
                                                                                                             PC: 0x20187
warning: No executable has been specified and target does not support
determining executable automatically. Try using the "file" command.
      offfo in ?? ()
(gdb) b setup.cpp:80
Breakpoint 1 at 0x207a4: file ../src/kernel/setup.cpp, line 80.
(gdb) c
Continuing.
Breakpoint 1, setup_kernel () at ../src/kernel/setup.cpp:80
(gdb) s
  ogramManager::executeThread (this=0x320c4 <programManager>, function=0x206b4 <first_thread(void*)>, parameter=0x0, name=0x21941 "first thread", priority=1, schedulingPolicy=0)
    at ../src/kernel/program.cpp:34
(gdb) b program.cpp:85
Breakpoint 2 at 0x20187: file ../src/kernel/program.cpp, line 85.
(gdb) c
Continuing.
Breakpoint 2, ProgramManager::executeThread (this=0x320c4 <programManager>,
function=0x206b4 <first_thread(void*)>, parameter=0x0, name=0x21941 "first thread", priority=1,
    schedulingPolicy=0) at ../src/kernel/program.cpp:85
(gdb)
   ogramManager::executeThread (this=0x320c4 <programManager>, function=0x206b4 <first_thread(void*)>, parameter=0x0, name=0x21941 "first thread", priority=1, schedulingPolicy=0)
    at ../src/kernel/program.cpp:87
(gdb) p thread
$1 = (PCB *) 0x220a0 <PCB_SET>
```

2. 打断点进入 asm_switch_thread 中,查看 first thread 线程调度前后寄存器的值。 由于 first thread 是手动创建并调度的,所以它之前的线程并不存在,对应 esp和ebp 寄存器的值是默认的。 此时 esp和ebp 保存上一个线程的状态。

```
/src/utils/asm_utils.asm
                                             db 0
   20
                ASM_IDTR dw 0
   21
22
23
                ; void asm_switch_thread(PCB *cur, PCB *next);
asm_switch_thread:
   24
25
   26
27
                    push ebp
push ebx
                    push edi
    28
   29
30
                    push esi
                   31
   32
33
                   mov eax, [esp + 6 * 4]
mov esp, [eax]; ^8^ 8^ 8^ %^ '^ $^ ur^8^ %^ 8^ %^ ext^8^
   ><mark>34</mark>
    35
    36
                    pop esi
                    pop edi
remote Thread 1.1 In: asm_switch_thread
eax
               0×0
               0x220a0
                                   139424
ecx
               0x0
edx
ebx
               0x39000
                                   233472
esp
               0x7bc0
                                   0x7bc0
               0x7bfc
                                   0x7bfc
ebp
esi
               0x0
edi
               0x0
               0x21766
                                   0x21766 <asm_switch_thread+10>
[ IOPL=0 AF ]
```

调度之后, 线程1的栈地址 esp 为 0x23084。

```
/src/utils/asm_utils.as
  28
             push edi
  29
             push esi
  30
            mov eax, [esp + 5 * 4]
mov [eax], esp ; ^$^ ^ %^ %^ %^
                                      &^
             mov eax, [esp + 6 * 4]
  34
             mov esp, [eax] ; ^&^ &^ &^ %^ '^ $^ ur^&^ %^ &^ %^ ext^&^
  35
  36
  >37
             pop esi
  38
             pop edi
  39
             pop ebx
  40
             pop ebp
  42
             sti
  43
            ret
          ; int asm_interrupt_status();
  45
          asm_interrupt_status:
  46
             xor eax, eax
            pushfd
(gdb) n
(gdb) n
    .tch_thread () at ../src/utils/asm_utils.asm:37
(gdb) info registers
eax
         0x220a0
                      139424
ecx
         0x220a0
                      139424
edx
         0x0
ebx
         0x39000
                      233472
esp
         0x23084
                      0x23084 <PCB_SET+4068>
ebp
         0x7bfc
                      0x7bfc
         0x0
esi
edi
         0x0
eip
         0x2176c
                      0x2176c <asm_switch_thread+16>
                      [ IOPL=0 AF ]
          0x12
```

3. 打断点到 c_time_interrupt_handler, 然后查看时间片和时间片剩余, 观察线程如何运行。

```
(gdb) b c_time_interrupt_handler
Breakpoint 2 at 0x20afc: file ../src/kernel/interrupt.cpp, line 89.
(gdb) c
Continuing.

Breakpoint 2, c_time_interrupt_handler () at ../src/kernel/interrupt.cpp:89
(gdb) n
(gdb) n
(gdb) p cur->ticks
$1 = 10
(gdb) p cur->ticksPassedBy
$2 = 0
(gdb) ■
```

当时间片为0时,Assignment 4 调度算法的实现打断点到 asm_switch_thread 查看当前线程寄存器的值和线程调度 之后的线程寄存器的值。

可以看调度之前先保存线程 first thread 当前的状态, esp 和 ebp 为 0x22fe8 和 0x23024

```
/src/utils/asm_utils.as
                      extern c_time_interrupt_handler
ASM_UNHANDLED_INTERRUPT_INFO db 'Unhandled interrupt happened, halt...'
      17
18
                                                              db 0
     20
21
22
23
24
25
26
27
                      ASM_IDTR dw 0 dd 0
                      ; void asm_switch_thread(PCB *cur, PCB *next);
asm_switch_thread:
                           push ebp
push ebx
push edi
push edi
push esi
     28
29
30
                           31
      32
                           mov eax, [esp + 6 * 4] mov esp, [eax] ; ^{8^{}} &^ &^ &^ '^ $^ ur^&^ %^ &^ &^ ext^&^
     ><mark>34</mark>
      35
     36
 remote Thread 1.1 In: asm_switch_thread
 $4 = 10
(gdb) s
ProgramManager::schedule (this=0x320c4 <programManager>) at ../src/kernel/program.cpp:140 (gdb) b asm_switch_thread
Breakpoint 5 at 0x2175c: file ../src/utils/asm_utils.asm, line 26.
(gdb) c
Continuing.
Breakpoint 5, asm_switch_thread () at ../src/utils/asm_utils.asm:26
Breakpoint 5, asm_swi
(gdb) n
(gdb) info registers
eax
0x220a
                     0x220a0
                                                 139424
ecx
                     0x22f92
                                                 143250
edx
                     0x8
ebx
                     0x0
                                                0x22fe8 <PCB_SET+3912>
0x23024 <PCB_SET+3972>
esp
                     0x22fe8
ebp
                     0x23024
esi
edi
                     0x0
                     0x0
eip
eflags
                     0x21766
                                                 0x21766 <asm_switch_thread+10>
                                                 [ IOPL=0 ]
```

调度之后,线程 second thread 的栈地址为 0x24084

```
/src/utils/asm_utils.asm
   B+ 26
                                               push ebp
         27
                                               push ebx
         28
                                               push edi
          29
                                               push esi
         30
         31
                                               mov eax, [esp + 5 * 4]
                                               CB^$^ /^ $^ $^ ^ ^&^ %^ &^
         32
                                                                                                                                            &^
                                                                                                                                                     )^ %^
         33
         34
                                               mov eax, [esp + 6 * 4]
                                               mov esp, [eax] ; ^&^ &^ &^ &^ '^ $^ ur^&^ %^ &^ *^ ext^&^
         35
         36
       >37
                                               pop esi
         38
                                               pop edi
         39
                                               pop ebx
         40
                                               pop ebp
         41
         42
                                               sti
         43
                                               ret
                                      ; int asm interrupt status();
         44
         45
                                      asm_interrupt_status:
remote Thread 1.1 In: asm switch thread
сг8
                                   0x0
                                                                                  0
efer
                                   0x0
                                                                                      ]
                                    v_{1} = v_{2} = v_{2
xmm0
xmm1
                                    {v4\_float} =
                                                               {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                                                               {0x0, 0x0},
                                                                                                                                                                           v16_int8 =
                                                                                                                                                                                                      {0x0 <repeats 16 times>
                                    .
{v4_float =
{v4_float =
                                                                                                                                               {0x0, 0x0}, v16_int8 = 
{0x0, 0x0}, v16_int8 =
xmm2
                                                                {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                                                                                                                      {0x0 <repeats 16 times>
                                                                \{0x0, 0x0, 0x0, 0x0\}, v2\_double =
                                                                                                                                                                                                      {0x0 <repeats 16 times>
xmm3
xmm4
                                    {v4\_float} =
                                                                {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                                                                {0x0, 0x0},
                                                                                                                                                                           v16_int8 =
                                                                                                                                                                                                      {0x0 <repeats 16 times>
                                                                                                                                               {0x0, 0x0}, v16_int8 = 
{0x0, 0x0}, v16_int8 =
xmm5
                                    \{v4\_float =
                                                                {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                                                                                                                     {0x0 <repeats 16 times>
                                    v4_float =
                                                               {0x0, 0x0, 0x0, 0x0}, v2_double =
хттб
                                                                                                                                                                                                     {0x0 <repeats 16 times>
                                    \{v4\_float = \{0x0, 0x0, 0x0, 0x0\}, v2\_double = \{0x0, 0x0\}, v16\_int8 = \{0x0 < repeats 12 times>
xmm7
[ IM DM ZM OM UM PM ]
                                   0x1f80
MXCSF
(gdb) n
(gdb) n
                 tch thread () at ../src/utils/asm utils.asm:37
(gdb) info registers
eax
                                   0x230a0
                                                                                  143520
ecx
                                   0x22f92
                                                                                  143250
                                   0x8
edx
                                                                                  8
ebx
                                   0x0
                                   0x24084
                                                                                  0x24084 <PCB_SET+8164>
esp
ebp
                                   0x23024
                                                                                  0x23024 <PCB_SET+3972>
                                   0x0
esi
edi
                                   0x0
                                   0x2176c
                                                                                  0x2176c <asm_switch_thread+16>
eip
eflags
                                                                                  [ IOPL=0 ]
                                   0x2
```

中间second thread这里先略过,因为我们要查看线程如何从中断恢复运行,所以我直接调试 third thread

4. 这里忽略 second thread 和 third thread 之间的调度,因为和前面的调度基本一样,主要是查看一下线程如何从中断中恢复。

打断点到 asm_switch_thread, 然后查看 third thread 线程寄存器值, esp 和 ebp 为 0x24fec 和 0x25028

```
Terminal
                     ASM_UNHANDLED_INTERRUPT_INFO db 'Unhandled interrupt happened, halt...'

db 0
     17
18
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
                     ASM_IDTR dw 0
dd 0
                    ; void asm_switch_thread(PCB *cur, PCB *next);
asm_switch_thread:
    push ebp
    push ebx
    push edi
    push esi
                         mov eax, [esp + 6 * 4] mov esp, [eax] ; ^8^ &^ &^ %^ '^ $^ ur^8^ %^ &^ %^ ext^8^
 remote Thread 1.1 In: asm_switch_thread
Breakpoint 12, asm_switch_thread () at ../src/utils/asm_utils.asm:26
Breakpoint 12, asm_swit
(gdb) n
(gdb) in
(gdb) in
(gdb) in
(gdb) asward
ex 0x246a0
ecx 0x24f96
edx 0x8
ebx 0x2
                                             147616
151446
8
                   0x8
0x2
0x24fec
0x25028
0x0
0x0
ebx
esp
ebp
esi
edi
                                             0x24fec <PCB_SET+12108>
0x25028 <PCB_SET+12168>
                                             0x21766 <asm_switch_thread+10>
[ IOPL=0 AF ]
                   0x21766
0x12
```

调度之后,可以观察到 esp 为 0x22fe8,为 first thread 中断时保存的地址,说明中断线程从中断点恢复执行的调度成功。

```
push ebp
      27
                                 push ebx
                                 push edi
      29
30
31
32
33
34
35
36
                                 push esi
                                mov eax, [esp + 5 * 4]
mov [eax], esp ; ^$^ ^ %^ %^ %^
                                                                                                  &^ )^ %^ CB^$^ /^ $^ $^ ^ ^&^ %^ &^ %^
                                 mov eax, [esp + 6 * 4]
mov esp, [eax] ; ^&^ &^ &^ %^
                                                                                                                 %^
                                                                                               $^
                                                                                                     ur^&^
                                                                                                                        &^ %^
                                                                                                                                    ext^&^
     ><mark>37</mark>
38
39
40
41
                                 pop esi
                                 pop edi
                                 pop ebx
                                 pop ebp
      42
                                 sti
      43
                                 ret
      44
                          ; int asm_interrupt_status();
                          asm_interrupt_status:
remote Thread 1.1 In: asm_switch_thread
сг8
                         0x0
efer
                         0x0
                         {v4\_float} =
                                            {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                     {0x0, 0x0}, v16_int8 = 
{0x0, 0x0}, v16_int8 =
xmm0
                                                                                                                                            {0x0 <repeats 16 times>}, v8_int
                        {v4_float = 
{v4_float = 
{v4_float = 
{v4_float = 
                                                                                                                                           {0x0 <repeats 16 times>}, v8_int:
xmm1
                                            {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0, 0x0, 0x0}, v2_double =
                                                                                                     {0x0, 0x0}, v16_int8 = 
{0x0, 0x0}, v16_int8 =
xmm2
xmm3
                                            {0x0, 0x0, 0x0, 0x0}, v2_double = 
{0x0, 0x0, 0x0, 0x0}, v2_double =
                                            {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0}, v16_int8 = {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0}, v16_int8 = {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0}, v16_int8 = {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0}, v16_int8 = {0x0, 0x0, 0x0, 0x0}, v2_double = {0x0, 0x0}, v16_int8 =
                         {v4_float =
{v4_float =
                                                                                                                                            {0x0 <repeats 16 times>}, v8_int
xmm4
                                                                                                                                            {0x0 <repeats 16 times>}, v8_int
xmm5
                         {v4_float =
                                                                                                                                           {0x0 <repeats 16 times>}, v8_int
{0x0 <repeats 12 times>, 0x80, 0
хттб
xmm7
                         \{v4\_float =
MXCSF
                        0x1f80
                                                          [ IM DM ZM OM UM PM ]
(gdb) n
(gdb) n
            tch_thread () at ../src/utils/asm_utils.asm:37
(gdb) info registers
                        0x220a0
                                                          139424
eax
                        0x24f96
                                                          151446
ecx
edx
                        0x8
ebx
                        0x2
                                                         0x22fe8 <PCB_SET+3912>
0x25028 <PCB_SET+12168>
                        0x22fe8
esp
ebp
                        0x25028
esi
                        0 \times 0
edi
                        0 \times 0
                                                          0x2176c <asm_switch_thread+16>
eip
                        0x2176c
                                                             TOPL=0 AF 1
```

Assignment 4 调度算法的实现

代码在 lab5/assignment4

• 任务要求:

在材料中,我们已经学习了如何使用时间片轮转算法来实现线程调度。但线程调度算法不止一种,

例如:

- 先来先服务
- 最短作业(进程)优先
- 响应比最高优先算法
- 优先级调度算法
- 多级反馈队列调度算法

现在,同学们需要将线程调度算法修改为上面提到的算法或者是同学们自己设计的算法。然后,同学们需要自行编写测试样例来呈现你的算法实现的正确性和基本逻辑。最后,将结果截图并说说你是怎么做的。

- 任务思路:在 program.cpp 中添加最短作业优先 SJF, 先来先服务 FCFS 和优先级调度 PRI 三种调度算法;然 后在 setup.cpp 中添加多个线程,用于测试算法思路。
- 任务步骤:

注意: ProgramManager::executeThread 函数中调度策略 schedulingPolicy 对应的调度算法为 0:RR, 1:SJF, 2:PRIORITY, 3:FCFS

1. 为了实现多种调度算法的选择,我这里修改了 program.cpp 中 ProgramManager::schedule() 函数,进行调度 算法的选择。

```
void ProgramManager::schedule(){
    if(running){
        switch (running->schedulingPolicy)
        {
            case SchedulingPolicy::SCHEDULED_RR:
                schedule_RR();
                break;
            case SchedulingPolicy::SCHEDULED_SJF:
                schedule_SJF();
            case SchedulingPolicy::SCHEDULED_PRIORITY:
                schedule_PRI();
                break;
            case SchedulingPolicy::SCHEDULED_FCFS:
                schedule_FCFS();
                break;
            default:
                break;
        }
    }
}
```

2. 添加先来先服务调度算法 FCFS

```
//先进先服务调度
void ProgramManager::schedule_FCFS()
{
   bool status = interruptManager.getInterruptStatus();
   interruptManager.disableInterrupt();

   if (readyPrograms.size() == 0)
   {
      interruptManager.setInterruptStatus(status);
      return;
   }

   if (running->status == ProgramStatus::RUNNING)
   {
      running->status = ProgramStatus::READY;
      readyPrograms.push_back(&(running->tagInGeneralList));
   }
   else if (running->status == ProgramStatus::DEAD)
```

```
{
    releasePCB(running);
}

ListItem *item = readyPrograms.front();
PCB *next = ListItem2PCB(item, tagInGeneralList);
PCB *cur = running;
next->status = ProgramStatus::RUNNING;
running = next;
readyPrograms.pop_front();
// 显示进程切换信息
//printf("pid %d is stop, and pid %d is continue...\n", cur->pid, next->pid);
asm_switch_thread(cur, next);
interruptManager.setInterruptStatus(status);
}
```

在 setup.cpp 中添加线程测例:

```
oid fifth_thread(void*arg){
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
}
void forth_thread(void*arg){
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           asm_halt();
}
void third_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           programManager.executeThread(forth_thread, nullptr, "forth thread", 1, 3);
           //asm_halt();
}
void second_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
```

```
get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           programManager.executeThread(fifth_thread, nullptr, "fifth thread", 1, 3);
    //asm_halt();
}
void first_thread(void *arg)
    // 第1个线程不可以返回
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy));
    if (programManager.running->pid==0)
    {
        programManager.executeThread(second_thread, nullptr, "second thread", 1, 3);
        programManager.executeThread(third_thread, nullptr, "third thread", 1, 3);
    }
    asm_halt();
}
```

根据代码,可以得知五个线程调度的顺序为 first thread -> second thread -> third thread -> fifth thread -> forth thread, 运行得到线程顺序符合调度算法。

```
The count of the country of the coun
```

3. 添加短作业优先调度算法 SJF:

这里设置使用ticksPassedBy来预测未来执行时间(已执行时间越短,预期剩余时间可能越长),从而实现短作业的判断。

```
//短作业优先调度
void ProgramManager::schedule_SJF()
{
   bool status = interruptManager.getInterruptStatus();
   interruptManager.disableInterrupt();
   if (readyPrograms.size() == 0)
   {
       interruptManager.setInterruptStatus(status);
       return;
   }
   // 如果当前线程仍在运行,且不是因为时间片耗尽被调度的
   // SJF是非抢占式的,应该让当前线程继续执行,除非它主动放弃CPU或结束
   if (running->status == ProgramStatus::RUNNING && running->ticks > 0)
   {
       interruptManager.setInterruptStatus(status);
       return;
```

```
// 处理当前线程状态
   if (running->status == ProgramStatus::RUNNING)
       running->status = ProgramStatus::READY;
       readyPrograms.push_back(&(running->tagInGeneralList));
   else if (running->status == ProgramStatus::DEAD)
       releasePCB(running);
   }
   // 找到估计运行时间最短的线程
   ListItem *item = readyPrograms.front();
   PCB *next = ListItem2PCB(item, tagInGeneralList);
   PCB *cur = running;
   // 使用合适的指标来评估作业长度
   // 这里使用ticksPassedBy来预测未来执行时间(已执行时间越短, 预期剩余时间可能越长)
   for (ListItem *i = readyPrograms.front(); i; i = i->next)
       PCB *program = ListItem2PCB(i, tagInGeneralList);
       // 主要排序条件: 预期总执行时间(这里用priority*10-ticksPassedBy估计)
       int current_estimate = next->priority * 10 - next->ticksPassedBy;
       int program_estimate = program->priority * 10 - program->ticksPassedBy;
       if (program_estimate < current_estimate ||</pre>
           (program_estimate == current_estimate && program->createTime < next-
>createTime))
           // 如果预期执行时间相同,选择先创建的
           next = program;
       }
   }
   next->status = ProgramStatus::RUNNING;
   running = next;
   // 显示进程切换信息
   /*printf("pid %d pid %d (lass time: %d)\n",
          cur->pid, next->pid,
          next->priority * 10 - next->ticksPassedBy);*/
   readyPrograms.erase(&(next->tagInGeneralList));
   asm_switch_thread(cur, next);
   // 恢复中断状态
   interruptManager.setInterruptStatus(status);
}
```

由于这里设置的时间片与优先级有关,所以通过设置不同的优先级来设置不同的测例的运行时间。


短进程排序为: first thread -> second thread -> fifth thread -> third thread -> forth thread

```
void fifth_thread(void*arg){
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
}
void forth_thread(void*arg){
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           asm_halt();
}
void third_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           //asm_halt();
}
void second_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
    //asm_halt();
}
void first_thread(void *arg)
    // 第1个线程不可以返回
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy));
    if (programManager.running->pid==0)
        programManager.executeThread(second_thread, nullptr, "second thread", 2, 1);
        programManager.executeThread(third_thread, nullptr, "third thread", 4, 1);
```

```
programManager.executeThread(fifth_thread, nullptr, "fifth thread", 3, 1);
programManager.executeThread(forth_thread, nullptr, "forth thread", 5, 1);

// 主动让出CPU
programManager.running->status = READY;
programManager.schedule();
}
asm_halt();
}
```

根据代码设置的线程顺序应该为 first thread -> second thread -> fifth thread -> third thread -> forth thread, 运行得到线程顺序符合调度算法。



4. 添加优先级调度算法 PRI:

利用前面在 PCB 中优先级属性 priorty 来进行优先级判断,从而实现优先级调度。

```
//优先级调度
void ProgramManager::schedule_PRI()
{
   bool status = interruptManager.getInterruptStatus();
   interruptManager.disableInterrupt();

   if (readyPrograms.size() == 0)
   {
      interruptManager.setInterruptStatus(status);
      return;
   }

   if (running->status == ProgramStatus::RUNNING)
```

```
running->status = ProgramStatus::READY;
        readyPrograms.push_back(&(running->tagInGeneralList));
    else if (running->status == ProgramStatus::DEAD)
        releasePCB(running);
    }
    ListItem *item = readyPrograms.front();
    PCB *next = ListItem2PCB(item, tagInGeneralList);
    PCB *cur = running;
    // 找到优先级最高的进程
    for (ListItem *i = readyPrograms.front(); i; i = i->next)
        PCB *program = ListItem2PCB(i, tagInGeneralList);
        if (program->priority > next->priority||(program->priority==next->priority&&program-
>createTime<next->createTime))
        {
            next = program;
       }
    }
    next->status = ProgramStatus::RUNNING;
    running = next;
    // 显示进程切换信息
    readyPrograms.erase(&(next->tagInGeneralList));
    asm_switch_thread(cur, next);
    interruptManager.setInterruptStatus(status);
}
```

在 setup.cpp 中添加测例:

这里设置优先级顺序为 first thread -> forth thread -> second thread -> third thread -> fifth thread

```
programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           //asm_halt();
}
void third_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
           programManager.executeThread(forth_thread, nullptr, "forth thread", 4, 2);
           //asm_halt();
}
void second_thread(void *arg) {
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy),
           programManager.running->createTime);
    //asm_halt();
}
void first_thread(void *arg)
{
    // 第1个线程不可以返回
    printf("pid %d name \"%s\", scheduling policy: %s ,creatTime: %d :thread has done!\n",
           programManager.running->pid,
           programManager.running->name,
           get_scheduling_policy_name(programManager.running->schedulingPolicy));
    if (programManager.running->pid==0)
    {
        programManager.executeThread(second_thread, nullptr, "second thread", 3, 2);
        programManager.executeThread(third_thread, nullptr, "third thread", 2, 2);
        programManager.executeThread(fifth_thread, nullptr, "fifth thread", 1, 2);
        programManager.executeThread(forth_thread, nullptr, "forth thread", 4, 2);
        programManager.running->status = READY;
        programManager.schedule();
    }
    asm_halt();
}
```

```
C around C manual C minutes ( Minutes) ( Min
```

五、实验总结和心得体会

- 1. 通过这次实验,我对于线程调度的过程有了更加深入的了解,初步实现了四种调度算法。
- 2. 通过这次实验, 我已经能熟练使用 gdb 进行调试, 并且通过调试, 我对于整个线程的创建, 调度, 中断恢复的过程更加熟悉。
- 3. 在这次实验中,我本来想通过时间中断去实现短作业优先调度算法,但是在实现的过程中发现,当前中断体系中没有实现时间中断的处理,所以无法实现时间中断,本来想自己实现的,但是能力有限,总是出现bug,所以暂时放弃,以后有时间的话再实现。

六、参考资料

- 1. https://gitee.com/sysu2024-osta/sysu-2024-spring-operating-system/tree/main/lab5
- 2. https://blog.csdn.net/DreamIPossible/article/details/108277473