
In the **Permissions** application, you can find a permission matrix for controlling role permissions to all pages within the content tree (in the **Pages** application).

To configure permissions for all content:

- 1. Open the **Permissions** application.
- 2. In the first **Permissions for** drop-down list, choose **Module**.
- 3. In the second drop-down list, choose **Content**.

The changes you make on the permission matrix apply immediately.



You can grant the following permissions to roles:

Browse tree	Allows members of the role to view the page content tree in the <b>Pages</b> application (not necessarily the actual page content – that is determined by the <i>Read</i> permission). For users without this permission, the system blocks the entire <b>P ages</b> application.
	Users need the <i>Browse tree</i> permission to perform page management actions via the <u>On-site editing interface</u> .
Read	Allows members of the role to access and view the <b>Page</b> , <b>Form</b> and <b>Properties</b> tabs for pages in the <b>Pages</b> application.
	The <i>Read</i> permission is also required to access:
	<ul> <li>Applications in the Content management category that are related pages (such as Checked-out items, My pages, Outdated pages, Pending pages, Recent pages)</li> <li>The On-site editing interface</li> </ul>

https://docs.xperience.io



Modify	Allows members of the role to make the following changes:
	Edit content of pages on the Page tab and Form tab.
	Move pages in the content tree.
	Move pages between workflow steps on the Page and Form tabs.
	• Modify the majority of page properties with the exception of <b>Security</b> and <b>Workflow</b> properties.
	• To modify the <b>Security</b> properties, only the <b>Modify permissions</b> permission is required.
	<ul> <li>To modify the Workflow properties, only the Manage workflow permission is required.</li> </ul>
Check in any page	Authorizes members of the role to perform the <b>Check-in</b> and <b>Undo check-out</b> actions on the <b>Properties -&gt; Versions</b> tab.
Create	Allows members of the role to create pages of any page type in the content tree.
Delete	Allows members of the role to delete any page in the content tree.
Manage workflow	Allows members of the role to approve or reject any page at any workflow step on the <b>Properties -&gt; Workflow</b> tab.
	Note: The <b>Modify</b> permission is required to move pages between workflow steps on the Page and Form tabs.
Destroy	Allows members of the role to destroy pages, i.e., delete without the <i>Undo</i> option.
Modify permissi ons	Allows members of the role to manage <u>page-level permissions</u> of any page on the <b>Properties -&gt; Security</b> tab.
	Note that the <b>Modify</b> permission is not necessary for managing page-level permissions.
Submit for	Allows members of the role to create new language versions of pages using <u>Translation services</u> .
translati on	

https://docs.xperience.io