The <u>UniGrid</u> is a complex control, so you need to explicitly define the design, content and many other configuration options. You can use two different approaches:

- An external XML configuration file, assigned through the UniGrid's **GridName** property
- ASPX markup directly within the UniGrid control definition (on the page or user control containing the UniGrid)

# Using external XML files

Organize the UniGrid XML configuration file according to the following structure (some elements are optional):

```
<?xml version="1.0" encoding="utf-8" ?>
<grid>
        <actions>
            <action />
        </actions>
        <massactions>
                <massaction />
        </massactions>
        <columns>
                <column>
                         <tooltip />
                         <filter>
                                 <parameters>
                                         <filterparameter />
                                 </parameters>
                         </filter>
                </column>
        </columns>
        <objecttype />
        <query>
                <parameter />
        </query>
        <pager>
                <key name="DefaultPageSize" value="10" />
        </pager>
                <key name="DisplayFilter" value="true" />
        </options>
</grid>
```

# Using ASPX markup

To define the UniGrid directly in the ASPX markup, you first need to register the following namespace on the web form or user control (in addition to the UniGrid user control):

```
<%@ Register Namespace="CMS.UIControls.UniGridConfig" TagPrefix="ug" Assembly="CMS.
UIControls" %>
```

Then add elements inside the UniGrid control tags according to the following structure:

```
<cms:UniGrid runat="server" ID="UniGrid" ... >
        <GridActions>
        <ug:Action />
    </GridActions>
        <GridMassActions>
                <ug:MassAction />
                . . .
        </GridMassActions>
    <GridColumns>
        <ug:Column>
            <Tooltip />
            <Filter>
                                 <CustomFilterParameters>
                                         <ug:FilterParameter />
                                 </CustomFilterParameters>
            </Filter>
            . . .
        </ug:Column>
    </GridColumns>
    <PagerConfig DisplayPager="true" ... />
    <GridOptions DisplayFilter="true" ... />
</cms:UniGrid>
```

# **Notes**

- When using markup, you need to specify the data source of the control directly through the UniGrid's properties (**Query**, **ObjectType** or **DataSource**).
- You can use the IntelliSense in Visual Studio to help find the appropriate elements and attributes.

#### UniGrid elements

The following reference describes all elements that you can define for UniGrid controls (and their attributes):

- Actions (GridActions)
  - Action (ug:Action)
- Mass actions (GridMassActions)

- Mass action (ug:MassAction)
- Columns (GridColumns)
  - O Column (ug:Column)
    - Tooltip
    - <u>Filter</u>
- Object type
- Query
  - O <u>Parameter</u>
- Pager (pagerConfig)
- Options (GridOptions)

## <actions> (<GridActions>)

The *actions* element defines a column with various actions (Edit, Delete, View, etc.) for every row of the UniGrid, represented by icons. Individual actions must be defined by child **<action>** elements.

Actions attributes	Description	Sample value
cssclass	Specifies the name of a CSS class from the website's stylesheet that the control applies to the actions column.	"UniGridCustomA ctionsColumn"
parameters	A list of columns from the data source separated by semicolons. The UniGrid provides the specified columns as parameters in the <b>onclick</b> or <b>menuparameter</b> attributes of child <b><act ion=""></act></b> elements.	"AttachmentGUID ; AttachmentForm GUID"
showhead er	Indicates whether the UniGrid displays the header of the actions column. The default value is true.	
width	Sets the width of the actions column in the UniGrid.	"30%" "100px"

#### <action> (<ug:Action>)

Action elements define individual actions offered by the UniGrid.

- Implement the functionality of individual actions through handlers of the UniGrid's OnAction event. See: <u>UniGrid Getting started</u>
- You can add advanced logic for individual actions buttons in handlers of the UniGrid's OnExternalDataBound event (for example, defining for which rows the actions are available). See: <u>UniGrid - Implementing custom functionality</u>

Action attributes	Description	Sample value
caption	Text used as the tooltip of the image defined in the <b>icon</b> attribute. You can enter the name of a <u>resource string</u> enclosed between \$ characters.	"\$General. Delete\$"
commanda rgument	The name of the column whose value the action passes as the <b>actionArgument</b> parameter of <b>OnAction</b> event handlers.	
	If not defined, the action uses the first column in the source data.	
confirmati on	The text displayed in a JavaScript confirmation for the action. Most commonly used as a confirmation for delete type actions. You can enter the name of a <a href="resource string">resource string</a> enclosed between \$ characters.	"\$General. ConfirmDelete\$"

contextme	The relative path to a control (.ascx file) that implements a context menu for the action.	"~
nu	Controls created for this purpose must inherit from the CMS.Base.Web.UI. CMSContextMenuControl class.	/CMSAdminCont rols/UI/UniGrid /Controls /ObjectMenu. ascx"
externalso urcename	Name of the action passed as the <b>sourceName</b> parameter of <b>OnExternalDataBound</b> event handlers.	"deletefile"
fonticoncla ss	Sets the action's image using a <u>font icon</u> . Enter the name of a CSS class that defines the font icon.	"icon-eye"
	To use the default font icon classes, you need to link the system's CSS stylesheets onto the page containing the UniGrid – call the <b>CMS.Base.Web.UI.CssRegistration. RegisterBootstrap(Page)</b> method in the page's code behind.	
	Alternatively, you can set the action's image using a standard image file through the <b>icon</b> attribute.	
fonticonsty le	Sets the color of the action's font icon (specified through the <b>fonticonclass</b> attribute). The default options are:  • default (gray) • allow (green) • warning (orange) • critical (red)	"default" "allow" "warning" "critical"
icon	Use the icon attribute to set the action's image using a standard image file (if you do not wish to use a font icon).	"delete.png"
	Specify the name of an image file located in the folder defined by the <b>ImageDirectoryPath</b> property of the UniGrid.	
menupara meter	Contains an array of parameters passed to the control implementing the action's context menu (the path to this control must be specified in the <b>contextmenu</b> attribute). You can retrieve these parameter in the control's code using the <b>GetContextMenuParameter</b> JavaScript function.	"new Array ('cms.site', '{0}')'
	You can insert the values of columns defined in the <b>parameters</b> attribute of the parent <b><acti< b=""> <b>ons&gt;</b> element using the following expressions:</acti<></b>	
	{0} - first parameter {1} - second parameter	
	and so forth.	
		H1 6:H
mousebutt on	Specifies which mouse button causes the action's context menu to appear (if a context menu is enabled via the <b>contextmenu</b> attribute).	"left" "right"

name	Identifies the action in the code that implements the functionality of the UniGrid's actions. The system passes the action name to handlers of the <b>OnAction</b> event through the <b>actionName</b> parameter.	"delete"
	Predefined UniGrid actions  If the UniGrid has an object type data source (specified either through the <i><objecttype></objecttype></i> element or the <b>ObjectType</b> property), you can use the following predefined actions without writing any code:	
	<ul> <li>#delete - deletes the object displayed on the given UniGrid row (removes the object from the Kentico database). The action automatically requires users to have the <i>Delete</i> permission for the given object type.</li> <li>#destroyobject - deletes the object and its version history (the object cannot be restored from the system's recycle bin). The action automatically requires users to have the <i>Delete</i> permission for the given object type.</li> <li>#move / #moveup / #movedown - moves items within ordered lists of objects. The #mo ve action allows drag and drop to any position, #moveup and #movedown switch objects with the previous or next item in the list.</li> <li>Only works if the object type has a defined order for the data records (uses a database column to store the item order).</li> <li>The actions automatically require users to have the Modify permission for the given object type.</li> <li>Sorting must be disabled for all columns in the UniGrid to ensure that the order is displayed correctly. Disable the AllowSorting attribute of the options element or the allowsorting attribute of individual column elements.</li> <li>All items in the UniGrid's data must belong to the same order. If the object type contains multiple subsets of objects that each have their own separate order, you need to filter the data to include only items that belong to a single order (for example through the UniGrid control's WhereConditon property).</li> </ul>	
onclick	The JavaScript OnClick function for the given action  You can insert the values of columns defined in the <b>parameters</b> attribute of the parent <b><actions></actions></b> element using the following expressions:	"alert('{0}');"
	<ul><li>{0} - first parameter</li><li>{1} - second parameter</li></ul>	
	and so forth.	
Action secur	rity	
modulena me	Add this attribute (and the <i>permissions</i> or <i>uielements</i> attributes) to leverage the Kentico security model for the action. You can make the action usable only by a limited group of users.	"cms. ecommerce"
	Enter the code name of the module related to the action. You can find information about modules, their permissions and UI elements in the <b>Modules</b> application of the Kentico administration interface.	
permissions	Sets the code name of the permission that users must have to perform the action. The permission must belong to the module specified in the <b>modulename</b> attribute.	"modifyorders"
uielements	Sets the UI element that users must be allowed to view in order to perform the action. The user interface element must belong to the module specified in the <b>modulename</b> attribute.	"orders.general"

hideifnota	Indicates whether the UniGrid completely hides the action for users who are not allowed to
uthorized	perform it (as defined by the attributes above).



#### **Default object menu actions**

If your UniGrid control uses an object type data source (specified either through the *<objecttype>* definition element or the **ObjectType** property), the grid automatically displays an action that opens a context menu when clicked. This menu provides options that allow users to Export, Backup, Restore or Destroy the listed objects. Some types of objects do not support all menu options.

The UniGrid does not add the default object menu action if you manually specify another action with a **contextmenu** attribute, or if there are no actions at all defined for the grid. You can also disable the menu action by setting the **Show ObjectMenu** property of the UniGrid to *false*.

# <massactions> (<GridMassActions>)

The *massactions* element is a container for the definitions of actions that can apply to multiple UniGrid rows. The element itself has no attributes – each mass action has its own settings. Define individual mass actions by adding child **<massaction>** elements.

#### <massaction> (<ug:MassAction>)

Massaction elements represent actions that can apply to multiple UniGrid rows. If you define at least one mass action:

- The UniGrid automatically displays a column that allows users to select rows.
- The following mass action controls are displayed below the UniGrid's main item listing and pager: Scope selector (all items or selected items), Mass action selector, OK button

Massaction attributes	Description	Sample value
behavior	Determines whether the mass action redirects users to a different page or opens a modal dialog. The corresponding values are:  • redirect	"redirect" "openmodal"
	<ul> <li>openmodal</li> <li>In both cases, the URL of the target page or dialog must be set through the url attribute or indirectly using a predefined mass action.</li> </ul>	
caption	Sets the text displayed in the mass action selector. You can enter the name of a <u>resource string</u> enclosed between \$ characters.	"\$General.Delete\$"
name	Identifier of the mass action ( <b>required</b> for all mass actions).  Allows you to specify predefined mass actions. Predefined mass actions do not require development of additional pages or components and have an automatic <b>u rl</b> value.  • <b>#delete</b> - deletes the selected objects (removes the objects from the Kentico database). The action automatically requires users to have the <i>Delete</i> permission for the given object type.	"#delete"
url	Sets the URL of the page or modal dialog that opens when a user performs the mass action. Not necessary for predefined mass actions.  The target page must contain the logic that performs the mass action.	"~/CMSAdminControls /UI/UniGrid/Pages /MassDelete.aspx"



# <columns> (<GridColumns>)

The *columns* element represents the main content of the UniGrid. The *<columns>* element itself has no attributes, since each column has its own settings. Define individual columns by adding child **<column>** elements.

## <column> (<ug:Column>)

*Column* elements define the UniGrid's columns. You can implement advanced formatting logic for the cells in columns in handlers of the UniGrid's **OnExternalDataBound** event. See: <u>UniGrid - Implementing custom functionality</u>

Columns can contain child **<tooltip>** and **<filter>** elements.

Column attributes	Description	Sample value
action	Sets the name of an action that the UniGrid performs when a user clicks the content of the column's cells. You need to define an action with a matching name via the <b>name</b> attribute of an <b><action></action></b> element.	
allowsorting	Indicates whether the column can be used to sort the rows of the UniGrid.  Note: To disable sorting for all columns in the UniGrid, set the AllowSorting attribute of the options element to false.	
caption	Specifies the text displayed as the header for the column. You can enter the name of a <u>resource</u> <u>string</u> enclosed between \$ characters.	"\$general. name\$"
commanda rgument	The name of the column whose value the column passes as the <b>actionArgument</b> parameter of <b>OnAction</b> event handlers (if the column uses an action specified via the <b>action</b> attribute).  If not defined, the action uses the first column in the source data.	
cssclass	Specifies the name of a CSS class from the website's stylesheet that the UniGrid uses to style the appearance of the column.	"UniGridCusto
externalso urcename	Sets a name for the column that the control passes as the <b>sourceName</b> parameter of <b>OnExter nalDataBound</b> event handlers. You can use such handlers to implement custom functionality in the column's cells.  Using column transformations	"user_modify' "#yesno" "#culturenam e {\$general. default\$}"
	The UniGrid provides built-in transformation functions that allow you to format the column's content without writing any code. You can assign the following values into the <i>externalsourcen ame</i> attribute by default:	

- #yesno applies to columns with a bit (boolean) type data source. Converts the values to text: Yes (colored green) or No (colored red).
- #yes applies to columns with a bit (boolean) type data source that have a true value (1).
   Displays: Yes (colored green).
- #isnullyesno displays Yes (colored green) if the column's value is null or DBNull, No (colored red) for all other values.
- #sitename converts site ID (integer) values into site display names.
- **#sitenameorglobal** converts site ID values into site display names. If a record is not related to a specific site (i.e. the site ID is *null*), the cell displays *(qlobal)* as its value.
- #countryname converts ID (integer) values into the display name of the Country object with the given ID.
- #culturename converts culture code text values into the full name of the matching culture. Other available variants are #cultureshortname and #culturenamewithflag.
- #username converts ID (integer) values into the user name of the User account with the given ID.
- #classname converts ID (integer) values into the display name of the Kentico class with the given ID.
- #htmlencode HTML encodes text values.
- #url converts URL text values into links.
- #mailto converts email addresses into links.
- #filesize recalculates file size values in bytes to values in kilobytes (kB), megabytes (MB), gigabytes (GB), etc.
- #date formats datetime values to display only the date, without the time. For example: 4
  /15/2013
- #time formats datetime values to display only the time, without the date. For example: 7: 58:39 AM
- #userdatetime modifies datetime values according to the <u>time zone</u> settings of the user viewing the page.
- #usertime formats datetime values to display only the time, without the date. The
  function modifies the time according to the <u>time zone</u> settings of the user viewing the
  page
- #userdatetimegmt modifies datetime values according to the time zone settings of the
  user viewing the page and displays the difference from GMT.
- #usertimezonename displays the name of the time zone configured for the user viewing the page.

For example: Arizona (GMT - 07.00)

You can also Register custom UniGrid transformations.

To set default values for functions, add the "|" character as a separator and specify the value. For example: #username|None. The column uses the default value if the result of the function is null or an empty string.

You can also specify custom transformation expressions for columns that contain the ID values of other objects. For example, you can use the following *externalsourcename* values for user ID columns:

- #transform: cms.user.fullname displays the full name of each user instead of the ID.
- #transform: cms.user: {%FullName%} ({%UserName%}) loads the user object with the matching ID for each row and formats it according to the entered macro expressions, e.g. Andrew Jones (Andy).

If a user decides to sort the UniGrid according to a column with an ID transformation, the order of the rows is based on the ID values, not the output of the transformation.

href	If you enter a URL here, the UniGrid generates a link to the given URL around the content of the column's cells. Macros {0}, {1}, can be used to access parameters defined by the <b>parameters</b> attribute.	"~/page.aspx'
icon	Name of an image that the UniGrid displays in column cells after the content loaded from the data source. The image must be located in the folder defined by the <b>ImageDirectoryPath</b> property of the UniGrid.	"edit.png"
istext	Indicates whether the content of the column is of type <i>Text</i> or <i>nText</i> . The UniGrid generates a special OrderBy clause according to this attribute's value, so you need to set it correctly to enable sorting for the column.	
localize	Indicates whether the column supports <u>localization</u> for string values.	
maxlength	Sets the maximum number of characters that can be displayed in the column's cells. The last 3 characters are replaced by periods.	
columnna me ( <b>name</b> in markup)	Sets a custom name for the column, which the UniGrid uses in the column dictionary accessible through the <b>NamedColumns</b> property.	
parameters	Specifies the names of columns from the data source, which can be used as parameters in the URL generated by the <b>Href</b> attribute. Separated by semicolons.	
source	Name of the column from the data source that the UniGrid uses as the source for the column's content.	
	Use the ##ALL## macro to specify all columns in the data source.	
sort	Defines the column name that the UniGrid uses for sorting if you enter the ##ALL## macro into the <b>source</b> attribute.	
style	CSS style applied to the entire column.	"padding: 10px"
visible	Indicates whether the column is visible.	
width	Determines the width of the column.	"20%" "200px"
wrap	Indicates whether the column uses word wrapping.	

## <tooltip>

If you add a *tooltip* element under a column, the UniGrid displays a tooltip when a user hovers over the content of the column's cells. If an icon is present in the cell, the tooltip is displayed over the icon instead of the text.

Tooltip attributes	Description
encode	Indicates whether the output of the tooltip is HTML encoded.
externalso urcename	Name used to identify the tooltip through the <b>sourceName</b> parameter of handlers of the UniGrid's <b>OnExternalD ataBound</b> event. You can use a handler to customize the appearance of the tooltip.
source	Name of the column from the UniGrid's data source that is used as the source for the tooltip's content.

width	Determines the width of the tooltip.
-------	--------------------------------------

### <filter>

If you add a *filter* element under a column, the UniGrid uses the given column in the filter.

Filter attributes	Description	Sample value
defaultvalue	Specifies a default values that the UniGrid presets in the filter when the page is loaded. The value must match the <b>type</b> of the filter.	
fieldname	Sets a custom name that can be used to identify the given filtering field in the form used by the default UniGrid filter. You can work with the field using the <b>FilterForm</b> property of the UniGrid. For example:	
	<pre>// Hides the filtering field with the "customField" fieldname value in the default UniGrid filter UniGrid.FilterForm. FieldsToHide.Add("customField");</pre>	
format	Allows you to define a custom format for the WHERE clause that the default filter generates for the column. You can use the following dynamic expressions:	" [{0}] {1} N'% {2}%' "
	<ul> <li>{0} - returns the name of the associated column (or the value of the filter element's source attribute)</li> <li>{1} - returns the operator selected in the default filter's dropdown list</li> <li>{2} - returns the filtering value (entered into the default filter's textbox)</li> </ul>	(2) /0
	<b>{3}</b> - resolves into the default WHERE condition  The default WHERE condition is [{0}] {1} {2}, but automatically adds:	
	<ul> <li>Single quotes around string values</li> <li>The N prefix to string values if required</li> <li>% wildcards around string values for LIKE operators</li> <li>is null conditions for inequality operators</li> </ul>	
path	Assigns a custom filter for the column instead of the default UniGrid filter. Enter the path to the user control (.ascx file) that implements the filter.	
	<ul> <li>If set, the filter ignores the <b>type</b> attribute.</li> <li>The default relative path is ~/CMSAdminControls/UI/UniGrid/Filters/.</li> </ul>	
	For more information, see: <u>Creating custom UniGrid filters</u>	
size	Determines the maximum amount of characters that users can enter into the textbox of the default filter.	
	<ul> <li>Available for Text, Integer, Double and Decimal filter types.</li> <li>The default value is 1000.</li> </ul>	
source	Sets the name of the column used in the WHERE clause generated by the filter.	

type	Determines the filter type that the UniGrid creates for the given column. We recommend setting the value according to the data type of the column: <i>text</i> , <i>bool</i> , <i>integer</i> , <i>double</i> or <i>decimal</i> If your UniGrid control uses an object type data source, you can filter the objects according to their site bindings:	"text" "bool" "integer" "double"
	<ol> <li>Add a <b><filter></filter></b> element under any column (the data of the column is not used)</li> <li>Set the value of the <b>type</b> attribute to <i>site</i>.</li> </ol>	"decimal" "site"

### <objecttype>

The *objecttype* element defines the type of the Kentico objects that the UniGrid loads and displays.



**Note**: Object type data sources are not supported for objects representing pages. In these cases, you can load the required data:

- Through the **<query>** element.
- By assigning a data source manually through the UniGrid control's **DataSource** property (before its *ReloadData()* method is called).

Objecttype attributes	Description	Sample value
columns	Names of the object type's columns that the UniGrid retrieves.  Separate the columns using commas.  If empty, all the UniGrid retrieves all columns.  By default, the values of the first column are passed as the actionArgument parameter of the UniGrid's OnAction event handlers. You can override this column in the definition by specifying a column name in the commandargument attribute of individual <action> elements.</action>	
name	Must contain the object type value for the given type of Kentico object. To find a list of available object type values, open the <b>System</b> application in the Kentico administration interface and select the <b>Object types</b> tab.	"cms. user"

### <query>

The *<query>* element specifies the query that retrieves the data displayed in the UniGrid from the Kentico database. The query element can contain *>parameter>* child elements.



To work with the system's queries:

- 1. In the Kentico administration interface, open the **Modules** application.
- 2. Edit the related module.
- 3. Open the **Classes** tab.
- 4. Edit the related class.
- 5. Manage the queries on the **Queries** tab.

You can alternatively assign the UniGrid's data source:

- Through the **<objecttype>** element.
- Through the UniGrid control's **Query** or **ObjectType** properties.

• By assigning an external data source in the UniGrid control's **DataSource** property (before its *ReloadData()* method is called).

Query attributes	Description	Sample value
columns	Names of the columns that the query retrieve.  Separate the columns using commas.  If empty, all the query retrieves all columns.  By default, the values of the first column are passed as the actionArgument parameter of the UniGrid's OnAction event handlers. You can override this column in the definition by specifying a column name in the commandargument attribute of individual <action> elements.</action>	
name	Must contain the code name of the used system query in format: <class name="">.<query name=""></query></class>	"cms. site. selectsite list"



**Tip:** When using a *<query>* data source together with UniGrid actions that target specific objects in the list (editing, deleting, etc.), you need to specify the ID column of the given data as an action argument. Use one of the following options:

- List all required data columns in the *query*> element's **columns** attribute, with the ID column first
- Set the **parameters** attribute of the definition's *<actions>* element, and include the ID column there
- Set the **commandargument** attribute of individual <action> elements in the definition to the name of the ID column

## <parameter>

Parameter elements allow you to define the values of parameters for the parent <query> element.

Parameter attributes	Description	Sample value
name	Sets the name of the parameter. Insert parameters into queries using the following syntax: @  For example, if your query looks like this:	
	SELECT TOP @customTop FROM CMS_User	
	You need to enter <i>customTop</i> into the <b>name</b> attribute. The query then uses the <b>value</b> of the parameter element instead of the <b>@customTop</b> expression.	
type	The type of the parameter.	"String" "Int" "Double" "Decimal" "Bool"
value	The value of the parameter.	



# <pager> (<pagerConfig>)

The pager element defines the behavior of the UniGrid pager. You can either add the settings as child **<key>** elements in the UniGrid's XML configuration file, or as attributes of the *<PagerConfig>* element directly in the control's markup.

The following settings are available:

Key name	Description	Sample value
DisplayPa ger	Indicates if the UniGrid displays a pager. <i>True</i> by default.	<key name="&lt;br&gt;DisplayPager" value="&lt;br&gt;false"></key>
DefaultPa geSize	Defines the default amount of rows displayed on one UniGrid page. If the value is not included among the options defined by the <b>PageSizeOptions</b> key, the system automatically inserts the value as an additional option.	<key <br="" name="&lt;br&gt;DefaultPageSize">value="10" /&gt;</key>
PageSizeO ptions	Can be used to override the default values offered by the page size selector. Values must be separated by commas.  You can use the ##ALL## value to add an option that lists all available rows on a single page (not recommended if you have objects with a very large number of records).  The default values are defined by the CMSDefaultPageSizeOptions web.config key (5, 10,25,50,100 if it is not set).	<key <br="" name="&lt;br&gt;PageSizeOptions">value="10,50,200" /&gt;</key>
ShowDire ctPageCo ntrol	If true, the pager displays a textbox that allows users to change the page directly by entering a number.  If all three page navigation keys (ShowDirectPageControl, ShowFirstLastButtons, ShowP reviousNextButtons) are false, the UniGrid only loads a limited number of records based on the configured page size.	<key name="&lt;br&gt;ShowDirectPageContr&lt;br&gt;ol" value="true"></key>
ShowFirst LastButto ns	If true, the pager includes links to the first and last page (if there is a large enough number of items). False by default.  If all three page navigation keys (ShowDirectPageControl, ShowFirstLastButtons, ShowPageViousNextButtons) are false, the UniGrid only loads a limited number of records based on the configured page size.	<key name=" ShowFirstLastButtons " value="true"></key>
ShowPage Size	If true, the pager displays the page size selector.	<key <br="" name="&lt;br&gt;ShowPageSize">value="false" /&gt;</key>
ShowPrev iousNextB uttons	If true, the pager displays buttons that link to the previous and next page.  If all three page navigation keys (ShowDirectPageControl, ShowFirstLastButtons, ShowPreviousNextButtons) are false, the UniGrid only loads a limited number of records based on the configured page size.	<key name="&lt;br&gt;ShowPreviousNextBut&lt;br&gt;tons" value="false"></key>
ShowPrev iousNextP ageGroup	If true, the pager displays links to the previous and next groups of page links.	<key <br="" name="&lt;br&gt;ShowPreviousNextPag&lt;br&gt;eGroup" value="false">/&gt;</key>
VisiblePag es	Determines the amount of page links displayed in one group.	<key name="&lt;br&gt;VisiblePages" value="&lt;br&gt;5"></key>



# <options> (<GridOptions>)

The options element configures additional settings and special features of the UniGrid control. You can either add the settings as child **<key>** elements in the UniGrid's XML configuration file, or as attributes of the *<GridOptions>* element directly in the control's markup.

The following settings are available:

Key name	Description	Sample value
AllowSo rting	If true, users can sort the rows displayed by the UniGrid according to the values of individual columns (depending on the settings of the <b>allowsorting</b> attribute of the <b>column</b> elements). If false, sorting is always disabled for all columns.	<key name="AllowSorting" value="false"></key>
	The default value is <i>true</i> .	
DisplayF ilter	Indicates whether the UniGrid displays a filter above the grid. If the number of displayed rows is lower than the value of the <b>FilterLimit</b> key, the filter is hidden despite this setting.	<key name="DisplayFilter" value="true"></key>
FilterLi mit	The UniGrid displays the filter only if the number of displayed rows is greater than or equal to this key's value. The default value is loaded from the <b>CMSDefa ultListingFilterLimit</b> web.config key.	<key name="FilterLimit" value="10"></key>
FilterPath	Allows you to replace the whole default UniGrid filter with your custom filter. Enter the path to the user control (.ascx file) that implements the filter.	<pre><key <="" name="FilterPath" pre="" value=" /CMSAdminControls/UI/UniGrid /Filters/TextSampleFilter.ascx"></key></pre>
	<ul> <li>If set, individual filter settings for columns are ignored.</li> </ul>	/>
	For more information, see: <u>Creating custom UniGrid filters</u>	
ShowSel ection	Indicates whether the UniGrid displays a column that allows users to select the rows of the grid. You can use selection to perform mass actions that affect multiple rows.	<key name="ShowSelection" value="true"></key>
	You can access the selected rows in the API through the <b>SelectedItems</b> property of the UniGrid.	
	Note: The selection column is automatically enabled if the UniGrid definition contains at least one <b>massaction</b> element.	
Selectio nColumn	Sets the name of the column from which the UniGrid loads values into the array of selected rows. You can access the array of selected rows through the <b>Selecte dItems</b> property of the UniGrid.	<key name="SelectionColumn" value="SiteName"></key>
	By default the UniGrid uses the first column in the data source.	
ShowSo rtDirecti on	Determines if the UniGrid displays an arrow showing the current sorting direction in the header of the column used for sorting.	<key name=" ShowSortDirection" value=" false"></key>