The CMSEditModeButtonEditDelete control displays a pair of buttons that allow content editors to edit or delete pages. The buttons only appear in the **Edit** mode of the **Pages** application and in <u>On-site editing mode</u>.



Tip: Many CMS listing controls (and web parts), such as the <u>CMSRepeater</u> (Repeater), have the **ShowEditDeleteButtons** (**Show Edit and Delete buttons**) property, which automatically adds the CMSEditModeButtonEditDelete control next to every displayed page. The system automatically sets the Path of these controls to match the displayed page.

Getting started

The following tutorial shows how to display a pair of buttons that edit or delete a specific news page:

- 1. Create a new ASPX page template.
- 2. In Visual Studio, drag the CMSEditModeButtonEditDelete control from the toolbox onto the page template's form.
- 3. Set the Path property of the control to: /News/New-Consulting-Services

```
<cms:CMSEditModeButtonEditDelete ID="CMSEditModeButtonEditDelete1" runat="server"
Path="/News/New-Consulting-Services" />
```

4. Switch to the template's code behind and add using statements for the following namespaces:

```
using CMS.PortalEngine;
using CMS.Helpers;
using CMS.DocumentEngine.Web.UI;
using CMS.Base.Web.UI;
```

5. Add the following code to the **Page_Load** method:



The code above is required if you wish to use the control individually on an ASPX page template.

6. Create a page based on the template in the Kentico administration interface.

If you view the page in the Edit mode of the Pages application, the control displays a pair of buttons:



If you click the **Edit** button, the control redirects you to the editing form of the /News/New-Consulting-Services page. If you click **D elete**, the system deletes the given page.

Adding the control to transformations

 $You \ can \ add \ the \ CMSE dit Mode Button Edit Delete \ control \ into \ the \ code \ of \ ASCX \ \underline{transformations} \ or \ Item \ templates.$

https://docs.xperience.io

<cms:CMSEditModeButtonEditDelete runat="server" id="btnEditDelete" Path='<%# Eval
("NodeAliasPath") %>' />

Alternatively, you can add the default version of the control to transformations through the following expression:

##editbuttons##

Configuration

You can set the following properties for the CMSEditModeButtonEditDelete control:

Property name	Description	Sample value
DeleteText	Sets the caption of the delete button. If not set, the default text is "Delete".	"Delete article"
EditMode	Determines which buttons the control displays. Possible options are both, just the Edit button, or just the Delete button. By default, both buttons are included.	"Both" "Edit" "Delete"
EditText	Sets the caption of the edit button. If not set, the default text is "Edit".	"Edit article"
Path	Path of the page that the control edits/deletes.	"/whitepapers /myfirstpaper"

Appearance and styling

The appearance of the CMSEditModeButtonEditDelete control is determined by the following CSS classes:

CSS class name	Applies to	
CMSEditModeButtonEdit	The edit button's <a> element.	
CMSEditModeButtonDelete	The delete button's <a> element.	

The recommended place to define these classes is in a Kentico <u>stylesheet</u> using the **CSS stylesheets** application.

You can apply stylesheets to:

- Entire websites
- Individual pages that contain the control

https://docs.xperience.io 2