To allow users to work with widgets, you need to create widget zones on your website's pages. You can set up widget zones on:

- Portal engine page templates
- Portal engine sections of ASPX templates

By default, all zones on portal engine templates are static web part zones. Only the website's designers can modify the content of web part zones by <u>adding web parts</u>. Widget zones represent sections of the page that other types of users can customize.

To change a web part zone into a widget zone:



Warning: Changing the widget type of a zone removes all instances of web parts or widgets placed in the given zone.

- 1. Open the **Pages** application.
- 2. Select the page in the content tree.
- 3. Switch to the **Design** tab.
- 4. Open the properties dialog of the given web part zone:
  - Expand the zone's menu ( ) and click Configure.
     or
  - Double click the zone header.
- 5. Set the zone's **Widget zone type** property:

Zone type	Description
None	Standard web part zones.
User personalization	Allows registered users to personalize the zone's widget content on the <i>live site</i> .  Each user has their own unique version of the zone. The personalized content cannot be seen by other users.
Customization by page editor	Allows website editors to work with widgets:  on the Page tab of the Pages application when editing pages in on-site editing mode
Customization by group administrator	Allows administrators of the group that owns the page to work with widgets on the <i>liv</i> e site.

### 6. Click OK.

The zone now provides an area on the page that users can customize (according to the selected zone type). You can add default widget content into the zone.



## Specifying widget zone types in code


Changing the *WidgetZoneType* property directly in layout code does not save the changes in the database. You need to set the *Widget zone type* property by configuring the zone properties.

# Creating default widget content for zones


You can set default content for widget zones by editing pages in the Pages application on the Design tab:

1. Right-click the header of the widget zone and click **Add new widget** in the menu.

https://docs.xperience.io



- 2. Select a widget from the catalog. You can only choose the widgets that are <u>allowed</u> for the given type of widget zone.
- 3. Click Select.
- 4. Set the values of the widget's properties (some widgets may be configured to skip the property configuration dialog).



#### 5. Click OK.

The system adds the widget into the zone. Repeat the process to define any default widget content for the zone. The zone displays the default widgets on the page until users edit the content (depending on the type of the zone).



**Important**: The widgets that you add on the **Design** tab only represent the *default* content of the zone. Changes that you make to the default widgets do NOT affect pages where users have already modified the widget content.

## Adding widget actions to pages

You can place the Widget actions web part onto pages that contain widget zones. The web part allows users to:

- Add widgets
- Reset all widget zones to their default content



The web part only works with the type of widget zone specified in its **Widget zone type** property. When a user clicks the **Add new widget** button, the web part places the widget into the zone specified by the **Widget zone ID** property. Users can drag the widget into another zone if the default placement is not suitable.

https://docs.xperience.io 2



**Tip**: When creating pages with *editor* widget zones, you can enable the **Use main menu** property of the *Widget actions* web part. This causes the web part to display the action buttons in the header of the main edit menu on the **Page** tab in the Pages application, instead of inside the page content.

https://docs.xperience.io 3