Orbitask Product Guide

Version 4.3. This guide explains how to set up and use Orbitask, the task and project management platform for growing teams.

Getting started

When you sign up you create a workspace. A workspace contains all of your team's projects, members and settings, and it is billed as a single subscription.

To invite people, go to Settings > Members > Invite and enter their email addresses. Invitations expire after 7 days. You can also share an invite link that admins can disable at any time.

Roles

Every person in a workspace has one role. The Owner controls billing and can delete the workspace; there is exactly one Owner. Admins manage members, integrations and workspace settings. Members create and edit projects and tasks. Guests only see projects shared with them.

Projects and tasks

Projects group related tasks. Each task has a title, description, assignee, due date, priority (Low, Medium, High or Urgent), labels and custom fields. Tasks can have subtasks nested up to 3 levels deep.

Views

Every project can be displayed as a List, Board (Kanban), Calendar or Gantt view. Gantt view is available on the Team, Business and Enterprise plans. Saved view filters are shared with everyone in the project.

Dependencies and recurring tasks

A task can be marked as blocked by another task. When the blocking task's due date moves, Orbitask can shift dependent tasks automatically if "auto-schedule" is enabled on the project. Recurring tasks are created again automatically when the previous occurrence is completed, using daily, weekly, monthly or custom intervals.

Automations

Automations run actions when something happens in a project, for example "when a task moves to Done, notify the project channel in Slack" or "when a task is overdue, raise its priority to Urgent".

Each action an automation performs counts as one automation run. An automation with a trigger and three actions therefore uses three runs each time it fires. The monthly allowance for each plan is listed in the Plan limits table.

Automation runs reset on the 1st day of each calendar month at 00:00 UTC. Unused runs do not roll over to the next month. When a workspace reaches its allowance, automations pause until the next reset and Admins receive an email; no tasks are lost.

Integrations and apps

Orbitask integrates with Slack, Microsoft Teams, Google Drive, GitHub, GitLab and Zapier. Admins connect integrations under Settings > Integrations. The GitHub and GitLab integrations link commits and pull requests to tasks when the task ID (for example ORB-123) appears in the commit message.

Mobile and desktop apps

The mobile apps require iOS 16 or later or Android 10 or later. Desktop apps are available for macOS 13 or later and Windows 10 or later. Push notifications can be configured per project from the app's notification settings.

Plan limits

The table below lists the usage limits for each plan. Limits apply per workspace unless stated otherwise.

Limit	Free	Team	Business	Enterprise
Members	3	Unlimited	Unlimited	Unlimited
Projects	5	Unlimited	Unlimited	Unlimited
Storage	1 GB	100 GB	1 TB	Unlimited
Max file upload	25 MB	250 MB	250 MB	5 GB
Automation runs per month	100	5,000	25,000	250,000
Guest seats per paid seat	0	5	10	Unlimited
Version history	7 days	90 days	1 year	Unlimited

If a workspace goes over its storage limit, existing files remain available but new uploads are blocked until files are deleted or the plan is upgraded.

Security and administration

Authentication controls

Any user can enable two-factor authentication. On Business and Enterprise plans, Admins can require two-factor authentication for every member. SAML single sign-on (SSO) with Okta, Microsoft Entra ID or Google Workspace is available on Business and Enterprise. Automated user provisioning with SCIM is available on Enterprise only.

Audit log

The audit log records sign-ins, permission changes, exports and deletions. It is available on Business (retained for 1 year) and Enterprise (retained for 3 years).

Deleting a workspace

Only the Owner can delete a workspace, from Settings > Workspace > Delete. Deleted workspaces can be restored by the Owner for 30 days. After 30 days all data is permanently deleted and cannot be recovered.