CS061 - Lab 1 Welcome to the LC-3!

1 High Level Description

Today's lab will get you set up, and cover the basics of how to use the LC3 Assembler/emulator, and have you write a tiny program in LC-3 Assembly language.

The specs for today's lab are rather lengthy, as there are a lot of new ideas & activities to cover. But don't panic - each step is pretty simple, and most future lab specs will be shorter (but harder!)

2 Objectives for This Week

- 1. Set up LC3Tool on your computer.
- 2. Introduction to the basics of LC3 programming
- Exercise 0: Hello World!
- 4. Exercise 1: Implement, run, and inspect a simple program yourself
- 5. So am I an assembly language programmer yet??

NOTICES:

We do encourage you to help one another and actively collaborate on your <u>lab exercises</u>
 (but NOT on your programming assignments, not EVER!)
 If you have taken this class before, you are required to <u>delete</u> all lab exercises and programming assignment code from your previous attempt.

See also the <u>class collaboration policy</u>.

- **2.** You will need a full-powered laptop or desktop computer to work on See the <u>BCOE laptop policy</u> for minimum laptop requirements.
- **3. Read** "Intro to Assembly Language" (review of material covered in your first lecture). You MUST read this BEFORE lab.

In general, for all future labs, you must read the lab specs before attending lab, and make a start coding at least the first exercise before lab: this is even more important now that labs are virtual!

3 Lab 1

3.0 Getting set up

First, you need to download and install the LC3Tool v2.0.1 on your local machine. Follow <u>this</u> link and download the installer according to your operating system; <u>LC3Tools-2.0.1.Applmage</u> for linux, <u>LC3Tools-2.0.1.dmg</u> for mac and <u>LC3Tools-Setup-2.0.1.exe</u> for windows and install the application.

**Alternative: Working on the remote sledge server

If you experience problems with your own machine, you can use the sledge server to edit and run your code. Although because of possible connection issues, we highly recommend for you to try installing the LC3Tool on your own machine first. You can skip to 3.1 if you already successfully installed the LC3Tool.

If you do not have a cs account yet, notify the TA immediately!

You will use X2Go, a package which provides remote connection to a server.

Download the appropriate X2Go client for your OS, following the instructions <u>here</u> (you must be logged into R'Mail to access this site).

Open the X2Go app, select Session->New Session.

In the New Session window, set:

Session name: to whatever you want (e.g. "sledge", or your name, or whatever)

Host: sledge.cs.ucr.edu

<u>Login</u>: your **NetID** (i.e. your UCR username, the name part of your @ucr.edu email address)

Session type: select XFCE from the drop-down list

Leave default values for all other settings.

When you click OK, this will create a session icon.

You will only need to do this part once.

Click the session icon to launch the connection: you will be asked to provide your cs account password.

When you are done with a remote session, do **NOT** end it by closing the X2Go window - your session will remain open & active on the server, chewing up resources and making the sysAdmin cry:(

ALWAYS end your session by *logging out* - click the little green running man icon at the bottom right of the screen.

3.1 Basic skeleton for LC-3 programs

Similar to C++, every LC-3 program has a certain amount of overhead necessary for making everything work properly.

In **C++**, you might have something like the following:

```
//
// File: main.cpp
// Description: A simple hello world-esque program
// Author: Noobie Q. Programmer
// Date created: 1/1/2019
// Date last modified: 1/1/2019
//
#include <iostream>
using namespace std;
int main()
{
   cout << "Wow, this is the most fun I've had in years!" << endl;
}</pre>
```

This source code is passed to a *compiler*, which ultimately produces a machine language *executable*.

In LC3, a basic program will have the following look:

```
; Author: Noobie Q. Programmer
; UCR NetID/CS username: nprog001
; Lab Section: xxx
; TA: Sean Foley
; Lab 1
; Date created: 1/1/2020
                            ; **ALL** your programs will start at x3000
.orig x3000
; Instructions (i.e. LC-3 code)
HALT
                            ; end of program code
; Local Data
                            ; pseudo-ops for hard-coding data go here
                            ; .end is like the "}" after main() in C++.
.end
                            ; It means "no more code or data"
```

If you haven't figured it out by now, LC-3 comments are denoted by semi-colons. They can be on a line by themselves or on the same line as actual code (after the code).

This source code is passed to an <u>assembler</u> - a much simpler beast than a compiler, but like a compiler it produces a machine language executable.

Pseudo-ops (the keywords that start with a '.' like .end - see next section for more details) are like compiler directives, in that they tell the assembler how to set things up.

3.2 Basics of LC-3 programming

An LC-3 program consists of three basic elements: instructions, pseudo-ops, and labels.

<u>Labels</u> are simply "aliases" for memory addresses. These are really, really useful because they relieve the programmer of the responsibility of figuring out which line of code is at which memory address, allowing us to use symbolic names to point to data and instructions.

<u>Pseudo-ops</u> tell the assembler how to set things up before starting to translate the source code into machine language. They are a bit like compiler directives in C++, such as #include.

For example, the pseudo-op .FILL tells the assembler to write a hard-coded value into memory (i.e. RAM, or system memory). For example, the two .FILL pseudo-ops in Table 1 would write the decimal value 6 into memory at x3005 (aka DEC6), and the decimal value 12 into memory at x3006 (aka DEC12) before the program begins execution.

Note that you just need to label the lines - you don't need to know the actual memory addresses corresponding to those labels (that's the assembler's job!).

<u>Table 1: Labels and Pseudo-ops</u>

Memory address	<u>Label</u>	<u>Pseudo-Op</u>	<u>Hard-coded value</u>
x3005	DEC6	.FILL	#6
x3006	DEC12	.FILL	#12

(The '#' before the numbers means decimal, i.e base 10; 'x' means hexadecimal, i.e. base 16).

Now we can refer to these memory locations (and therefore access the data stored there) using the names DEC6 and DEC12.

We will learn about another pseudo-op .STRINGZ in a moment (in section 3.3).

<u>Instructions:</u> There are 15 LC-3 instructions, in three distinct categories (see <u>this tutorial</u> for more):

- Arithmetic / Logic operations (addition, bitwise AND, bitwise NOT)
- Data movement (moving data back & forth between memory and local registers)
- Program control (changing the order of execution of code branches & loops)

The following sections illustrate one or two instructions from each of these categories.

3.2.1 Arithmetic / Logic Operations

These instructions are used for manipulating values and doing calculations - Adding two numbers, bitwise ANDing two words together, or taking the bitwise logical NOT of a word.

The LC-3 has 8 general purpose, 16-bit local registers (analogous to variables in C++), named R0 through R7, that can be used as temporary storage for performing such operations.

The ADD instruction (2's complement integer data type)

This instruction adds two numbers, and writes the result to a register. It comes in two flavors: One in which both operands come from local registers; the other in which the first operand comes from a register, while the second is actually embedded in the instruction itself ("immediate" mode).

In the immediate mode, the embedded value can only be in the range {-16, +15}.

See the ADD tutorial (also on the Canvas Resources page, "LC3 instruction set") for more details

3.2.2 Data movement

Data movement instructions are used when you want to copy a value from a memory location into a local register ("loading"), or copy a value from a register to a memory location ("storing"). You will be doing this a *lot*, since the LC3 can operate only on values in registers, not in memory.

The LD instruction ("Load Direct" - probably the most frequently used instruction!)
This instruction copies the contents of a specified memory location (identified by a label) into a register.
See the LD tutorial

The LEA instruction ("Load Effective Address")

This instruction translates a <u>label</u> – the name you give to a memory location – back into the 16-bit <u>memory address</u> it stands for, and stores that <u>address</u> into the specified register.

There is no actual data movement here – just the decoding of a label.

See the **LEA tutorial**

3.2.3 Program control

These instructions are used in control structures such as BRANCHING, LOOPING, and SUBROUTINE CALLS (a simpler version of function calls in higher-level languages).

By default, a program starts at the first instruction and executes one instruction after another in order until it reaches the end ("sequential execution").

Control instructions allow us to alter the default sequencing in several ways.

The BR instruction ("Conditional Branch") can be used to transfer control to the instruction at a specified label based on a *condition*.

<u>All</u> the control structures you are familiar with from C++ (if; if-else; if-else; for; while; do-while; switch) can be built using this instruction, sometimes in combination with the <u>JMP</u> instruction.

But before we can learn how it works, we have to know about the **Condition Codes**:

Three "flags" (single-bit registers) are set whenever a value is written into any one of the local registers, indicating whether the value being written is Negative, Zero, or Positive. These flags are called the N Z P Condition Codes, and allow us to make decisions based on the last value written to a register - referred to as the last modified register ("LMR").

The decisions are made by the conditional branch instruction BR, which has three possible modifiers: $\{n, z, p\}$.

As you can guess, the n modifier asks whether the N Condition Code is currently set or not (was the value just written negative?); and likewise for the z and p modifiers.

The BR instruction can be modified by any combination of n, z, p. It will cause a branch to the labelled instruction *IF AND ONLY IF* any one of the specified conditions is met.

See the <u>BR tutorial</u>

And now, we can finally get started on the actual lab exercises :)

3.3 Exercise 0: lab1 ex0 (aaargh!! not "hello world" again?!?!)

As always, the very first program we will write will simply output the message "Hello World!" Though simple, it will illustrate several of the points above, plus some things you will fully understand only later on (exactly like when you first encountered cout in C++):

 We will store the string as an array of ASCII characters in memory, starting at an address labelled "message", using the pseudo-op .STRINGZ

This pseudo-op stores a string in memory, one character per memory address, with a zero ("the null character" or '\0') after the last character.

You will recognize this as a "c-string", i.e. a null-terminated character array. So the line: shrug .STRINGZ "whatever"

will write the characters 'w' 'h' 'a' 't' 'e' 'v' 'e' 'r' followed by x0000, to the nine memory locations starting with the labelled address shrug.

- We will use the LEA instruction to translate the label "shrug" into its actual address, which we will store in RO.
- We will invoke an i/o subroutine called PUTS (can also be written as TRAP x22), which uses R0 to locate the string (it knows when to stop because the last value in the char array is '\0').

Now write this program for yourself:

```
; Name: Shirin Shirazi
; Email: shaji007@ucr.edu
; Lab: lab 2
; Lab section: 23
; TA: Shirin
; Hello world example program
; Also illustrates how to use PUTS (aka: Trap x22)
.ORIG x3000
:-----
; Insructions
 LEA RO, MSG_TO_PRINT ; RO <- the location of the label: MSG_TO_PRINT
              ;Prints string defined as MSG_TO_PRINT
 HALT
              ;terminate program
;-----
; Local data
 MSG_TO_PRINT .STRINGZ "Hello world!!!\n" ;store 'H' in an address labelled
                       ;MSG_TO_PRINT and then each
                       ;character ('e','l','l','o','','w',...) in
                       ;it's own (consecutive) memory
                       ;address, followed by #0 at the end
                       ; of the string to mark the end of the
                       ;string
.END
```

- Open LC3Tools and use the open file button, navigate to cs061/labs/lab1 and open your exercise 0 file: lab1_ex0.asm
- 2. Copy in the code from the above image & save the file.
- 3. Hit the Run button on the left side of the emulator window, and observe the words "Hello World!" magically appear in the console window!
- 4. Now if you have successfully generated the assembly code, you can navigate to the simulator using the button on the up right corner to see a simulation of the system memory, registers and the console which shows the state and the i/o from your code.
- 5. Hit the Run button on the left side of the emulator window, and observe the words "Hello World!" magically appear in the console window!

3.4 Exercise 1: lab1_ex1 - A "real" program

Now Hello World is out of the way, we can write a program that actually does some processing: it will multiply a number, which we will store in advance in memory, by six (How hard can that be, right??!?)

We will also take this opportunity to introduce the style you **MUST** use for all your LC-3 programs.

See the image below:

First comes the header, which will always be included in your starter code: obviously, you have to always fill it out with your personal details.

Next, we have the line .orig x3000 (you may use upper or lower case for all LC-3 instructions, as you wish). This indicates where in memory the code will reside. The LC3 assembler requires all programs to be loaded at or above x3000: all your programs <u>must</u> load the "main" routine to x3000 (just try something else and see what happens!! On second thoughts – don't!)

The code itself multiplies 6 by 12.

Since the LC-3 has no multiply instruction (really!!), the operation has to be carried out by adding 12 into an accumulator 6 times.

We could have added 6 into an accumulator 12 times: why would that not be a good idea?

```
; Name: Shirin Shirazi
; Email: shaji007@ucr.edu
; Lab: lab 2
; Lab section: 23
; TA: Shirin
. ______
.orig x3000
 ; Instructions
  LD R2, DEC_0 ;R2 <- #0
LD R3, DEC_12 ;R3 <- #12
LD R4, DEC_6 ;R4 <- #6
 DO_WHILE_LOOP
   ADD R2, R2, R3 ;R2 <- R2 + R3
   ADD R4, R4, #-1 ; R4 <- R4 - #1
   BRp DO_WHILE_LOOP ;if (R4>0): goto DO_WHILE_LOOP
 END_DO_WHILE_LOOP
            ;halt program (like exit() in C++)
 HALT
 DEC_0 .FILL #0 ;put #0 into memory here
 DEC_12 .FILL #12 ;put #12 into memory here
 DEC_6 .FILL #6 ;put #6 into memory here
.end
```

The next three lines load hard-coded values from memory into registers R1, R2, and R3 respectively:

R1 is an "accumulator" - i.e. at the end, it will hold the result - so we have to initialize it to 0;

R2 holds the multiplicand (the number to be multiplied); and

R3 holds the multiplier - we will use it as a loop counter, to keep track of how many times the loop will execute (i.e. we will create a "counter-controlled" loop).

Make sure you understand how the BRp instruction controls the loop - this is the foundation of all Assembly Language control structures!!

TIP:

Actually, copying values from memory to register (and vice versa) is rather inefficient.

Mostly, we can't avoid it - our fixed data has to be stored in memory.

However, there is one special value for which we can do better - 0!

There is a much cleaner way to "zero out" a register than copying a hard coded 0 from memory to register:

AND R1, R1, x0 ; R1 <- (R1) AND x0000

This does what we call a "bitwise AND" of R1 with 0, i.e. it ANDs each of the 16 bits in R1 with the corresponding bit in x0000, and stores the result (x0000) back in R1 - a LOT quicker than reading from memory!

Note how the program data is stored in a block separated from the code, *following* the HALT instruction, which ends code execution - this way, the processor does not attempt to "execute" the data as though it were code!

And note how we use comments to clearly distinguish the two blocks.

Now that you have had a nice lengthy overview of some basic LC-3 instructions and have seen how to use the LC3Tools assembler/emulator, it is time for you to implement the program yourself.

Open file **lab1_ex1.asm** in LC3Tools, type in the code from the image, and save it.

Remember to replace the first LD R1 instruction with the AND instruction, as per the tip above.

This time, instead of hitting Run, step through each line of code using the **Step over** button in the simulator until you reach the HALT instruction. Notice how the value of R1 keeps going up by 12 until it reaches (quess what??) 72

(Now, how did it know to stop at just the right number??)

Finally, congratulate yourself on a job well done:)

3.5 Submission

Do not submit lab 1 - instead, demo your work to your TA before you leave lab.

Your TA will maintain a Google doc where you can signal that you're ready to demo (and another to request assistance).

In later labs, you may occasionally get stuck and not be able to complete all exercises in the 3 hours: in that case, you must still show your TA how far you got, and request permission to complete it after lab. Your TA will usually give you partial credit for what you have done (so long as you have actually been present for the whole time), and allow you to complete & demo the rest later for full credit, so long as

you have worked at it seriously for the full 3 hours.

When you complete the exercises, demo it to any of the instruction team in their office hours **before your next lab**.

Office hours are posted on Canvas, on the "Staff" page.

4 So what do I know now?

You have now mastered the following skills:

- How to write basic LC-3 assembly language code
- What labels are and how to use them
- How to use the .FILL and .STRINGZ pseudo-ops to store program data in memory
- The LD, LEA, BR, HALT (aka Trap x25) instructions
- The PUTS output routine (aka: Trap x22)
- How to create, save, run, and step through an LC-3 program
- And you now know that the LC-3 can't even multiply two integers by itself!

Not bad for the first day:)