

实验四十三、VPN(GRE)的配置

一、 实验目的

- 1. 掌握 GRE (通用路由封装) 的配置
- 2. 隧道接口的作用


二、 应用环境

GRE 主要用与在 Internet 网络上以 IP 封装 IP 或 IPX 报文

三、 实验设备

DCR-1751 两台
 PC 机 两台

四、 实验拓扑



五、 实验要求

配置表

Router-A		Router-B		
F0/0	192.168.0.1/24	F0/0	192.168.2.1/24	
S1/1 (DCE)	192.168.1.1/24	S1/0	192.168.1.2/24	

PCSERVERIP 192.168.0.10/24192.168.2.2/24网关 192.168.0.1192.168.2.1

结果:

在路由器 A 与 B 之间建立 VPN, 保护从 PC 到 SERVER 的数据



六、 实验步骤

第一步: 参照实验三和上表配置接口地址并测试连通性

第二步: 路由器 A 的配置

Router-A#conf

Router-A_config#ip route 192.168.2.0 255.255.255.0 192.168.1.2

! 配置静态路由

Router-A_config#interface Tunnel0

!配置 TUNNEL 接口

Router-A_config#ip address 172.16.1.1 255.255.255.0

!配置 IP 地址

Router-A_config# tunnel source Serial1/1

! 设定物理源接口

Router-A_config# tunnel destination 192.168.1.2

!设定目的地址

Router-A_config# tunnel key 4

! 设定密钥

第三步: 查看配置

Router-A#sh int tunnel 0

! 查看 TUNNEL 接口

Tunnel0 is up, line protocol is up

Hardware is Tunnel

Interface address is 172.16.1.1/24

MTU 1472 bytes, BW 9 kbit, DLY 50000 usec

Encapsulation TUNNEL, loopback not set

Keepalive(period:0/5 s, retry:0/5)

TUNNEL source 192.168.1.1(Serial1/1), destination 192.168.1.2

TUNNEL protocol/transport GRE/IP, key enabled, sequencing disabled

Checksumming of packets disabled, fast tunneling enabled

60 second input rate 0 bits/sec, 0 packets/sec!

60 second output rate 0 bits/sec, 0 packets/sec!

60 packets input, 2760 bytes input, 0 error, 0 discard

60 packets output, 3960 bytes output, 68 discard

第四步: 路由器 B 的配置

Router-B#conf

Router-B_config#ip route 192.168.0.0 255.255.255.0 192.168.1.1

Router-B_config#interface Tunnel0

Router-B_config#ip address 172.16.1.2 255.255.255.0

Router-B_config#tunnel source Serial1/0

Router-B_config# tunnel destination 192.168.1.1

Router-B_config# tunnel key 4

Router-B_config_s1/0#^Z

第五步: 查看配置

Router-B#sh int tunnel 0

Tunnel0 is up, line protocol is up

Hardware is Tunnel

Interface address is 172.16.1.2/24

MTU 1472 bytes, BW 9 kbit, DLY 50000 usec



Encapsulation TUNNEL, loopback not set

Keepalive(period:0/5 s, retry:0/5)


TUNNEL source 192.168.1.2(Serial1/0), destination 192.168.1.1

TUNNEL protocol/transport GRE/IP, key enabled, sequencing disabled

Checksumming of packets disabled, fast tunneling enabled

- 60 second input rate 0 bits/sec, 0 packets/sec!
- 60 second output rate 0 bits/sec, 0 packets/sec!
 - 60 packets input, 2760 bytes input, 0 error, 0 discard
 - 60 packets output, 3960 bytes output, 0 discard

第六步:测试



七、 注意事项和排错

- 1. 注意两端参数要一致
- 2. 静态路由不要忘记配置
- 3. 密钥要一致

八、 配置序列

Router-B#sh run

正在收集配置...

当前配置:

lyangian

!version 1.3.2E

service timestamps log date service timestamps debug date

no service password-encryption



```
!
hostname Router-B
ip host a 192.168.1.1
ip host c 192.168.2.2
interface Tunnel0
 mtu 1472
 ip address 172.16.1.2 255.255.255.0
 no ip directed-broadcast
 tunnel source Serial 1/0
 tunnel destination 192.168.1.1
 tunnel key 4
interface FastEthernet0/0
 ip address 192.168.2.1 255.255.255.0
 no ip directed-broadcast
interface Serial1/0
 ip address 192.168.1.2 255.255.255.0
 no ip directed-broadcast
interface Async0/0
 no ip address
 no ip directed-broadcast
ip route 192.168.0.0 255.255.255.0 Tunnel0
```

九、 共同思考

1. TUNNEL 接口的作用是什么?



2. 静态路由的接口地址为什么是 TUNNEL 接口?

十、 课后练习

请重复以上实验

十一、相关命令详解

interface

使用 interface 全局配置命令配置接口类型和进入接口配置态。使用这个命令的 **no** 形式删除接口或初始化接口。

interface type interface-number

interface type slotlport (用于带有非信道化 E1 的物理接口的路由器)

interface serial slot/port:channel-group (用于配置非信道化 E1 的物理接口)

要配置子接口,使用这个形式的 interface 全局配置命令:

interface serial slot/port.subinterface-number {multipoint | point-to-point}

参数

参数	参数说明
type	指定要配置的接口类型。
interface-number	逻辑接口序号
slot	插槽或插卡编号
port	插槽或插卡端口编号
channel-group	范围为0-30的E1信道组号,使用channel-group配置命令定义
subinterface-number	范围为1-32767的子接口号。
multipoint	指定点对多点或点对点子接口,没有缺省值。创建时必须指定。
point-to-point	

缺省

无接口被缺省配置。

命令模式

全局配置态

使用说明

子接口可以用于配置支持非全连通的帧中继网络。



表 0-1 接口类型关键字和描述对照表

关键字	接口类型
async	异步接口
bm	DTU接口
bri	ISDN基本速率接口 (BRI)
dialer	拨号接口
ethernet	以太网接口
fastethernet	快速以太网接口
loopback	仅软件实现的回环接口,模拟总是开启的接口。 interface-number是想创建或配置的回环接口序号。
null	空接口
serial	串行接口
Multilink	Multilink接口
Virtual-template	Virtual-template接口
Tunnel	Tunnel接口

对于物理接口和子接口,使用 no interface 命令恢复接口的缺省配置。对于其它接口,使用 no interface 命令删除。

示例

下面的例子使用 PPP 封装配置串行接口 1/0:

interface serial 1/0

encapsulation ppp

下面的例子配置回环接口,并给接口分配一个 IP 网络地址和网络掩码。

interface loopback 0

ip address 192.168.1.1 255.255.255.0

下面的例子表明如何配置子接口。在这个例子中,子串行接口 1/0.1 配置为有 3 个关联帧中继 PVC 的点对多点子接口,子串行接口 1/0.2 配置为点对点子接口。

interface serial 1/0

encapsulation framerelay

interface serial 1/0.1 multipoint

ip address 192.168.1.1 255.255.255.0

map 192.168.1.2 pvc 22 broadcast

map 192.168.1.3 pvc 23 broadcast

interface serial 1/0.2 point-to-point

encapsulation ppp



ip address 192.168.2.1 255.255.255.0
map 192.168.2.2 pvc 102 broadcast
下面的例子配置 E1 链路的信道组 3 封装 PPP 协议:
controller E11 2/3
channel-group 3 timeslots 0-3
interface serial 2/3:3
ip address 192.168.3.1 255.255.255.0

