

# 实验四十一、DHCP配置

### 一、 实验目的

- 1. 掌握 DHCP SERVER 的配置
- 2. 掌握 DHCP CLIENT 的配置
- 3. 掌握 DHCP RELAY 的配置


## 二、应用环境

- 1. 在实际应用环境中需要为 DHCP 做中继以便让客户机获得 IP 地址
- 2. 也可以将路由器作为 DHCP 的服务器或者客户机

### 三、 实验设备

DCR-1751 两台
 PC 机 一台
 网线(交叉线) 两条

## 四、 实验拓扑



## 五、 实验要求

ROUTER-B ROUTER-C PC机

F0/0 192.168.2.1 E1/0 192.168.3.1 动态获得 IP 地址

### 六、 实验步骤

第一步:按照实验三和上表配置接口 IP 地址

第二步: DHCP 服务器的配置

Router-B#conf

Router-B\_config#ip dhcpd pool 1

! 定义地址池



Router-B\_config\_dhcp#network 192.168.2.0 255.255.255.0

Router-B config dhcp#range 192.168.2.10 192.168.2.20

Router-B\_config\_dhcp#lease 1

Router-B\_config\_dhcp#exit

Router-B\_config#ip dhcpd enable

! 定义网络号

! 定义地址范围 ! 定义租约为1天

! 启动 DHCP 服务

#### 第三步: 验证

#### Router-B#sh ip dhcp pool

**DHCP Server Address Pool Information:** 

#### Pool 1:

Network: 192.168.2.0

Range: 192.168.2.10 - 192.168.2.20

Total address: 11 Leased address: 1 Abandoned address: 0 Available address: 10

#### 第四步: DHCP 客户机的配置

Router-C#conf

Router-C\_config#int f0/0

Router-C\_config\_f0/0#ip address dhcp

Router-C\_config\_f0/0#^Z

### ! 配置 DHCP 客户端

#### 第五步:验证获得地址

#### Router-C#show interface f0/0

FastEthernet0/0 is up, line protocol is up address is 00e0.0f20.0368

#### Interface address is 192.168.2.10/24

! 获得了地址

MTU 1500 bytes, BW 100000 kbit, DLY 10 usec

Encapsulation ARPA, loopback not set

Keepalive not set

ARP type: ARPA, ARP timeout 04:00:00

60 second input rate 117 bits/sec, 0 packets/sec!

60 second output rate 116 bits/sec, 0 packets/sec!

Full-duplex, 100Mb/s, 100BaseTX, 1804 Interrupt

1729 packets input, 120998 bytes, 200 rx\_freebuf

Received 102 unicasts, 0 lowmark, 1729 ri, 0 throttles

0 input errors, 0 CRC, 0 framing, 0 overrun, 0 long

75 packets output, 5213 bytes, 50 tx\_freebd, 0 underruns

0 output errors, 0 collisions, 0 interface resets

0 babbles, 0 late collisions, 0 deferred, 0 err600

0 lost carrier, 0 no carrier 0 grace stop 0 bus error

0 output buffer failures, 0 output buffers swapped out



Router-B#show ip dhcp binding

! 在服务器上看到被分配的地址

IP Address

Hardware Address

Type Lease Expired

192.168.2.10

00.e0.0f.20.03.68

automatic Fri Jan 2 00:21:02 2004

#### DHCP 中继的配置

第六步: 在服务器上新建地址池

Router-B\_config#ip dhcpd pool 2

! 建立地址池

 $Router-B\_config\_dhcp \# network~192.168.3.0~255.255.255.0$ 

! 设定网络号

Router-B\_config\_dhcp#range 192.168.3.10 192.168.3.20

! 设定地址范围!配置分配给客户机的网关

Router-B\_config\_dhcp#default-router 192.168.3.1 Router-B\_config\_dhcp#dns-server 1.1.1.1

! 配置分配给客户机的 DNS 服务器地址

Router-B\_config\_dhcp#lease 1

! 设定租约为1天

Router-B\_config\_dhcp#^Z

第七步: 在路由器 C 上配置 DHCP 中继

Router-C\_config\_f0/0#int e1/0

! 进入收到 DHCP 客户机请求的接口

Router-C\_config\_e1/0#ip address 192.168.3.1 255.255.255.0

!配置 IP 地址

Router-C config e1/0#ip helper-address 192.168.2.1

! 设定中继的 DHCP 服务器地址

Router-C\_config\_e1/0#exit

Router-C\_config#ip dhcpd enable


! 启动服务

Router-C\_config#

DHCP Service is now starting. Please wait...

**DHCP Service started successfully.** 

第八步: 配置 PC 机及验证获得地址



运行-->cmd-->ipconfig/all



```
C:\VINDOVS\system32\cmd.exe
                                                                            _ 🗆 ×
Microsoft Windows XP [版本 5.1.266]
(C) 版权所有 1985-2001 Microsoft Corp.
C:\Documents and Settings\孙斌>ipconfig/all
Windows IP Configuration
       nost Name . . . . . . . : sunbin1
Primary Dns Suffix . . . . . :
Node Tune
       Node Type . . . . . . . . : Unknown IP Routing Enabled. . . . . : No
       WINS Proxy Enabled. . . . . . : No
Ethernet adapter 本地连接:
       Connection-specific DNS Suffix .:
Description . . . . . . . . . . . . . . . . Realtek RTL8139 Family PCI Fast Ethe
rnet NIC
       Physical Address. . . . . . . : 00-02-3F-73-52-E0
       Dhcp Enabled. . . . . . . . : Yes
Autoconfiguration Enabled . . . : Yes
       Default Gateway . . . . . . . : 192.168.3.1
```

## 七、 注意事项和排错

- 1. DHCP-RELAY 的实验一定要新建相应的地址池
- 2. 路由器与 PC 连接要使用交叉线

## 八、 配置序列

```
Router-B#sh run
Building configuration...

Current configuration:
!
!version 1.3.2E
service timestamps log date
service timestamps debug date
no service password-encryption
!
hostname Router-B
!
ip host c 192.168.2.2
ip host a 192.168.1.1
!
!
!
```



```
interface FastEthernet0/0
ip address 192.168.2.1 255.255.255.0
no ip directed-broadcast
!
interface Serial1/0
no ip address
no ip directed-broadcast
!
interface Async0/0
no ip address
no ip directed-broadcast
!
!
ip dhcpd pool 2
network 192.168.3.0 255.255.255.0
range 192.168.3.10 192.168.3.20
default-router 192.168.3.1
dns-server 1.1.1.1
!
ip dhcpd enable
!
!
```

## 九、 共同思考

- 1. DHCP 的作用是什么?
- 2. 租约的设定有什么作用?

## 十、 课后练习

将地址池修改成 10.0.0.0/24 重复以上实验

## 十一、相关命令详解

## ip dhcpd pool

### 参数

参数	参数说明
name	DHCP地址池的名称。



缺省

无

命令模式

全局配置态

使用说明

用户可以使用如下命令来增加名为 name 的 DHCP 地址池,并进入 DHCP 地址池配置模式 ip dhcpd pool name

示例

以下命令增加名为 test 的 DHCP 地址池,同时进入 DHCP 地址池配置模式。 ip dhcpd pool test

## ip dhcpd enable

参数

无

缺省

缺省情况下,关闭 DHCP 服务

命令模式

全局配置态

使用说明

用户可以使用如下命令来打开 DHCP 服务。 此时,DHCP 服务器也支持 relay 操作,对于自身不能分配的地址请求,配置了 ip helper-address 的端口将转发 DHCP 请求。 ip dhcpd pool name

示例

以下命令打开 DHCP 服务。 ip dhcpd enable