Algorithms and Data Structures

Encoding Machine numbers for \mathbb{R}



Learning goals

- IEEE 745
- Types in C
- Floating point numbers in R
- Distance



REALS ON A MACHINE

- \bullet Floating point numbers on a machine don't correspond to $\mathbb R$ in a mathematical sense. They are merely an approximation.
- Because there is only a finite number of machine numbers, there are no arbitrarily small or large numbers and also no arbitrarily close numbers.
- A finite subset of the real numbers cannot be closed w.r.t. rational operations (+,-,*,:)

We would like to have:

- ullet Operations as similar as possible to those in \mathbb{R} ,
- fast and easy implementation on digital computers.



MACHINE NUMBERS FOR $\mathbb R$: IEEE 754

IEEE (Institute of Electrical and Electronics Engineers) 754 defines standard representations for floating point numbers in computers.

Characterized by:

- Sign bit $S \in \{-1, +1\}$
- Base *b* >1, common are 2, 8, 10 and 16 (usually 2)
- Mantissa of length m, the significant bits / digits
- Smallest and largest exponent $e_{min} < 0$ and $e_{max} > 0$
- Mantissa, exponent and S are coded as bits u_i

Representation:

$$x = S \cdot b^e \cdot (1 + \sum_{i=1}^m u_i b^{-i})$$


Thus: a sign bit, an exponent and the significant digits (binary coded with mantissa bits u_i , i = 1, ..., m).



IEEE 754

Single precision, 32 bit:

- b = 2; u_{32} : sign bit
- e is 8 bits $u_{24}, ..., u_{31}$ (excess coding with bias 127)
- m = 23, the first 23 bits are used for the mantissa.



Source: https://en.wikipedia.org/wiki/Single-precision_floating-point_format

Converter: https://www.h-schmidt.net/FloatConverter/IEEE754.html

Example:

- sign bit $u_{32} = 0 \Rightarrow S = +1$
- $e = \sum_{i=1}^{8} u_{i+23} 2^{i-1} 127 = 2^2 + 2^3 + 2^4 + 2^5 + 2^6 127 = -3$
- mantissa bits: $u_2 = 1$, $u_1 = u_3 = ... = u_{23} = 0$

$$\Rightarrow x = S \cdot b^e \cdot (1 + \sum_{i=1}^{23} u_i b^{-i}) = 1 \cdot 2^{-3} \cdot (1 + 2^{-2}) = 0.15625$$



Double precision, 64 bit:

- b = 2; u_{64} : sign bit
- e is 11 bits $u_{53}, ..., u_{63}$ (excess coding with bias 1023)
- m = 52



In addition to single and double precision, IEEE 754 also has single extended and double extended. Here only a minimum number of bits is required - the exact number of bits is the implementor's choice.



Normalized Number:

To guarantee a unique representation, most systems require that the first bit of the mantissa is $\neq 0$. In case of b = 2, the first bit of the mantissa does not need to be stored in a normalized representation. Hence, one gains one extra bit of precision (hidden bit).



A number is considered normalized if at least one exponent bit is 1.

$$x = S \cdot b^{e} \cdot (1 + \sum_{i=1}^{m} u_{i}b^{-i})$$

Special cases:

- 0: If all mantissa bits and all exponent bits are 0, then $x=\pm 0$.
- ∞ : If all mantissa bits are 0 and all exponent bits are 1, then $x=\pm\infty$. This results from the division by 0, or if the result is too large or too small.
- NaN: If all exponent bits are 1 and at least one mantissa bit is 1, then x = NaN ("Not a Number"). E.g.: 0/0 or $\infty \infty$.

If all exponent bits are 0, a **denormalized** number is stored. The mantissa before the "decimal" point is then 0. In this case:

$$x = S \cdot b^{e_{\min}} \cdot \left(\sum_{i=1}^{m} u_i b^{-i} \right)$$

This allows very small numbers close to 0.



Binary representation of smallest and largest numbers (IEEE 754, single precision, 32 bit):

| | Sign Bit | Exponent bits | Mantissa bits |
|--------------------------------|----------|---------------|---|
| Smallest number (normalized) | 0 | 00000001 | 000000000000000000000000000000000000000 |
| Smallest number (denormalized) | 0 | 00000000 | 000000000000000000000000000001 |
| Largest number | 0 | 11111110 | 1111111111111111111111111111 |



The corresponding values in the decimal system:

| | exact value | scient. notation |
|--------------------------------|--|---------------------------|
| Smallest number (normalized) | 2^{-126} | $1.175494 \cdot 10^{-38}$ |
| Smallest number (denormalized) | $2^{-126} \cdot 2^{-23}$ | $1.401298 \cdot 10^{-45}$ |
| Largest number | $2^{127} \cdot (1 + \sum_{i=1}^{23} 2^{-i})$ | $3.4028235 \cdot 10^{38}$ |

TYPES IN C (PROGRAMMING LANGUAGE)

Most programming languages provide several fixed-point and floating point representations. C has:

Fixed: signed short int, unsigned short int, signed long int, ...

Float: float, double, long double

The compiler translates them for the CPU. Standard PCs (usually) have hardware support for floating-point arithmetic in single and double accuracy. CPUs of different architecture (with the same nominal clock rate) can strongly differ in computing power.



FLOATING POINT NUMBERS IN R

- By default, R displays 6 decimal places. This can be adjusted using the command options(digits = m).
- Internally, R calculates all floating point operations in double precision (IEEE 754, double precision, 64 bit).
- .Machine contains all information about the encoding



FLOATING POINT NUMBERS IN R / 2

.Machine\$double.base # base ## [1] 2 .Machine\$double.digits # number of mantissa bits ## [1] 53 .Machine\$double.exponent # number of exponent bits ## [1] 11 .Machine\$double.xmin # smallest float ## [1] 2.225074e-308 .Machine\$double.xmax # largest float



[1] 1.797693e+308

FLOATING POINT NUMBERS IN R / 3

```
0.1 + 0.2 == 0.3
## [1] FALSE
```

 sprintf (wrapper for the corresponding C function) outputs a formatted string. Both numbers cannot be represented exactly (hence, also not their sum):

```
sprintf("%.20f", 0.1)  # decimal notation (20 digits)
## [1] "0.1000000000000000555"

sprintf("%.20f", 0.2)
## [1] "0.20000000000000001110"

sprintf("%.20f", 0.1 + 0.2)
## [1] "0.300000000000000004441"
```

 This problem can be avoided by using the comparison with tolerance all.equal instead of the exact comparison ==.


```
all.equal(0.1 + 0.2, 0.3)
## [1] TRUE
```



DISTANCE

The machine floats \mathcal{M} are **not uniformly distributed** in the domain. The interval $[b^{i-1}, b^i]$ contains the same quantity of numbers as the interval $[b^i, b^{i+1}]$, even though the latter is b times as big.





DISTANCE / 2

The distance between the representable numbers is important:

- The smallest numbers around 0 are $\pm b^{e_{\min}-m}$.
- The smallest number greater than 1 is $1 + b^{-m}$ $(e = 0, u_0 = \ldots = u_{m-1} = 0 \text{ and } u_m = 1).$
- The largest real number less than 1 is $1 b^{-m-1}$ $(e = -1, u_0 = 0 \text{ and } u_1 = \dots = u_m = 1).$
- This results in important constants called "machine epsilons":

$$\epsilon_{\min} = b^{-m-1}$$
 $\epsilon_{\max} = b^{-m}$


• For numbers greater than b^{m+1} , the distance between numbers is > 1 and even integer parts are no longer exact.



DISTANCE / 3

Machine epsilons can be used to estimate the distance between the numbers in the entire domain.

In general: Around a number $x \neq 0$, the **relative distance** between machine numbers is approximately ϵ_{max} , and the **absolute distance** is thus $x \cdot \epsilon_{\text{max}}$ (approximately, since neither x nor the product with ϵ_{max} need to be representable).



From now on, we define $\epsilon_m := \epsilon_{\mathsf{max}}$.

This machine epsilon is our minimal accuracy.



DISTANCE / 4

```
options(digits = 20)
1 + 1 / (2^53)
## [1] 1
1 + 1 / (2^52)
1 / (2<sup>52</sup>)
## [1] 2.2204460492503131e-16
```

.Machine\$double.eps ## [1] 2.2204460492503131e-16

