CONL

Database Systems

705

5.1.6: Modifying Tables - Examples

ALTER TABLE

Using ALTER TABLE

Additional Attributes/Columns can be added (ADD)

Existing attributes

- Can be modified (change data type and/or size) (MODIFY)
- Can be deleted (DROP)
- Can be renamed (RENAME)

Constraints

- Can be added and deleted (ADD, DROP)
- Can be disabled and enabled (DISABLE, ENABLE)
- Can be renamed (RENAME)

Syntax

ALTER TABLE TableName

[ADD [COLUMN] columnName dataType [NOT NULL] [UNIQUE] [DEFAULT defaultOption] [CHECK (searchCondition)]]

[DROP [COLUMN] columnName [RESTRICT | CASCADE]]

[ADD [CONSTRAINT [ConstraintName]] tableConstraintDefinition]

[DROP CONSTRAINT ConstraintName [RESTRICT | CASCADE]]

[ALTER [COLUMN] SET DEFAULT defaultOption]

[ALTER [COLUMN] DROP DEFAULT]

ADD COLUMN

The Author table has three columns.

DESC AUTHOR;

Name	Null	Туре
AUTHOR_NUM	NOT NULL	NUMBER(4)
AUTHOR_LAST		VARCHAR2(12
AUTHOR_FIRST		VARCHAR2(10

 Add a column to store Telephone number of the Author.

ALTER TABLE AUTHOR ADD TEL NUMBER(12);

DESC AUTHOR;

Name	Null	Туре
AUTHOR_NUM	NOT NULL	NUMBER(4)
AUTHOR_LAST		VARCHAR2(12)
AUTHOR_FIRST		VARCHAR2(10)
TEL		NUMBER(12)

MODIFY COLUMN

 Telephone number being Numeric can't take initial 0, change the data type the CHAR.

ALTER TABLE AUTHOR

MODIFY TEL CHAR(12);

DESC AUTHOR;

TEL		CHAR(12)
AUTHOR_FIRST		VARCHAR2(10)
AUTHOR_LAST		VARCHAR2(12)
AUTHOR_NUM	NOT NULL	NUMBER(4)
Name	Null	Туре

Rename the column Tel to Tel_Num.

ALTER TABLE AUTHOR

RENAME COLUMN TEL **TO** TEL_NUM;

DESC AUTHOR;

Name	Null	Type
AUTHOR_NUM	NOT NULL	NUMBER(4)
AUTHOR_LAST		VARCHAR2(12)
AUTHOR_FIRST		VARCHAR2(10)
TEL_NUM	CHAR(12)	

DROP COLUMN

DESC AUTHOR;

Name	Null	Туре
AUTHOR_NUM	NOT NULL	NUMBER(4)
AUTHOR_LAST		VARCHAR2(12)
AUTHOR_FIRST		VARCHAR2(10)
TEL_NUM		CHAR(12)

 Column can be dropped using DROP

ALTER TABLE AUTHOR **DROP** (TEL_NUM);

•DESC AUTHOR;

Name	Null	Туре
AUTHOR_NUM	NOT NULL	NUMBER(4)
AUTHOR_LAST		VARCHAR2(12)
AUTHOR_FIRST		VARCHAR2(10)

DROP Multiple Columns

Deleting Multiple Columns (GRADE table).

DESC GRADE;

Name	Null	Туре
STUDENT_ID	NOT NULL	NUMBER(8)
SECTION_ID	NOT NULL	NUMBER(8)
GRADE_TYPE_CODE	NOT NULL	CHAR(2)
GRADE_CODE_OCCURRENCE	NOT NULL	NUMBER (38)
NUMERIC_GRADE	NOT NULL	NUMBER(3)
COMMENTS		VARCHAR2(2000)
CREATED_BY	NOT NULL	VARCHAR2(30)
CREATED_DATE	NOT NULL	DATE
MODIFIED_BY	NOT NULL	VARCHAR2(30)
MODIFIED_DATE	NOT NULL	DATE

ALTER TABLE GRADE

DROP (MODIFIED_BY, MODIFIED_DATE);

DESC GRADE;

Name		Null	Туре
STUDENT_ID		NOT NULL	NUMBER(8)
SECTION_ID		NOT NULL	NUMBER(8)
GRADE_TYPE_CODE		NOT NULL	CHAR(2)
GRADE_CODE_OCCURRE	NCE	NOT NULL	NUMBER (38)
NUMERIC_GRADE		NOT NULL	NUMBER(3)
COMMENTS			VARCHAR2(2000)
CREATED_BY		NOT NULL	VARCHAR2(30)
CREATED_DATE		NOT NULL	DATE

Modify Constraints

Create DEPARTMENT table DPNT

CREATE TABLE DPNT

(DEPTNO NUMBER(2),

DNAME VARCHAR2(20),

LOC VARCHAR2 (25));

Create EMPLOYEE table EMPL

CREATE TABLE EMPL

(EMPNO NUMBER(4),

JOB VARCHAR2(20),

MGR NUMBER(4),

HIREDATE DATE,

SAL NUMBER (7,2),

COMM NUMBER (7, 2),

DEPTNO NUMBER(2));

ADD Constraints

Add Primary Key

```
ALTER TABLE EMPL ADD PRIMARY KEY (EMPNO);
```

Add Validation Rule (CHECK constraint)

```
ALTER TABLE EMPL ADD CHECK (SAL <5000.99);
```

Add Foreign Key

```
ALTER TABLE EMPL ADD FOREIGN KEY (DEPTNO) REFERENCES DPNT(DEPTNO);
```

Check the result - Frror ?

Modifying Constraints

Adding Constraints

ALTER TABLE EMPL ADD FOREIGN KEY (DEPTNO) REFERENCES DPNT(DEPTNO);

Error report -

ORA-02270: no matching unique or primary key for this column-list

02270. 00000 - "no matching unique or primary key for this column-list"

*Cause: A REFERENCES clause in a CREATE/ALTER TABLE statement gives a column-list for which there is no matching unique or primary key constraint in the referenced table.

*Action: Find the correct column names using the ALL_CONS_COLUMNS catalog view

- Modify the DPNT table
 - Add Primary Key

ALTER TABLE DPNT

ADD PRIMARY KEY (DEPT_NO);

Result: Table DPNT altered.

Modify EMPNL add foreign key

ALTER TABLE EMPL

ADD FOREIGN KEY (DEPTNO) REFERENCES DPNT(DEPTNO);

Result: Table EMPL altered.

Modifying Constraints

 Disabling constraints – disable CHECK constraint on EMPL (remember to find the appropriate constraint name)

```
ALTER TABLE EMPL

DISABLE CONSTRAINT SYS_C0022166; /*please find the appropriate constraint name from your table*/
```

Enable constraints

```
ALTER TABLE EMPL

ENABLE CONSTRAINT SYS_C0022166; /*same name as above*/
```

Rename constraints

```
ALTER TABLE EMPL

RENAME CONSTRAINT SYS_C0022166 TO EMPL_CHECK_SAL; /*rename the from the name above to EMPL_CHECK_SAL*/
```

Delete Constraint

```
ALTER TABLE EMPL

DROP CONSTRAINT EMPL_CHECK_SAL;
```

DROP CASCADE

 Column that has references cannot be dropped using simple DROP.

ALTER TABLE DPNT DROP (DEPTNO);

Error report -

ORA-12992: cannot drop parent key column 12992. 00000 - "cannot drop parent key column"

*Cause: An attempt was made to drop a parent key column.

*Action: Drop all constraints referencing the parent key column, or specify CASCADE CONSTRAINTS in statement.

Column can be dropped using DROP with CASCADE

ALTER TABLE DPNT

DROP (DEPTNO) CASCADE CONSTRAINTS;

DESC DPNT;

Name	Nulls	Туре
DNAME		VARCHAR2(20)
LOC		VARCHAR2(25)

- Please note its not the primary key constraint prevented the DROP, it's the foreign key constraint defined in the EMPL table.
- Columns can be dropped even if it's a primary key, however if it
 is referenced from any other objects you must use CASCADE.

Deleting Tables - DROP

- Can correct errors by dropping (deleting) a table and starting over
- Useful when table is created before errors are discovered
- Command is followed by the table to be dropped and a semicolon
- Any data in table also deleted

DROP Table to correct mistakes

 DPNT was created with no Primary key

DROP TABLE DPNT; /*only works if you completed the previous steps, especially dropping the DEPNO*/

Create DPNT Table

CREATE TABLE DPNT

(DEPTNO NUMBER(2) PRIMARY KEY,

DNAME VARCHAR2(20),

LOC VARCHAR2 (25));

Drop the table EMPL DROP TABLE EMPL;

);

Create the table EMPL

CREATE TABLE EMPL

(EMPNO NUMBER(4) PRIMARY KEY,

JOB VARCHAR2(20),

MGR NUMBER(4),

HIREDATE DATE,

SAL NUMBER(7,2),

COMM NUMBER (7, 2),

DEPTNO NUMBER(2) REFERENCES DPNT (DEPTNO)

Deleting Tables - DROP

 Generally to delete a table use DROP TABLE followed by the table the table name.

DROP TABLE DPNT;

- Even though the same statement worked in the previous slide, here it will be an error as DPNT is a parent table.
- If the table is a Parent Table
 - All the Child tables must be deleted (dropped) before the Parent table
 - Or use

DROP TABLE DPNT CASCADE CONSTRAINTS;

/*Result: Table DPNT dropped. */