ECE 350
Real-time
Operating
Systems



Lecture 3: Multithreaded Kernels


Prof. Seyed Majid Zahedi

https://ece.uwaterloo.ca/~smzahedi

Outline


- Thread implementation
 - Create, yield, switch, etc.
- Kernel- vs. user-managed threads
- Implementation of synchronization objects
 - Mutex, semaphore, condition variable

Kernel-managed Multithreading




User-Level Processes

- System library allocates user-space stack for each user-level thread
- System library then uses system calls to create, join, yield, exit threads
- Kernel handles scheduling and context switching using kernel-space stacks



Recall: Thread Lifecycle



A process can go directly from ready or waiting to finished (example: main thread calls exit)

What Triggers a Context Switch?

- Synchronous event: thread invokes a system call or an exceptions happens
 - E.g., yield, join, write, read, or segmentation fault, divide by zero, etc.
 - This is called a voluntary context switch

```
void compute_PI() {
    while(TRUE) {
        compute_next_digit();
        thread_yield();
    }
}
```

- Asynchronous event: interrupts happens
 - E.g., timer interrupt, new packet arrives, a DMA request finishes
 - This is called an involuntary context switch

System Call, Interrupt, and Exception Handlers

```
handler() {
    // this runs in kernel mode
    // SP points to a kernel stack
    Push regs that might be used by handler on kernel stack
    // (handle the event)
Handler_Exit
    Pop regs that were pushed
    Return
```



Switch Between Threads

```
// We enter as oldTCB, but we return as newTCB
// Returns with newTCB's registers and stack
thread_switch(TCB *oldTCB, TCB *newTCB) {
    Push all regs onto kernel stack of oldTCB
    Set oldTCB->sp to stack pointer
    Set stack point to newTCB->sp
    Pop regs from kernel stack of newTCB
    Return
```

newTCP could be a thread that was context switched before and we are context switching back to it, or it could be a **newly created** thread

Where does this return to?

If newTCB is not newly created, then we return to kernel code that called thread_switch (return address is stored on newTCB's stack)

If **newTCB** is newly created, then it should have an **entry point** address on its stack

What is popped here?

If **newTCB** is not newly created, then we pop what we pushed last time we context switched it

If **newTCB** is newly created, then it should have dummy data frame on top of its stack

Threads Entry Point

- For kernel threads, no mode switch is required
 - Could directly jump to function that thread will run

- For user threads, switch from kernel to user mode is required
 - Need one level of indirection
 - Could jump to a kernel code that then jumps to user code and changes mode atomically
 - E.g., could jump to **Handler_Exit**

Creating New User Threads

```
thread create(void *(*func)(void*), void *args) {
     // Allocate TCB
     TCB *tcb = new TCB()
     // Allocate kernel stack (note that stack grows downwards)
     tcb->sp = new Stack(stack size) + stack size;
     // Set up kernel stack
     // (1) Push func and args
     *(--tcb->sp) = args;
     *(--tcb->sp) = func;
     // (2) push data for Handle_Exit
     push dummy handler frame(&tcb->sp);
     *(--tcb->sp) = Handler Exit
     // (3) Push dummy data for thread_switch
     push dummy switch frame(&tcb->sp);
     // Set state of thread to read
     tcb->state = READY;
     // Put tcb on ready list
     readyList.add(tcb);
```

Stack for Yielding Thread

```
void run_new_thread() {
                                                                compute_PI
    // Prevent interrupt from stopping us
                                                                                    Thread
                                                                                                 Stack's growth
    // in the middle of switch
                                                                                     Stack
                                                               thread_yield
   disable interrupts();
                                                   Trap to OS
    // Choose another TCB from ready list
    chosenTCB = scheduler.getNextTCB();
   if (chosenTCB != runningTCB) {
        // Move running thread onto ready list
                                                              kernel_yield
         runningTCB->state = READY;
                                                                                     Kernel
         ready list.add(runningTCB);
                                                              run new thread
                                                                                     Stack
        // Switch to the new thread
        thread switch(runningTCB, chosenTCB);
                                                              thread switch
        // We're running again!
         runningTCB->state = RUNNING;
         // Do any cleanup
        do cleanup housekeeping();
                                              Start from here whenever another
                                              thread switches back to this thread
    // Enable interrupts again
    enable_interrupts();
```

How Do Stacks Look Like?

• Two threads run following code

```
A() {
    B();
}

B() {
    while(TRUE) {
        thread_yield();
    }
}
```

Thread I

A
B (while)
thread_yield

Thread 2

A
B (while)
thread_yield

kernel_yield

run_new_thread

thread_switch

kernel_yield

run_new_thread

thread_switch




Outline

- Thread implementation
 - Create, yield, switch, etc.
- Kernel- vs. user-managed threads
- Implementation of synchronization objects
 - Mutex, semaphore, condition variable

Some Numbers

 Many process are multi-threaded, so thread context switches may be either within-process or across-processes




Some Numbers (cont.)

- Frequency of performing context switches is ~10-100ms
- Context switch time in Linux is \sim 3-4 us (Intel i7 & Xeon E5)
 - Thread switching faster than process switching (~100 ns)
- Switching across cores is ~2x more expensive than within-core
- Context switch time increases sharply with size of working set*
 - Can increase ~100x or more
- Moral: overhead of context switching depends mostly on cache limits and process or thread's hunger for memory


^{*}Working set is subset of memory used by process in time window

Kernel- vs. User-managed Threads




- We have been talking about kernel-managed threads
- Each user thread maps to one TCB (1:1 mapping)
- Every thread can run or block independently
- This approach is relatively expensive
 - Need to make crossing into kernel mode to schedule

User-managed Threads



- Alternative is for user-level library to do all thread management tasks
- User process creates threads, maintains their state, and schedules them
- Kernel is not aware of existence of multiple threads
- Kernel only allocates single TCB to user process (N:1 mapping)
- Examples: Solaris Green Threads, GNU Portable Threads

User-managed Threads: Thread vs. Process State



Running

Downside of User-managed Threads

- Multiple threads may not run in parallel on multicore
- When one thread blocks on I/O, all threads block
- Alternative: scheduler activations
 - Notify user-level scheduler of relevant kernel events

Classification of OSes

- Most operating systems have either
 - One or many address spaces
 - One or many threads per address space

# threads # of addr spaces:	One	Many
One	MS/DOS, early Macintosh	Traditional UNIX
Many	Embedded systems (Geoworks,VxWorks, JavaOS, Pilot(PC), etc.)	Mach, OS/2, Linux, Windows 10, Win NT to XP, Solaris, HP-UX, OS X

Outline

- Thread implementation
 - Create, yield, switch, etc.
- Kernel- vs. user-managed threads
- Implementation of synchronization objects
 - Mutex, semaphore, condition variable

Implementing Synchronization Objects

Programs	Bounded Buffers	
Synch Objects	Mutex Semaphore Monitor	
Atomic Inst	Load/Store Disable Interrupts Test&Set	

Atomic Memory Operations

- In most architectures, load and store operations on single byte are atomic
 - Threads cannot get context switched in middle of load/store to/from a word
- In x86, load and store operations on naturally aligned variables are atomic
 - I.e., aligned to at least multiple of its own size
 - E.g., 8-byte int that is aligned to an address that's multiple of 8
- Many instructions are not atomic
 - Double-precision floating point store often not atomic
 - VAX and IBM 360 had an instruction to copy whole array
- Unless otherwise stated, we assume loads and stores are <u>atomic</u>

Mutual Exclusion With Load and Store

Mutual Exclusion With Load and Store: Discussion

- It's very unsatisfactory
 - Only protects a single critical section
 - Extending this solution to protect multiple critical sections is nontrivial
 - Way too complex even for this simple example
 - It's hard to convince yourself that this really works
 - A's code is different from B's
 - What if there are more than two threads?
 - See Peterson's algorithm
 - A is busy-waiting while B is in critical section
 - While A is waiting, it is consuming CPU time
- It doesn't work on most of today's computers
 - It only works if instructions are executed in program order
 - Compilers and hardware could reorder instructions
 - E.g., store buffer allows next instruction to execute while store is being completed

Question: Can This Panic?

Aside: Memory Consistency in Multiprocessors

```
// initially flag = data = r1 = r2 = 0

CPU1

S1: data = NEW;

L1: r1 = flag;

S2: flag = SET;

B1: if (r1 != SET) goto L1;


L2: r2 = data;
```

- Intuition says we should print r2 = NEW
- Yet, in some consistency models, this isn't required!

Sequential Consistency

"The result of any execution is the same as if the operations of all processors (CPUs) were executed in some sequential order, and the operations of each individual processor (CPU) appear in this sequence in the order specified by its program."


Lamport, 1979



Sequential Consistency (cont.)

"The result of any execution is the same as if the operations of all processors (CPUs) were executed in some sequential order, and the operations of each individual processor (CPU) appear in this sequence in the order specified by its program."

Lamport, 1979



x86 Memory-consistency Model

```
// initially x = y = r1 = r2 = r3 = r4 = 0

CPU1
S1: x = NEW;
L1: r1 = x;
L2: r2 = y;

CPU2
S2: y = NEW;
L3: r3 = y;
L4: r4 = x;
```

```
Program Order of CPU | Memory Order | Program Order of CPU2 | S1: x = NEW; // NEW | S2: y = NEW; // NEW | L3: r3 = y; // NEW | L4: r4 = x; // 0
```

Mutual Exclusion with Mutex

- Mutex operations
 - mutex.lock() wait until lock is free, then grab
 - mutex.unlock() Unlock, waking up anyone waiting
- Rules of using mutex
 - Always lock before accessing shared data
 - Best place for locking is beginning of procedure!
 - Always unlock after finishing with shared data
 - Best place for unlocking is end of procedure!
 - Only the thread that locked mutex should unlock it
 - DO NOT throw locked mutex to someone else to unlock
 - Never access shared data without lock
 - Danger! Don't do it even if it's tempting!

Lock Before Accessing Shared Data, ALWAYS!

```
getP() {
    if (p == NULL) {
        mutex.lock();
        if (p == NULL) {
            temp = malloc(sizeof(...));
            temp->field1 = ...;
            temp->field2 = ...;
            p = temp;
        }
        mutex.unlock();
    }
    return p;
}
```

```
• Safe but expensive solution is

getP() {
    mutex.lock();
    if (p == NULL) {
        temp = malloc(sizeof(...));
        temp->field1 = ...;
        temp->field2 = ...;
        p = temp;
    }
    mutex.unlock();
    return p;
}
```

Does this work?

- No! Compiler/HW could make **p** point to **temp** before its fields are set
- This is called double-checked locking

Mutex Implementation - Take 1: Disabling Interrupts

- Recall: context switching is triggered in two ways
 - Voluntary: thread does something to relinquish CPU
 - Involuntary: interrupts cause dispatcher to take CPU
- On <u>uniprocessors</u>, we can avoid context switching by
 - Avoiding voluntary context switches
 - Preventing involuntary context switches by disabling interrupts
- Naïve implementation of mutex in uniprocessors

```
class Mutex {
   public:
      void lock() { disable_interrupts(); };
      void unlock() { enable_interrupts(); };
}
```

Problems with Naïve Implementation of Mutex

OS cannot let users use this!

```
Mutex::lock();
while(TRUE);
```

- It does not work well in multiprocessors
 - Other CPUs could be interrupted



- Real-time OSes should provide guarantees on timing!
 - Critical sections might be arbitrarily long
 - What happens with I/O or other important events?
 - "Reactor about to meltdown. Help?"

Implementation of Mutex - Take 2: Disabling Interrupts + Lock Variable

Key idea: maintain lock variable and impose mutual exclusion only during operations on that variable

```
class Mutex {
  private:
    int value = FREE;
    Queue waiting;
  public:
    void lock();
    void unlock();
}
```

Take 2 (cont.)

```
Mutex::lock() {
                                                    Mutex::unlock() {
     disable_interrupts();
                                                         disable interrupts();
     if (value == BUSY) {
                                                         if (!waiting.empty()) {
          // Add TCB to waiting queue
                                                              // Make another TCB eady
          waiting.add(runningTCB);
                                                              next = waiting.remove();
          runningTCB->state = WAITING;
                                                              next->state = READY;
          // Pick new thread to run
                                                              ready list.add(next);
          chosenTCB = ready list.get nextTCB();
                                                         } else {
          // Switch to new thread
                                                              value = FREE;
          thread switch(runningTCB, chosedTCB);
          // We're back! We have locked mutex!
                                                         enable_interrupts();
          runningTCB->state = RUNNING;
     } else {
          value = BUSY;
                                                Enable/disable interrupts also act as a
     enable_interrupts();
                                                memory barrier operation forcing all
                                                memory writes to complete first
```

Take 2: Discussion

- Why do we need to disable interrupts at all?
 - Avoid interruption between checking and setting lock value
 - Otherwise, two threads could think that they both have locked the mutex

```
Mutex::lock() {
    disable_interrupts();
    if (value == BUSY) {
        ...
    } else {
        value = BUSY;
    }
    enable_interrupts();
}

Critical section of mutex
    (different form critical section of program)
```

- Unlike previous solution, critical section (inside lock()) is very short
 - User of mutex can take as long as they like in their own critical section (doesn't impact global machine behavior)
 - Critical interrupts taken in time!


Re-enabling Interrupts

```
Mutext::lock() {
    disable_interrupts();
    if (value == BUSY) {
        waiting.add(runningTCB);
        runningTCB->state = WAITING;
        chosenTCB = ready_list.get_nextTCB();
        thread_switch(runningTCB, chosedTCB);
        runningTCB->state = RUNNING;
    } else {
        value = BUSY;
    }
    enable_interrupts();
}
```

- Before putting thread on wait queue?
 - unlock() can check waiting queue and not wake up thread
- After putting thread on wait queue?
 - unlock() puts thread on ready queue, but thread still thinks it needs to go to sleep!
 - Thread goes to sleep while keeping mutex locked (deadlock!)
- After thread_switch()? But ... how?

How to Re-enable After thread_switch()?

- It is responsibility of next thread to re-enable interrupts
 - This invariant should be carefully maintained
- When sleeping thread wakes up, returns to lock() and re-enables interrupts



Problems with Take 2

- User libraries cannot use this implementation (why?)
- Doesn't work well on multiprocessor
 - Disabling interrupts on all processors requires messages and would be very time consuming
- Alternative solution: atomic read-modify-write instructions
 - Read value from an address and then write new value to it atomically
 - Make HW responsible for implementing this correctly
 - Uniprocessors (not too hard)
 - Multiprocessors (requires help from cache coherence protocol)
 - Unlike disabling interrupts, this can be used in both uniprocessors and multiprocessors

Examples of Read-Modify-Write Instructions

```
/* most architectures */
test&set (&address) {
       result = M[address];
                                           /* return result from
       M[address] = 1;
                                              "address" and set value at
       return result;
                                              "address" to 1 */
swap (&address, register) {
                                          /* x86 */
       temp = M[address];
                                          /* swap register's value to
       M[address] = register;
                                              value at "address" */
       register = temp;

    compare&swap (&address, reg1, reg2) { /* 68000 */

       if (reg1 == M[address]) {
           M[address] = reg2;
           return success;
       } else {
           return failure;
```

Spinlock with test&set()

Simple implementation

```
class Spinlock {
  private:
    int value = 0
  public:
    void lock() { while(test&set(value)); };
    void unlock() { value = 0; };
}
```

- Unlocked mutex: test&set reads 0 and sets value = 1
- Locked mutex: test&set reads 1 and sets value = 1 (no change)
- What is wrong with this implementation?
 - Waiting threads consume cycles while busy-waiting

Spinlock with test&set(): Discussion

- Upside?
 - Machine can receive interrupts
 - User code can use this mutex
 - Works on multiprocessors



- Downside?
 - This is very wasteful as threads consume CPU cycles (busy-waiting)
 - Waiting threads may delay the thread that has locked mutex (no one wins!)
 - Priority inversion: if busy-waiting thread has higher priority than the thread that has locked mutex then there will be no progress! (more on this later)
- In semaphores and monitors, threads may wait for arbitrary long time!
 - Even if busy-waiting was OK for mutexes, it's not OK for other primitives
 - Exam/quiz solutions should avoid busy-waiting!

Implementation of Mutex - Take 3: Using Spinlock

- Can we implement mutex with text&set without busy-waiting?
 - We cannot eliminate busy-waiting, but we can minimize it!
 - Idea: only busy-wait to atomically check mutex value

```
class Mutex {
                                       class Scheduler {
 private:
                                        private:
   int value = FREE;
                                           Queue readyList;
    Spinlock mutex spinlock;
                                           Spinlock scheduler spinlock;
   Queue waiting;
 public:
                                        public:
   void lock();
                                           void suspend(Spinlock *spinlock);
   void unlock();
                                           void make ready(TCB *tcb);
                                       }
```

Implementation of Mutex - Take 3 (cont.)

```
Mutex::lock() {
                                                Mutex::unlock() {
     mutex spinlock.lock();
                                                     mutex spinlock.lock();
     if (value == BUSY) {
                                                     if (!waiting.empty()) {
                                                           // Make another TCB ready
          // Add TCB to waiting queue
          waiting.add(runningTCB);
                                                          next = waiting.remove();
          scheduler->suspend(&mutex spinlock)
                                                           scheduler->make ready(next);
          // Scheduler unlocks mutex spinlock
                                                     } else {
     } else {
                                                          value = FREE;
          value = BUSY;
          mutex spinlock.unlock();
                                                     mutext spinlock.unlock();
```

Can interrupt handler use this lock?

- No! Interrupt handler is not a thread, it cannot be suspended
 How should we protect data shared by interrupt handler and kernel thread?
- Use spinlocks!
- To avoid deadlock, kernel thread should disable interrupts before locking the spinlock.
- Otherwise, interrupt handler could spin forever if spinlock is locked by a kernel thread!

Implementation of Mutex - Take 3 (cont.)

```
Scheduler::suspend(Spinlock *spinlock) {
    disable_interrupts();
    scheduler_spinlock.lock();
    spinlock->unlock();
    runningTCB->state = WAITING;
    chosenTCB = ready_list.get_nextTCB();
    thread_switch(runningTCB, chosenTCB);
    runningTCB->state = RUNNING;
    scheduler_spinlock.unlock();
    enable_interrupts();
}
```

```
Scheduler::make_ready(TCB *tcb) {
    disable_interrupts();
    scheduler_spinlock.lock();
    ready_list.add(tcb);
    thread->state = READY;
    scheduler_spinlock.unlock();
    enable_interrupts();
}
```

Why disable interrupts?

- To avoid deadlock!
- Interrupt handler could spin forever if it needs scheduler's spinlock!

What might happen if we unlock mutex_spilock before suspend()?

Then make_ready() could run before suspend(), which is very bad!

Mutex Using Interrupts vs. Spinlock

```
lock() {
                                        lock() {
   disable interrupts();
                                           mutex spinlock.lock();
   if (value == BUSY) {
                                           if (value == BUSY) {
      // put thread on wait queue and
                                               // put thread on wait queue and
      // go to sleep
                                               // go to sleep
   } else {
                                           } else {
      value = BUSY;
                                               value = BUSY;
                                               mutex_spinlock.unlock();
   enable interrupts();
                                        }
```

- Replace
 - disable interrupts; ⇒ spinlock.lock;
 - enable interrupts ⇒ spinlock.unlock;

Recap: Mutexes Using Interrupts

```
int value = FREE;
                              lock() {
                                                               lock() {
                                disable interrupts();
                                                                  // Short busy-wait time
                                                                 disable interrupts();
                                                                 if (value == BUSY) {
                                                                    // put thread on wait queue
Mutex::lock();
                                                                   // and go to sleep
                                                                 } else {
                                                                    value = BUSY;
 critical section:
                                                                 enable interrupts();
Mutex::unlock();
                              unlock() {
                                                               unlock() {
                                enable interrupts();
                                                                 // Short busy-wait time
                                                                 disable interrupts();
                                                                 if (!waiting.empty()) {
                                                                   // take thread off wait queue
                                                                   // place it on ready queue;
                                                                 } else {
                            If one thread is in critical
                                                                   value = FREE;
                            section, no other activity
                                                                 enable interrupts();
                             (including OS) can run!
```

Recap: Mutexes Using Spinlock (test&set)

```
int value = FREE
                            lock() {
                              while (test&set(value));
Mutex::lock();
critical section:
Mutex::unlock();
                            unlock() {
                              value = FREE;
                            Threads waiting to enter
                            critical section busy-wait
```

```
Spinlock mutex spinlock;
int value = FREE:
lock() {
  // Short busy-wait time
  mutex spinlock.lock();
  if (value == BUSY) {
    // put thread on wait queue
    // and go to sleep
  } else {
    value = BUSY;
    mutex spinlock.unlock();
Release() {
 // Short busy-wait time
 mutex spinlock.lock();
 if (!waiting.empty()) {
   // take thread off wait queue
   // place it on ready queue
  } else {
   value = FREE;
 mutex spinlock.unlock();
```

Mutex Implementation in Linux

- Most mutexes are free most of the time
 - Linux implementation takes advantage of this fact
- Hardware supports powerful atomic operations
 - E.g., atomic increment, decrement, exchange, etc.
 - Linux implementation takes advantage of these too
- Fast path
 - If mutex is unlocked, and no one is waiting, two instructions to lock
 - If no one is waiting, two instructions to unlock
- Slow path
 - If mutex is locked or someone is waiting, use take 3 implementation

Mutex Implementation in Linux (cont.)

```
struct Mutex {
    // 1: unlocked; < 1: locked
    atomic_t count;
    Spinlock mutex_spinlock;
    Queue waiting;
}</pre>
```

```
// code for lock()
lock decl (%eax)
// jump if not signed
// i.e., if value is now 0
jns 1f
call slow_path_lock
1:
//critical section
```

- For Mutex::lock(), Linux uses macro
 - To void making procedure call on fast path
- x86 *lock* prefix before *dec1* instruction signifies to processor that instruction should be executed <u>atomically</u>

Mutex Implementations: Discussion


- Our lock implementations are procedure calls
- Work well for kernel threads



- Does not work properly for user threads
 - Because system call may often disable interrupts/save state to TCB
 - But same basic idea works e.g., in Linux, user-level mutex has two paths Fast path: lock using test&set and slow path: system call to kernel, use kernel mutex
- How do lock—initiated and timer-interrupt-initiated switches interleave?
 - Turns out, they just work as long as we maintain the invariant on interrupts -disable before calling thread_switch() and enable when thread_switch() returns

Recall: Semaphores

- First defined by Dijkstra in late 60s
- Main synchronization primitive used in original UNIX
- Semaphore has non-negative integer value and 2 operations
 - P(): atomic operation that waits for semaphore to become positive, then decrements it by one
 - V(): atomic operation that increments semaphore by one, then wakes up a waiting P(), if any



Implementation of Semaphore

```
Semaphore::P() {
                                                      Semaphore::V() {
    semaphore spinlock.lock();
                                                          semaphore spinlock.lock();
    if (value == 0) {
                                                          if (!waiting.empty()) {
        waiting.add(myTCB);
                                                              next = waiting.remove();
        scheduler->suspend(&semaphore spinlock);
                                                              scheduler->make ready(next);
    } else {
                                                          } else {
        value--:
                                                              value++;
    semaphore spinlock.unlock();
                                                          semaphore spinlock.unlock();
```

Can interrupt handler use this semaphore?

- It cannot use P (why?), but it might want to use V (more on this later)
- In that case, interrupts should be disabled at the beginning of P and V and enabled at the end

Semaphores are Harmful!

"During system conception it transpired that we used the semaphores in two completely different ways. The difference is so marked that, looking back, one wonders whether it was really fair to present the two ways as uses of the very same primitives. On the one hand, we have the semaphores used for <u>mutual exclusion</u>, on the other hand, the <u>private semaphores</u>."

Dijkstra "The structure of the 'THE'-Multiprogramming System" Communications of the ACM v. 11 n. 5 May 1968.

Monitors and Condition Variables

- Problem: analyzing code that uses semaphores is complex
 - They are dual purpose (both mutual exclusion and scheduling constraints)

- Solution: use monitors
 - It consists of one mutex with zero or more condition variables (CV)
 - Mutex is used for mutual exclusion, CV's are used for scheduling constraints

Recall: Condition Variables

- CV is queue of threads waiting for an event inside critical section
 - Makes it possible to go to sleep inside critical section
 - Atomically unlocks mutex at time thread goes to sleep
 - With semaphores, threads cannot wait inside critical section (deadlock)
- CV operations
 - wait(Mutex *CVMutex)
 - Atomically unlocks mutex, puts thread to sleep, and relinquishes processor
 - Attempts to locks mutex when thread wakes up
 - signal()
 - Wakes up a waiter, if any
 - broadcast()
 - Wakes up all waiters, if any

Recall: Properties of CV

- Condition variables are memoryless
 - No internal memory except a queue of waiting threads
 - No effect in calling signal/broadcast on empty queue



• <u>ALWAYS</u> hold lock when calling wait(), signal(), broadcast()

• Calling wait() atomically adds thread to wait queue and releases lock

- Re-enabled waiting threads may not run immediately
 - No atomicity between **signal/broadcast** and the return from **wait**

Recall: CV Design Pattern

```
method_that_waits() {
                                        method_that_signals() {
   mutex.lock();
                                           mutex.lock();
   // Read/write shared state
                                           // Read/write shared state
  while (!testSharedState())
                                           // If testSharedState is now true
      cv.wait(&mutex);
                                           cv.signal();
   // Read/write shared state
                                           // Read/write shared state
   mutex.unlock();
                                           mutex.unlock();
```

Example: Bounded Buffer With Monitors

```
Mutex BBMutex:
CV emptyCV, fullCV;
produce(item) {
   BBMutex.lock();
   while (buffer.size() == MAX)
      fullCV.wait(&BBMutex); <</pre>
   buffer.enqueue(item);
   emptyCV.signal();
   BBMutex.unlock();
consume() {
   lock.acquire();
   while (buffer.isEmpty())
      emptyCV.wait(&lock);
   item = buffer.dequeue();
   fullCV.signal();
   lock.release();
   return item;
```

```
// lock the mutex
// wait until there is space

// signal waiting costumer
// unlock the mutex

// lock the mutex
// wait until there is item

// signal waiting producer
// unlock the mutex
```

Mesa vs. Hoare Monitors

• Consider piece of consume() code

```
while (queue.empty())
    emptyCV.wait(&mutex);
```

Why didn't we do this?

```
if (queue.empty())
   emptyCV.wait(&mutex);
```

- Answer: it depends on the type of scheduling
 - Hoare style
 - Mesa style

Hoare Monitors

- Signaler gives up mutex and processor to waiter waiter runs immediately
- Waiter gives up mutex and processor back to signaler when it exits critical section or if it waits again

```
mutex.lock()
mutex.lock()
...
mutex.lock()
...
if (queue.empty())
emptyCV.signal();
...
emptyCV.wait(&mutex);
...
mutex.unlock();
```

Mesa Monitors

- Signaler keeps mutex and processor
- Waiter placed on ready queue with no special priority
- Practically, need to check condition again after wait
- Most real operating systems

```
Put waiting thread
on ready queue
mutex.lock()
...
while (queue.empty())
emptyCV.signal();
...
mutex.unlock();
schedule waiting
mutex.unlock();
```

Mesa Monitor: Why "while()"?

• What if we use "if" instead of "while" in bounded buffer example?

```
consume() {
                                      produce(item) {
  mutex.lock();
                                        mutex.lock();
  if (queue.empty())
                                       _if (queue.size() == MAX)
    emptyCV.wait(&mutex);
                                          fullCV.wait(&mutex);
  item = queue.remove();
                                        queue.add(item);
  fullCV.signal();
                                        emptyCV.signal();
  mutex.unlock();
                                        mutex.unlock();
  return item;
                                Use "if" instead of "while"
```

App. Shared State

Monitor

CPU State

queue

mutex: unlocked emptyCV queue → NULL

Running: TI ready queue → NULL

...

TI (Running)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State


queue

mutex: locked (TI)
emptyCV queue → NULL

Running: TI
ready queue → NULL
....

TI (Running)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```



if (aueue.emptv())

fullCV.signal();
mutex.unlock();
return item;

}

emptyCV.wait(&mutex);

item = queue.remove();

App. Shared State

Monitor

CPU State

queue

mutex: unlocked emptyCV queue →TI


Running: T2
ready queue → NULL

TI (Waiting)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T2 (Running)

```
produce(item) {
    mutex.lock();
    if (queue.size()==MAX)
        fullCV.wait(&mutex);
    queue.add(item);
    emptyCV.signal();
    mutex.unlock();
}
```



```
TI (Waiting)
```

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T2 (Running)

```
produce(item) {
   mutex.lock();
   if (queue.size()==MAX)
      fullCV.wait(&mutex):
    queue.add(item);
   emptyCV.signal();
   mutex.unlock();
}
```

App. Shared State

Monitor

CPU State

queue

mutex: locked (T2) emptyCV queue → NULL

Running: T2 ready queue → TI

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T2 (Running)

```
produce(item) {
   mutex.lock();
   if (queue.size()==MAX)
      fullCV.wait(&mutex);
   queue.add(item);
   emptyCV.signal();
   mutex.unlock();
}
```

signal() wakes up and moves it to ready queue



Monitor

```
CPU State
```

```
queue
```

mutex: locked (T2) emptyCV queue → NULL

```
Running: T2 ready queue → T1, T3 ...
```

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T2 (Running)

```
produce(item) {
   mutex.lock();
   if (queue.size()==MAX)
      fullCV.wait(&mutex);
   queue.add(item);
   emptyCV.signal();
   mutex.unlock();
}
```

T3 (Ready)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State

queue

mutex: unlocked emptyCV queue \rightarrow NULL

Running: ready queue →TI,T3

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T2 (Terminated)

```
produce(item) {
   mutex.lock();
   if (queue.size()==MAX)
      fullCV.wait(&mutex);
   queue.add(item);
   emptyCV.signal();
   mutex.unlock();
}
```

T3 (Ready)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State



mutex: unlocked emptyCV queue \rightarrow NULL

Running: T3 ready ueue $\rightarrow T1$

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T3 is scheduled first

T3 (Running)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State

queue

mutex: locked (T3) emptyCV queue → NULL Running: T3 ready queue →TI

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T3 (Running)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State

queue

mutex: locked (T3) emptyCV queue → NULL

Running: T3 ready queue →TI

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T3 (Running)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

App. Shared State

Monitor

CPU State

queue

mutex: unlocked emptyCV queue \rightarrow NULL

Running: ready queue →TI

TI (Ready)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

T3 (Terminated)

```
consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item:
}
```

App. Shared State

Monitor

CPU State


queue

mutex: locked (T1)
emptyCV queue → NULL

Running: T1
ready queue → NULL
...

TI (Running)


```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```



```
TI (Running)


consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();

  fullCV.signal();
  mutex.unlock();
  return item;
}
```



```
TI (Running)

consume() {
  mutex.lock();
  if (queue.empty())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```



TI (Waiting)

```
consume() {
  mutex.lock();
  if (queue.emptv())
    emptyCV.wait(&mutex);
  item = queue.remove();
  fullCV.signal();
  mutex.unlock();
  return item;
}
```

When waiting upon a *Condition*, a spurious wakeup is permitted to occur, in general, as a concession to the underlying platform semantics. This has little practical impact on most application programs as a *Condition* should always be waited upon in a loop, testing the state predicate that is being waited for

From Java User Manual

Condition Variable vs. Semaphore

- CV's signal() has no memory
 - If signal() is called before wait(), then signal is waisted
- Semaphore's V() has memory
 - If V() is called before P(), P() will not wait
- Generally, it's better to use monitors but not always
- Example: interrupt handlers
 - Shared memory is used concurrently by interrupt handler and kernel thread
 - Interrupt handler cannot use mutexes
 - Kernel thread checks for data and calls wait() if there is no data
 - Interrupt handler write to shared memory and calls signal()
 - This is called naked notify because interrupt handler hasn't locked mutex (why?)
 - This may not work if signal comes before kernel thread calls wait
 - Common solution is to use semaphores instead

Implementation of Condition Variables

```
class CV {
   private:
     Queue waiting;
   public:
     void wait(Mutex *mutex);
     void signal();
     void broadcast();
 }
 CV::wait(Mutex *mutex) {
     waiting.add(myTCB);
     scheduler.suspend(&mutex);
     mutex->lock();
```

```
CV::signal() {
    if (!waiting.empty()) {
        thread = waiting.remove();
        scheduler.make ready(thread);
void CV::broadcast() {
   while (!waiting.empty()) {
        thread = waiting.remove();
        scheduler.make ready(thread);
```

Why doesn't class CV need cv_spinlock?

• Since mutex is locked whenever wait, signal, or broadcast is called, we already have mutually exclusive access to condition wait queue

Implementation of Condition Variable using Semaphores (Take 1)

```
wait(*mutex) {
    mutex->unlock();
    semaphore.P();
    mutex->lock();
}
signal() {
    semaphore.V();
}
```

- Does this work?
 - No! signal() should not have memory!

Implementation of Condition Variable using Semaphores (Take 2)

```
wait(*mutex) {
    mutex->unlock();
    semaphore.P();
    mutex->lock();
}
signal() {
    if (semaphore's queue is not empty)
        semaphore.V();
}
```

- Does this work?
 - No! For one, not legal to look at contents of semaphore's queue.
 - But also, unlocking mutex and going to sleep should happen atomically

 signaler can slip in after mutex is unlocked, and before waiter is put
 on wait queue, which means waiter never wakes up!

Implementation Condition Variable using Semaphores (Take 3)


Key idea: have separate semaphore for each waiting thread and put semaphores in ordered queue

```
wait(*mutex) {
    semaphore = new Semaphore; // a semaphore per waiting thread
    queue.add(semaphore); // queue for waiting threads
    mutex->unlock();
    semaphore.P();
    mutex->lock();
}
signal() {
    if (!queue.empty()) {
        semaphore = queue.remove()
        semaphore.V();
    }
}
```

Summary

- Use HW atomic primitives as needed to implement synchronization
 - Disabling of Interrupts, test&set, swap, compare&swap
- Define lock variable to implement mutex,
 - Use HW atomic primitives to protect modifications of that variable
- Maintain the invariant on interrupts
 - Disable interrupts before calling thread_switch() and enable them when thread_switch() returns
- Be very careful not to waste machine resources
 - Shouldn't disable interrupts for long
 - Shouldn't busy-wait for long

Questions?



Acknowledgment

Slides by courtesy of Anderson, Culler, Stoica,
 Silberschatz, Joseph, and Canny