

Trademarks

SOA Software and the SOA Software logo are either trademarks or registered trademarks of SOA Software, Inc. Other product names, logos, designs, titles, words or phrases mentioned within this guide may be trademarks, service marks or trade names of SOA Software, Inc. or other third parties and may be registered in the U.S. or other jurisdictions.

Copyright

©2001-2014 SOA Software, Inc. All rights reserved. No material in this manual may be copied, reproduced, republished, uploaded, posted, transmitted, distributed or converted to any electronic or machine-readable form in whole or in part without prior written approval from SOA Software, Inc.

Table of Contents

MWARE [®]		
Preface		
Overview Deployment Diagrams In This Guide	4	
Deploying and Installing the API Gateway Appliance	7	
OverviewStep 1: Download API Gateway ApplianceStep 2: Deploy API Gateway ApplianceStep 3: Select API Gateway Appliance FeaturesStep 4: Use It	7 7 8	
Appendix A: System Requirements	13	
Appendix B: Console Default Credentials	14	
Appendix C: Setting Up a Community Manager Tenant	16	
Appendix D: Documentation	17	
Appendix E: Customer Support	18	

PREFACE

OVERVIEW

The SOA Software API Gateway virtual appliance is a virtual machine that provides an automated installation and configuration approach for SOA Software's Community Manager, Policy Manager, and Network Director. Product installations are packaged in the following feature sets:

Option 1: SOA Software API Gateway Master

Installs a virtual machine with Policy Manager, Network Director, and MySQL Server.

Option 2: SOA Software API Gateway Master—Community Manager

Installs a virtual machine with Community Manager, Policy Manager, and Network Director with options for installing an internal MySQL database or using an external database (e.g., Oracle, Microsoft SQL Server, or MySQL Server).

Option 3: SOA Software API Gateway Slave

Installs a virtual machine with Network Director. The Network Director instance will be a node of the Network Director Cluster created on the master appliance.

DEPLOYMENT DIAGRAMS

You can choose an option from one of the deployment scenarios described in the diagrams below to decide which feature to install.

Note: Option 3: SOA Software API Gateway Slave is used *only* if you plan to deploy the Network Director Cluster scenario.




Figure 1: Deployment Diagram for Feature Option 1 (SOA Software API Gateway Master) and Multiple Instances of Feature Option 3 (SOA Software API Gateway Slave)




Figure 2: Deployment Diagram for Feature Option 2 (SOA Software API Gateway Master - Community Manager) and Multiple Instances of Feature Option 3 (SOA Software API Gateway Slave)

In This Guide

This guide includes the following:

- Deploying and Installing the API Gateway Appliance
 - Step 1 Download API Gateway Appliance
 - Step 2 Deploy API Gateway Appliance
 - Step 3 Select API Gateway Appliance Features
 - Step 4 Use It
- Appendix A System Requirements
- Appendix B Console Default Credentials
- Appendix C Setting Up a Community Manager Tenant
- Appendix D Documentation
- Appendix E Customer Support

DEPLOYING AND INSTALLING THE API GATEWAY APPLIANCE

OVERVIEW

The following instructions tell you how to deploy and install the SOA Software API Gateway Appliance on supported VMware[®] environments.

Note: If you need help determining a console password, refer to *Appendix B: Console Default Passwords*.

STEP 1: DOWNLOAD API GATEWAY APPLIANCE

Download the SOA Software API Gateway Appliance ZIP (contains VMDK-Virtual Machine Disk files), or OVF (Open Virtualization Format) files to your local machine via the SOA Software Customer Support website (http://support.soa.com) from the following location:

Downloads -> API Gateway

Select the format that is supported by the VMware version you are using (see *Appendix A: System Requirements*).

VMware Version	VMware Server 1.0 and above
	VMware ESX 3.0 and above
	VMware ESXi 3.5 and above
	VMware Workstation 6.0 and above
	VMware Player 2.0 and above
	VMware Fusion 1.1 and above
Setup File Type	OVF, ZIP(contains VMDK files)

Refer to the next section for installation examples using an OVF file for VMWare ESX 5.1, and zip file for VMWare workstation 9.0.

STEP 2: DEPLOY API GATEWAY APPLIANCE

- Before you start VMware, verify that your Memory and Network Adaptor settings comply with those specified in *Appendix A: System Requirements*.
- The deployment process automatically assigns a default host name of soagw.

To Deploy the API Gateway Appliance

Step	Procedure	
1.	For VMware ESX 5.1:	
	Use the vCenter <i>Deploy OVF Template</i> wizard to deploy the OVF file.	
	Select Power on after deployment.	
	For VMware Workstation 9.0:	
	Extract the downloaded ZIP file to a local folder.	
	Use VMware Workstation 9.0 to Open the vmxf file.	
	Select Power on this virtual machine.	
2.	During the installation process:	
	You can use the space bar to scroll down to the end of the agreement.	
	Accept the license agreement.	
3.	The deployment process takes approximately three minutes.	
4.	After the initial deployment, you are presented with Login and Set Timezone (Current: <timezone>) options.</timezone>	
	Set Time Zone:	
	We recommend setting your system time zone before starting the installation. Policy Manager will be automatically installed according to the system time zone. You can also change the time zone in the <i>Policy Manager Management Console</i> after you complete the installation.	
	Login:	
	If this is your first login, enter the root login credentials admin/password and provide a new password. Refer to Appendix B: Console Default Credentials for information on default passwords and password rules.	
	Note: When performing the change password process, remember to enter the default password first, followed by the new password and confirmation.	
	Please make sure you remember the password. Your new password will also be your login credentials for the API Gateway Appliance Administration Console.	
5.	After the deployment is complete, continue to Step 3: Select API Gateway Appliance Features.	

STEP 3: SELECT API GATEWAY APPLIANCE FEATURES

After you complete the initial login process, you configure the API Gateway Appliance for selected feature sets. There are three configuration options, each with different configuration requirements.

Option	Feature Set Name	Description
1	SOA Software API Gateway Master (Uses INTERNAL database)	Includes a Policy Manager instance, a Network Director instance, and an internal MySQL Server.
2	SOA Software API Gateway Master — Community Manager	Includes a Policy Manager instance, a Network Director instance, and a Community Manager instance, This feature set offers two Database support options:
	(Uses Internal or	 Create a database on an internal MySQL Server.
External database)	 Use an external database. The appliance supports Oracle, Microsoft SQL Server, and MySQL Server. 	
	Note: If you are using Microsoft SQL Server, the database driver file is included as part of the feature set installation.	
3	SOA Software API	Includes a Network Director Slave instance.
Gateway Slave	You must specify the IP address of the API Gateway Master. This enables the API Gateway Slave to connect to the database on the API Gateway Master.	
		The API Gateway Master must be running when the SOA Software API Gateway Slave feature is being installed.

Note: Refer to the *Deployment Diagrams* section in the *Preface* to decide which feature set to install. Each virtual appliance can only support a single feature set.

To Install the API Gateway Appliance Features

1.	Choose a feature set to install from the displayed list.	
	During the installation, you will see a list of tasks being performed (i.e., installation, configuration, startup, and an expected time of completion).	
	The startup process takes approximately three minutes. Note that the Linux interface may show a notification that describes the status as well as the expected wait time.	
2.	2. If you choose to install <i>Option 2: SOA Software API Gateway Master—Community Manager</i> (with an external database) or <i>Option 3: SOA Software API Gateway Slave</i> , you will be prompted to "Enter Gateway ID." This Gateway ID must be a string without a space and can contain letters, numbers or a dash "-" character.	
3.	Upload Database Driver File	
	First download the specified database driver version from the MySQL or Oracle website (MySQL: com.springsource.com.mysql.jdbc-5.1.6.jar, Oracle: ojdbc6.jar).	

To Install the API Gateway Appliance Features

- Then launch https://ip:5480/dbdrive.html in your browser and upload the MySQL Server or Oracle database driver.
- 4. If you choose to install *Option 2: SOA Software API Gateway Master—Community Manager* (with an external database), after installing Community Manager and Policy Manager, you will use the *Community Manager Administration Console* and *Policy Manager Administration Console* to complete configuration. You will need to:

Community Manager:

- Open the Community Manager Administration Console URL presented after the "Installing CM" prompt.
- Log in using "administrator/password" credentials and "admin console" domain.
- Select Installed Features > Complete Configuration > Pending Installation Tasks.
- Select **Add Database** and provide external database information.
- Select Manage Schemas and add schemas listed in the "Available Schemas" section.

Policy Manager:

- Open the Policy Manager Administration Console URL presented after the "Installing PM" prompt.
- Log in using "administrator/password" and "admin console" domain.
- Select Installed Features > Complete Configuration > Pending Installation Tasks.
- Select **Add Database**, then select the "Use existing database" option and provide external database information.

5. **SOA Software Slave Feature**

If you choose the SOA Software API Gateway Slave feature, you will be prompted for more information:

- At the **Enter the hostname of the primary gateway prompt**, specify the IP address of the Master API Gateway and password of the admin user.
- The API Gateway Master must be running.

This will exchange the admin user account SSH public keys of the primary and slave gateways to enable communication after the installation is complete.

To Verify API Gateway Appliance Installation

After the appliance installation is complete, the system displays the *API Gateway Appliance Administration Console* URL that you will launch to complete the remaining installation tasks.

The default URL is https://<Appliance ip address>:5480/.

- 2. To illustrate what you've accomplished:
 - Log into the API Gateway Appliance Administration Console for the API Gateway Master (<a href="https://<Appliance-ip-address>:5480/">https://<Appliance-ip-address>:5480/).

To Verify API Gateway Appliance Installation

- On the *Management* tab, you will see the container instances that you installed. If you installed *Option 1: SOA Software API Gateway Master*, use the *Policy Manager Management Console* URL and log in using the default credentials (administrator/password) at http://cappliance.ip.address:9900/.
- From the *Policy Manager Management Console*, select the *Containers* folder in the root level Organization to verify that the Network Director container is running (State = Started).
- If you have multiple Network Director Slaves, you can also verify that these Network Director containers are running.

Option 2: SOA Software API Gateway Master—Community Manager

If you chose *Option 2: SOA Software API Gateway Master - Community Manager*, you must create a tenant using the download package from Appliance console.

On the *Management* tab of the API Gateway Administration Console, click the link **Download Create Tenant Package**. The download package is a zip file "create_tenant.zip." You can unzip the file to a local machine, and run the script remotely to create tenants.

For example,

```
[unzipped file path]/bin>jython
../scripts/Lib/soa/atmosphere/tenant.py -a -v --url
http://10.1.22.236:9980 --tenantName gw1 --tenantId gw1 --address
http://gw1:9980 --consoleAddress http://gw1:9980 --theme default --
contactEmailAddress abc@company.com --fromEmailAddress abc@.com
```

Please refer to Appendix C for a description of script syntax and parameters.

You can also refer to *Step 12: Create Community Manager Tenant* in the *Enterprise API Platform Installation Guide for Windows and UNIX Platforms* for script examples for both Windows and UNIX Platforms. You can find this guide on the SOA Software Documentation Repository (http://docs.soa.com).

After you create a tenant, verify the tenant URL you just created in the script (e.g., http://<hostname>:<port>/<tenantname>).

Note: Verify that the tenant name is accessible from your network.

If you would like to access the *Community Manager Console* on a local system, you must add a hostname in the following hosts file:

- Windows: C:\Windows\System32\drivers\etc
- LINUX: /etc/hosts.
- 4. Refer to the SOA Software API Gateway Appliance Administration Guide where you will use the API Gateway Appliance Administration Console to complete a series of general configuration tasks that apply to all feature sets including:

To Verify API Gateway Appliance Installation

- Configuring Network Address and Proxy Settings
- Updating the API Gateway Appliance

STEP 4: USE IT

Now that you've completed the installation of one or more API Gateway feature sets, it's time to start using the system to publish services, monitor services, define policies, and so on. Refer to the *Policy Manager Getting Started Guide* for details.

APPENDIX A: SYSTEM REQUIREMENTS

The following table provides hardware requirements, a list of VMware versions that the SOA Software API Gateway Appliance product has been certified on, and a list of minimum system requirements for running the SOA Software API Gateway Appliance.

Item	Requirement
VMware Environment to Host the API Gateway Virtual Appliance	 VMware vCenter > ESX 5.1 (Requires OVF setup file) VMware Workstation 9.0 (Requires ZIP setup file)
Resources required by API	64-bit Processor ONLY.
Gateway Virtual Appliances	 Memory: The default and recommended memory size is 6GB with 3GB minimum.
	CPU: 2 cores
	Hard Drive: 60GB
	Network Adapter: One Ethernet Network Adapter
	 IP Address: DHCP server is required to provide an IP address. One static IP address is required to be configured on the primary virtual appliance if slave virtual appliances 4neet to be set up. IPV4 is supported.
	 DNS Setting: One host name for each tenant must be configured in the DNS server if the virtual appliance needs to host tenants.
Web Browser	IE 8.0 and above
	Mozilla Firefox 10+ and above

APPENDIX B: CONSOLE DEFAULT CREDENTIALS

The following table provides a detailed explanation and the default username / password credentials that are used during API Gateway Appliance installation tasks and for logging into consoles that are accessed via the API Gateway Appliance Administration Console.

Note: For security purposes, access to the appliance operating system is not permitted. If you require advanced troubleshooting, contact SOA Software Customer Support.

Console Name	Default Username / Password
Appliance Login Credentials (for initial API Gateway Appliance Installation and Appliance Administration Console access)	If this is your first login, enter the login credentials admin/password and provide a new password.
	Note: When performing the change password process, remember to enter your existing password first, followed by the new password and confirmation.
	Your new password will also be your login credentials for the API Gateway Appliance Administration Console.
	If you forget your root login credentials contact SOA Software Customer Support.
	Password Rules:
	Password must be 6 to 8 characters in length and cannot contain a space.
	Password cannot include Linux reserved words.
	Password cannot be the reverse, same with a change of case, similar, or rotated version of the previous password.
Policy Manager Management Console	The default login for the <i>Policy Manager Management Console</i> is administrator/password.
	 If you would like to change the administrator password, log into the Policy Manager Management Console, and use the Modify User function in the Security section.
SOA Software Administration Console	The SOA Software Administration Console is available for Policy Manager, Network Director, and Community Manager installations.
	The default login for the SOA Software Administration Console is

Console Name	Default Username / Password	
	administrator/password.	
	 If you would like to change the Administrator credentials, log into the SOA Software Administration Console, and use the Manage Admin Console Administrator function in the Configuration > Configuration Actions section. 	
Community Manager Administration Console	The default login for the Community Manager Management Console is administrator/password.	
	If you would like to change the administrator password, log into the Community Manager Console, go to the Profile > Settings section, edit your account and update the password.	
SOA Software Network Director Slave (for initial installation)	If you change the <i>Policy Manager Management Console</i> username/password to something other than the administrator/password default, the console installation process will prompt you for the new password.	

APPENDIX C: SETTING UP A COMMUNITY MANAGER TENANT

Community Manager requires at least one tenant. Each tenant is logically separate from every other tenant and is keyed off the hostname used to access the console. The following table provides a brief description of fields used to define your create tenant script:

Field	Description
URL	This is the base URL of the Platform API. The URL is normally structured similar to the following: http://[hostname/ip address]:9980. This is the hostname or IP Address on which the SOA container is running. There is normally no context unless the product is running in an application server.
Tenant Name	This is a friendly name for the tenant that may be used in emails, etc.
Tenant Id	This is the internal id of the tenant. It cannot have spaces or special characters. It should be lower case. It is normally the lower case (without spaces) version of the tenant name above. This will appear in all object ids and the URLs in the system.
Address	This is the base URL of the tenant. The hostname must be unique. This hostname is what will be used in the browser when accessing the UI and the product will use it to identify the tenant. Do not use any additional context paths in the Address field, as it should be root only. For example, use http://[hostname]:9980, not http://[hostname]:9980/abc/.
Console Address	This is the same as Address : it is the full URL where Community Manager is running. Console Address is used in the browser when accessing the UI.
Theme	This is the UI theme identifier. It is typically set to "default" unless a custom theme has been developed.
Email Address	This is the email address you want to be used as the default tenant administrator.
Password	This is the password you want to configure for the default tenant administrator.
Contact Email Address	Used in email templates.
From Email Address	Account used by the system to send email.
Virtual Hosts	A comma-separated list of host names that the product will accept (e.g., "open.soa.com")

APPENDIX D: DOCUMENTATION

After the base product installation is complete, refer to the following product documentation for Policy Manager administration and usage information.

- API Gateway Appliance Administration Guide
- Policy Manager Getting Started Guide
- Policy Manager Online Help
- Policy Manager Administration Guide

APPENDIX E: CUSTOMER SUPPORT

SOA Software offers a variety of support services to our customers. The following options are available:

Support Options:	
Email (direct)	support@soa.com
Phone	1-866 SOA-9876 (1-866-762-9876)
Email (Web)	The "Support" section of the SOA Software website (<u>www.soa.com</u>) provides an option for emailing product related inquiries to our support team.
Support Site	SOA Software Customer Support website (https://support.soa.com/support)