

# Nginx Module Extension

Customize and regulate the robust Nginx web server, and write your own Nginx modules efficiently



### **Nginx Module Extension**

Customize and regulate the robust Nginx web server, and write your own Nginx modules efficiently

**Usama Dar** 



BIRMINGHAM - MUMBAI

#### Nginx Module Extension

Copyright © 2013 Packt Publishing

All rights reserved. No part of this book may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, without the prior written permission of the publisher, except in the case of brief quotations embedded in critical articles or reviews.

Every effort has been made in the preparation of this book to ensure the accuracy of the information presented. However, the information contained in this book is sold without warranty, either express or implied. Neither the author, nor Packt Publishing, and its dealers and distributors will be held liable for any damages caused or alleged to be caused directly or indirectly by this book.

Packt Publishing has endeavored to provide trademark information about all of the companies and products mentioned in this book by the appropriate use of capitals. However, Packt Publishing cannot guarantee the accuracy of this information.

First published: December 2013

Production Reference: 1191213

Published by Packt Publishing Ltd. Livery Place 35 Livery Street Birmingham B3 2PB, UK.

ISBN 978-1-78216-304-6

www.packtpub.com

Cover Image by Rakesh Shejwal (shejwal.rakesh@gmail.com)

#### **Credits**

**Author** 

Usama Dar

Reviewer

Alex Kapranoff

**Acquisition Editor** 

Rebecca Youe

**Commissioning Editor** 

Manasi Pandire

**Technical Editors** 

Aparna Chand

Aparna Kumari

Adrian Raposo

**Copy Editors** 

Janbal Dharmaraj

Dipti Kapadia

Karuna Narayanan

Alfida Paiva

**Project Coordinator** 

Amey Sawant

Proofreader

Ting Baker

Indexer

Rekha Nair

**Production Coordinator** 

Melwyn D'sa

**Cover Work** 

Melwyn D'sa

#### About the Author

**Usama Dar** has over 13 years' experience working with software systems. During this period, he has not only worked with large companies such as Nortel Networks, Ericsson, and Huawei, but has also been involved with successful startups such as EnterpriseDB. He has worked with systems with mission-critical requirements of scalability and high availability. He writes actively on this website: www.usamadar.com. These days, Usama works at the Huawei Research Centre in Munich, where he spends most of his time researching highly scalable, high-performing infrastructure software (such as operating systems), databases, and web and application servers.

Big thanks to my parents for always providing me with confidence to pursue my dreams. Thanks to my wife for putting up with my crazy schedule and allowing me to work at odd hours to complete this book.

#### About the Reviewer

Alex Kapranoff was born into the family of an electronics engineer and programmer for the old Soviet "Big Iron" computers. He started programming at the age of 12 and has never worked outside the IT industry since. After earning a degree in Software Engineering with honors, he had a short stint in the world of enterprise databases and Windows. Then he settled on open source, Unix-like environments for good, first FreeBSD and then Linux, working as a developer for many Russian companies from ISPs to search engines. Most of his experience has been with e-mail and messaging systems and web security. Right now, he is trying his hand at a product and project management position in Yandex, one of the biggest search engines in the world.

He took his first look at Nginx working in Rambler side by side with the author of Nginx, Igor Sysoev, before the initial public release of the product. Since then, Nginx has been an essential tool in his kit. He doesn't launch a website — no matter how complex it is — without using Nginx.

He strongly believes in the Free Software Movement, loves Perl, plain C, LISP, cooking, and fishing, and lives with a beautiful girlfriend and an old cat in Moscow, Russia.

#### www.PacktPub.com

# Support files, eBooks, discount offers and more

You might want to visit www.PacktPub.com for support files and downloads related to your book.

Did you know that Packt offers eBook versions of every book published, with PDF and ePub files available? You can upgrade to the eBook version at www.PacktPub.com and as a print book customer, you are entitled to a discount on the eBook copy. Get in touch with us at service@packtpub.com for more details.

At www.PacktPub.com, you can also read a collection of free technical articles, sign up for a range of free newsletters and receive exclusive discounts and offers on Packt books and eBooks.



http://PacktLib.PacktPub.com

Do you need instant solutions to your IT questions? PacktLib is Packt's online digital book library. Here, you can access, read and search across Packt's entire library of books.

#### Why Subscribe?

- Fully searchable across every book published by Packt
- Copy and paste, print and bookmark content
- On demand and accessible via web browser

#### Free Access for Packt account holders

If you have an account with Packt at www.PacktPub.com, you can use this to access PacktLib today and view nine entirely free books. Simply use your login credentials for immediate access.

## **Table of Contents**

Pretace	1
Chapter 1: Installing Nginx Core and Modules from Source	5
Installing binary distribution	5
Red Hat, Fedora, and CentOS	6
Official Debian/Ubuntu packages	6
FreeBSD	7
OpenBSD	8
Official Win32 binaries	8
Installing source distribution	8
Nginx library dependencies	9
Configuring options	9
Files and permissions	10
The Event loop	11
Optional modules	11
Compilation controls	12
Example	12
The Custom module	13
Debugging	13
Installing on other platforms	13
Verifying your Nginx installation	14
Summary	14
Chapter 2: Configuring Core Modules	15
Understanding the Main module	15
Explaining directives	16
daemon	16
master_process	16
timer resolution	16
pid	17
lock_file	17
worker processes	17

#### eBooks-IT.org

Table of Contents

debug_points	17
user	17
worker_priority	18
worker_cpu_affinity	18
worker_rlimit_nofile	18
worker_rlimit_core worker_rlimit_sigpending	18 18
working_directory	19
env	19
Understanding the Events module	19
Explaining directives	20
accept mutex	20
accept_mutex_delay	20
debug_connection debug_connection	20
devpoll_changes and devpoll_events	21
kqueue_changes and kqueue_events	21
epoll_events	21
multi_accept	22
rtsig_signo rtsig_overflow events, rtsig_overflow test, and rtsig_overflow threshold	22 22
use	23
worker connections	23
Summary	23
Chapter 3: Installing and Configuring HTTP Modules	25
Standard HTTP modules	25
Standard HTTP modules The core module (HttpCoreModule)	<b>25</b> 25
Standard HTTP modules The core module (HttpCoreModule) Explaining directives	<b>25</b> 25 26
Standard HTTP modules The core module (HttpCoreModule) Explaining directives server	25 25 26 26
Standard HTTP modules The core module (HttpCoreModule) Explaining directives server server_name	25 25 26 26 26
Standard HTTP modules The core module (HttpCoreModule) Explaining directives server server_name Controlling access (HttpAccessModule)	25 25 26 26 26 32
Standard HTTP modules The core module (HttpCoreModule) Explaining directives server server_name Controlling access (HttpAccessModule) Authenticating users (HttpBasicAuthModule)	25 25 26 26 26 26 32 33
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives	25 25 26 26 26 32 33 33
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule)	25 25 26 26 26 32 33 33
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives	25 25 26 26 26 32 33 33 34
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule)	25 25 26 26 26 32 33 33 34 34
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives	25 25 26 26 26 32 33 33 34 34 36
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule)	25 25 26 26 26 32 33 33 34 34 36 36
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives	25 25 26 26 26 32 33 33 34 34 34 36 42
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives  Controlling logging (HttpLogModule)	25 25 26 26 26 32 33 33 34 34 34 36 42 42
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives  Controlling logging (HttpLogModule) Explaining directives	25 25 26 26 26 32 33 34 34 34 36 42 42 43
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives  Controlling logging (HttpLogModule) Explaining directives  Setting response headers (HttpHeadersModule)	25 25 26 26 26 32 33 34 34 36 36 42 42 43 44
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives  Controlling logging (HttpLogModule) Explaining directives  Setting response headers (HttpHeadersModule) Explaining directives	25 25 26 26 26 32 33 33 34 34 36 36 42 42 43 44 45
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives  server  server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule)  Explaining directives  Load balancing (HttpUpstreamModule)  Explaining directives  Acting as a proxy (HttpProxyModule)  Explaining directives  Compressing content (HttpGzipModule)  Explaining directives  Controlling logging (HttpLogModule)  Explaining directives  Setting response headers (HttpHeadersModule)  Explaining directives  Rewriting requests (HttpRewriteModule)	25 25 26 26 26 32 33 33 34 34 42 42 42 43 44 45 45
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives server server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule) Explaining directives  Load balancing (HttpUpstreamModule) Explaining directives  Acting as a proxy (HttpProxyModule) Explaining directives  Compressing content (HttpGzipModule) Explaining directives  Controlling logging (HttpLogModule) Explaining directives  Setting response headers (HttpHeadersModule) Explaining directives  Rewriting requests (HttpRewriteModule) Explaining directives	25 25 26 26 26 32 33 33 34 34 34 42 42 43 44 45 45
Standard HTTP modules  The core module (HttpCoreModule)  Explaining directives  server  server_name  Controlling access (HttpAccessModule)  Authenticating users (HttpBasicAuthModule)  Explaining directives  Load balancing (HttpUpstreamModule)  Explaining directives  Acting as a proxy (HttpProxyModule)  Explaining directives  Compressing content (HttpGzipModule)  Explaining directives  Controlling logging (HttpLogModule)  Explaining directives  Setting response headers (HttpHeadersModule)  Explaining directives  Rewriting requests (HttpRewriteModule)	25 25 26 26 26 32 33 33 34 34 42 42 42 43 44 45 45

#### eBooks-IT.org

Table of	Contents
Explaining directives	51
Limiting requests (HttpLimitReqModule)	52
Explaining directives	52
Limiting connections (HttpLimitConnModule) Explaining directives	53 54
Summary	55
Chapter 4: Installing Third-party Modules	57
Compiling third-party modules	57
Communicating with PostgreSQL (ngx_postgres) Explaining directives	58 58
Communicating with MySQL and drizzle (drizzle-nginx) Explaining directives	61 61
Digest Authentication (ngx_http_auth_digest) Explaining directives	64 64
Speeding up web pages (ngx_pagespeed)	66
Configuring handlers Lua scripting (ngx_lua)	67 <b>68</b>
Explaining directives	71
Reverse IP lookup using the GeoIP module (ngx_http_geoip_module)  Explaining directives	76 76
Doing healthchecks	78
ngx_http_healthcheck_module	78 70
Explaining directives Load balancing	79 81
Summary	82
Chapter 5: Creating Your Own Module	83
Nginx module delegation	83
Handlers	84
Load balancers	84
Filters	84
Order of execution	84
The extended "Hello world" module	85
Writing and compiling a module	85
The "Hello world" source code	86
Components of the Nginx module  Module configuration structures	90 90
Module directives	91
The module context	94
The module definition	98
The handler function	100
Nginx Development Toolkit (NDK)	104 105
Summary	
Index	107

#### **Preface**

This book is for advanced users such as system administrators and developers who want to extend Nginx's functionality using its highly flexible add-on system. We look at the existing modules available and how to compile and install them, along with practical examples of how to configure them with focus on optimizing the configuration. It also goes beyond what is available off the shelf and teaches you how to write your own module, in case something is not available from the big Nginx open source community.

#### What this book covers

Chapter 1, Installing Nginx Core and Modules from Source, serves as a quick reference for downloading and installing Nginx and compilation options related to different modules and add-ons.

Chapter 2, Configuring Core Modules, is a reference to the core modules in Nginx, which cannot be disabled, and explores different configuration options for them.

Chapter 3, Installing and Configuring HTTP Modules, is a reference to the standard and optional HTTP modules, their synopsis, directives as well as practical configuration examples.

Chapter 4, Installing Third-party Modules, introduces third-party modules, mostly available on GitHub. It talks about some well-known third-party modules, their installation and configuration, and also some guidelines on how to find different third-party modules out there.

Chapter 5, Creating Your Own Module, gives a brief introduction to creating your own modules. This chapter is a quick reference to the module system in Nginx. It also has a quick reference to the internal architecture of Nginx, which makes extension possible.

#### What you need for this book

This book will help you understand the module-based architecture of Nginx. You will learn to install Nginx as well as extend it with several available modules. This book specially touches on the topic of creating your own Nginx modules. Most people have to read heaps of code to get this done. This book will make it easier for advanced users who are looking to extend Nginx by not only using existing modules, but also writing something of their own.

#### Who this book is for

This book is intended for advanced users, system administrators, and developers of Nginx modules.

#### **Conventions**

In this book, you will find a number of styles of text that distinguish between different kinds of information. Here are some examples of these styles, and an explanation of their meaning.

Code words in text, database table names, folder names, filenames, file extensions, pathnames, dummy URLs, user input, and Twitter handles are shown as follows: "You can reload the Nginx configuration once you edit the nginx.conf file."

A block of code is set as follows:

```
[nginx]
name=nginx repo
baseurl=http://nginx.org/packages/centos/$releasever/
    $basearch/
gpgcheck=0
enabled=1
```


When we wish to draw your attention to a particular part of a code block, the relevant lines or items are set in bold:

```
ngx_uint_t spare0;
ngx_uint_t spare1;
ngx_uint_t spare2;
ngx_uint_t spare3;
ngx_uint_t version;
void *ctx;
```

Any command-line input or output is written as follows:

- # cd /usr/ports/www/nginx
- # make install clean

**New terms** and **important words** are shown in bold. Words that you see on the screen, in menus or dialog boxes, for example, appear in the text like this: "For example, according to the following configuration, this module will make sure that it prints **Hello World**."



#### Reader feedback

Feedback from our readers is always welcome. Let us know what you think about this book — what you liked or may have disliked. Reader feedback is important for us to develop titles that you really get the most out of.

To send us general feedback, simply send an e-mail to feedback@packtpub.com, and mention the book title via the subject of your message.

If there is a topic that you have expertise in and you are interested in either writing or contributing to a book, see our author guide on www.packtpub.com/authors.

#### **Customer support**

Now that you are the proud owner of a Packt book, we have a number of things to help you to get the most from your purchase.

Preface

#### **Errata**

Although we have taken every care to ensure the accuracy of our content, mistakes do happen. If you find a mistake in one of our books—maybe a mistake in the text or the code—we would be grateful if you would report this to us. By doing so, you can save other readers from frustration and help us improve subsequent versions of this book. If you find any errata, please report them by visiting http://www.packtpub.com/submit-errata, selecting your book, clicking on the errata submission form link, and entering the details of your errata. Once your errata are verified, your submission will be accepted and the errata will be uploaded on our website, or added to any list of existing errata, under the Errata section of that title. Any existing errata can be viewed by selecting your title from http://www.packtpub.com/support.

#### **Piracy**

Piracy of copyright material on the Internet is an ongoing problem across all media. At Packt, we take the protection of our copyright and licenses very seriously. If you come across any illegal copies of our works, in any form, on the Internet, please provide us with the location address or website name immediately so that we can pursue a remedy.

Please contact us at copyright@packtpub.com with a link to the suspected pirated material.

We appreciate your help in protecting our authors, and our ability to bring you valuable content.

#### **Questions**

You can contact us at questions@packtpub.com if you are having a problem with any aspect of the book, and we will do our best to address it.

# Installing Nginx Core and Modules from Source

This chapter serves as a quick reference to downloading and installing Nginx using binary and source distribution and compilation options related to different modules and add-ons.

If you are reading this book, you are already familiar with Nginx (pronounced as engine-x). Therefore, we will not spend too much time discussing the basics. However, you will need a working copy of Nginx before proceeding to advanced topics.

#### Installing binary distribution

Most UNIX and Linux distributions have Nginx included in their package manager repositories. Use package manager commands on your platform to install it. For example, use **apt-get** on Ubuntu or Debian, and **emerge** on Gentoo. For Red Hat, Fedora, or CentOS, see the instructions that follow.

You can find binary installation instructions for different platforms such as Red Hat and Ubuntu on the Nginx installation wiki at http://wiki.nginx.org/Install. However, we will briefly describe the process here, quoting from the wiki.

#### Red Hat, Fedora, and CentOS

To add the Nginx yum repository, create a file named /etc/yum.repos.d/nginx.repo and paste one of the following configurations:

#### • For CentOS:

```
[nginx]
name=nginx repo
baseurl=http://nginx.org/packages/centos/$releasever/
    $basearch/
gpgcheck=0
enabled=1
```

#### For RHEL:

```
[nginx]
name=nginx repo
baseurl=http://nginx.org/packages/rhel/$releasever/
    $basearch/
gpgcheck=0
enabled=1
```

CentOS, RHEL, and Scientific Linux, each populate the \$releasever variable differently. Therefore, depending on your OS version, replace \$releasever with 5 (for 5.x) or 6 (for 6.x). Therefore, baseurl for 6.x would look like baseurl=http://nginx.org/packages/rhel/6/\$basearch/.

#### Official Debian/Ubuntu packages

Append the following lines to the /etc/apt/sources.list file, and replace the codename with the one appropriate for the release that you are using, for example, Ubuntu 13.10 is codenamed saucy:

#### • For Ubuntu 12.10:

```
deb http://nginx.org/packages/ubuntu/ saucy nginx
deb-src http://nginx.org/packages/ubuntu/ saucy nginx
```

Please note that when you will run the apt-get update after adding the repository, you will get a **GPG** error of not being able to verify keys. If this happens and you find it hard to ignore it, do the following:

```
wget http://nginx.org/packages/keys/nginx_signing.key
cat nginx signing.key | sudo apt-key add -
```

• For Debian 6:

```
deb http://nginx.org/packages/debian/ squeeze nginx
deb-src http://nginx.org/packages/debian/ squeeze nginx
```

- **For Ubuntu PPA**: This PPA is maintained by volunteers and is not distributed by nginx.org. It has some additional compiled-in modules, and it may be more fitting for your environment. You can get the latest stable version of Nginx from **Nginx PPA** on Launchpad: You will require root privileges to execute the following commands.
  - ° For Ubuntu 10.04 and newer:

```
sudo -s
nginx=stable # use nginx=development for latest
development version
add-apt-repository ppa:nginx/$nginx
apt-get update
apt-get install nginx
```

If you get an error about add-apt-repository not existing, you will want to install python-software-properties. For other Debian/Ubuntu based distributions, you can try the lucid variant of the PPA that is the most likely to work on older package sets.

```
sudo -s
nginx=stable # use nginx=development for latest development
  version
echo "deb http://ppa.launchpad.net/nginx/$nginx/ubuntu lucid
  main" > /etc/apt/sources.list.d/nginx-$nginx-lucid.list
apt-key adv --keyserver keyserver.ubuntu.com --recv-keys
  C300EE8C
apt-get update
apt-get install nginx
```

#### **FreeBSD**

Update the BSD ports tree using the following command:

```
# portsnap fetch update
```

Install the web server using the following commands:

```
# cd /usr/ports/www/nginx
# make install clean
```

```
Installing Nginx Core and Modules from Source
```

Type the following command to turn the Nginx server on:

```
echo 'nginx_enable="YES"' >> /etc/rc.conf
To start Nginx, enter:
# /usr/local/etc/rc.d/nginx start
```

#### **OpenBSD**

OpenBSD, as of Version 5.1, includes Nginx as part of the base system. This means Nginx comes pre-installed along with all the library dependencies. The version is not always the latest and greatest one. However, this allows you to start migrating Apache applications over to Nginx. In the future, it is expected that the default httpd will be Nginx instead of Apache.

#### Official Win32 binaries

As of Version 0.8.50 of Nginx, the official Windows binary is now available.

The Windows version is provided as binary-only due to the current build process, which uses WineTools at the moment. You will not be able to compile a Windows version from source. Once you download the Windows ZIP file, perform the following steps:

#### 1. Installation:

```
cd c:\
unzip nginx-1.2.3.zip
ren nginx-1.2.3 nginx
cd nginx
start nginx

2. Control:
nginx -s [ stop | quit | reopen | reload ]
```

For problems, look in the c:\nginx\logs\error.log file or in EventLog.

#### Installing source distribution

Nginx binary packages are outdated and usually have an older version. If the binaries on your platform are not the latest and up-to-date, you can download the source from http://nginx.org/en/download.html. At the time of writing this chapter, Version 1.4.3 is the stable downloadable version.

You can also checkout or clone the latest source.

Read-only Subversion repositories:

code: svn://svn.nginx.org/nginx

Read-only Mercurial repositories:

site: http://hg.nginx.org/nginx.org

After you have downloaded the source archive, un-tar it and use the following standard build commands to build a standard binary:

./configure

make

sudo make install

This places the Nginx binary under user/local. However, you can override this path through configure options.

#### **Nginx library dependencies**

If you want to build Nginx from source, the following libraries are needed at the minimum:

- GCC
- Autotools (automake and autoconf)
- PCRE (Perl Compatible Regular Expressions)
- zlib
- OpenSSL

You also have the option to disable the dependency on PCRE, zlib, and OpenSSL by disabling the compilation of rewrite, gzip, and ssl modules. These modules are enabled by default.

#### **Configuring options**

Compile-time options are provided through configure. You can also find documentation related to the configure-time options online at http://wiki.nginx.org/InstallOptions.

The configure command defines various aspects of the system including the methods that Nginx is allowed to use for connection processing. At the end, it creates a makefile. You can use ./configure --help to see a full list of options supported by the configure command.

The following section is extracted from the Nginx online wiki.

#### Files and permissions

- --prefix=path: It is set to the /usr/local/nginx directory by default.
  The path specified here is the root folder for keeping the server files.
  This includes the executable files, server log files, configuration files, and html documentation.
- --sbin-path=path: The default Nginx executable name is /sbin/nginx. You can change the name using this configure option.
- --conf-path=path: The default for this option is prefix/conf/nginx.conf. This is the default path for the Nginx configuration file. This file, as you will learn later, is used to configure everything about the Nginx server. The path also contains a number of other configuration files such as a sample fastcgi configuration file and character-set maps. You can always change this path later on in the configuration file.
- --pid-path=path: This option allows you to change the name of the pid file. The pid files are used by various utilities (including start/stop scripts) to determine if the server is running. Normally, it is a plain text file with the server process ID in it. By default, the file is named prefix/logs/nginx.pid.
- --error-log-path=path: This option allows you to specify the location of
  the error log. By default, the file is named prefix/logs/error.log. You can
  set this value to stderr. It will redirect all the error messages to the standard
  error on your system. Normally, this will be your console or the screen.
- --http-log-path=path: This sets the name of the log file where all HTTP requests are logged. By default, the file is named prefix/logs/access.log.
  Like other options, this can be changed anytime by providing the access\_log directive in the configuration file.
- --user=USER: This sets the username that will be used to run the Nginx worker processes. You should make sure that this is an unprivileged or non-root user. The default user name is nobody. You can change it later through the user directive in the configuration file.
- --group=name: This sets the name of the group used to run the worker processes. The default group name is nobody. You can change this through the user directive in the configuration file.

#### The Event loop

One of the reasons for Nginx being so fast and stable is its ability to use event-based functions. Input/Output. The event-based coding ensures maximum performance within a single core by allowing it to be non-blocking. However, event-based code needs the underlying platform support such as kqueue (FreeBSD, NetBSD, OpenBSD, and OSX), epoll (Linux), and /dev/poll (Solaris, HPUX).In cases where these methods are not available, Nginx can work with more traditional select() and poll() methods as well. The following options affect this behavior:

- --with-select module
- --without-select module

These enable or disable building of a module that allows the server to work with the select() method. This module is built automatically if the platform does not appear to support more appropriate methods such as kqueue, epoll, rtsig, or /dev/poll.

- --with-poll module
- --without-poll module

These enable or disable the building of a module that allows the server to work with the poll() method. This module is built automatically if the platform does not appear to support more appropriate methods such as kqueue, epoll, rtsig, or / dev/poll.

#### **Optional modules**

The optional modules are as follows:

- --without-http\_gzip\_module: This option allows you to disable over-the-wire compression. This can be quite useful if you are sending or receiving large text documents over HTTP. However, if you don't want to build this compression into Nginx binary, or you don't have access to the zlib library that is required to enable this support, you can disable it using this option.
- --without-http\_rewrite\_module: This option allows you to disable the HTTP rewrite module. The HTTP rewrite module allows you to redirect HTTP requests by modifying URIs that match a given pattern. You need the PCRE library to enable this module.
- --without-http\_proxy\_module: This disables ngx\_http\_proxy\_module.
   The proxy module allows you to pass the HTTP request to another server.
- --with-http\_ssl\_module: This enables the SSL support in the server.
   This is not enabled by default and you need OpenSSL in order to build SSL support in the Nginx binary.

- --with-pcre=path: If you have downloaded the PCRE source on your machine, you can provide its path through this parameter. Nginx will automatically build this library before building the Nginx server. Please make sure that the version of PCRE source is 4.4 or higher.
- --with-pcre-jit: This builds the PCRE library with the "just-in-time compilation" support. This is significantly to improve the pattern matching or rewriting speed by converting the regular expressions into machine code.
- --with-zlib=path: If you have already downloaded the zlib library source, you can provide its path here. Nginx will build the zlib library before building the server binary. Please make sure that the source version is 1.1.3 or higher.

#### **Compilation controls**

The compilation controls are as follows:

- --with-cc-opt=parameters: Additional options for the CFLAGS variable
- --with-ld-opt=parameters: Additional parameters for the linker (LD\_ LIBRAY\_PATH) that you should provide --with-ld-opt="-L /usr/local/ lib when building on FreeBSD

#### **Example**

Example of parameters usage (all of this needs to be typed in one line):

```
./configure
```

```
--sbin-path=/usr/local/nginx/nginx

--conf-path=/usr/local/nginx/nginx.conf

--pid-path=/usr/local/nginx/nginx.pid

--with-http_ssl_module

--with-pcre=../pcre-4.4

--with-zlib=../zlib-1.1.3
```

When using the system PCRE library under FreeBSD, the following options should be specified:



- --with-ld-opt="-L /usr/local/lib" \
- --with-cc-opt="-I /usr/local/include"

If the number of files supported by  ${\tt select}()$  needs to be increased, it can also be specified like this:

• --with-cc-opt="-D FD\_SETSIZE=2048"

#### The Custom module

One of the great strengths of Nginx is its modular design. You are able to hook in third-party modules or modules that you write yourself.

--add-module=path compiles the module located at path into Nginx binary. You can find a list of third-party modules available for Nginx at http://wiki.nginx.org/3rdPartyModules.

#### **Debugging**

--with-debug enables debug logging. This option is already enabled in the Windows binary. Once you compile Nginx with this option, you then have to set the debug level with the error\_log directive in the configuration file, and so on:

```
error_log /path/to/log debug
```

In addition to debug logging, you can also attach a debugger to a running version of Nginx. If you intend to do so, enable the debugging symbols in the Nginx binary. Compile with -g or -ggdb and recommended compiler optimization level of 00 or 02 (this makes the debugger output easier to understand). The optimization level 03 auto-vectorizes the code and introduces certain other optimizations that make debugging harder. Set the CFLAGS environment variable as follows and run configure:

CFLAGS="-g -00" ./configure ...

#### Installing on other platforms

Let us install Nginx on other platforms such as the following:

- Gentoo: To get the latest version of Nginx, add a platform mask in your portage configuration file /etc/portage/package.keywords
  - www-servers/nginx ~x86 (or ~amd64, etc)
- X86/64 builds for Solaris are available on http://joyent.com/blog/ok-nginx-is-cool
- MacOSX: Install Xcode or Xcode command-line tools to get all the required compilers and libraries
- A detailed account of how to resolve dependencies like PCRE and others is described in detail for Solaris 10 u5 http://wiki.nginx.org/Installing\_ on\_Solaris\_10\_u5

#### **Verifying your Nginx installation**

Following are the steps to verify that Nginx has been installed:

- 1. Once you have successfully compiled and built Nginx, verify it by running the nginx -v command.
- 2. As a root user, run the Nginx server using prefix/ nginx/sbin/nginx.
- 3. You will see the nginx.pid file once the server is running. The location of this file depends on the option that you provided while running the configure script. On Ubuntu, the default location is /var/run/nginx.pid.

You can reload the Nginx configuration once you edit the nginx.conf file. To do this, send SIGNUP to the main process. The PID of this process is in the nginx.pid file. The following command will reload the configuration on Ubuntu:

kill -HUP `cat var/run/nginx.pid

#### **Summary**

In this chapter, we learned how to download binary and source releases of Nginx and install binary releases. We have also learned how to compile and install Nginx from source, how to override installation paths and other properties using configure options, how to compile Nginx with debugging symbols, and finally, how to verify the installation.

In the next chapter, we will learn more about configuration of core Nginx modules.

# 2 Configuring Core Modules

In this chapter we will explore the configuration of the Main and Events modules of Nginx, which are also called the core modules. We will discuss the module-related configuration options and important points that one needs to remember while using these options.

#### **Understanding the Main module**

The Nginx Main module consists of the following configuration directives or commands:

Name	Value	Default	Example
daemon	on, off	on	
master_process	on, off	on	
timer_resolution	interval	0	100ms
pid	file	logs/nginx.pid	/var/log/nginx.pid
lock_file	file	logs/nginx.lock	/var/log/nginx.lock
worker_processes	number, auto	1	2
debug_points	stop, abort	null	stop
user	user [group]	nobody nobody	www users
worker_priority	number	0	15
worker_cpu_affinity	cpu mask		0101 1010
worker_rlimit_nofile	number		1000
worker_rlimit_core	size		500M
worker_rlimit_sigpending	number		1000
working_directory	directory	compile time	/usr/local/nginx
env	variable = value		PERL5LIB=/data/ site/modules

#### **Explaining directives**

We will now discuss all the Main module's directives mentioned in the preceding table in detail.

#### daemon

The daemon directive determines if Nginx will run in the daemon mode. A daemon (or a service) is a background process that is designed to run autonomously, with little or no user intervention. Since Version 1.0.9 of Nginx, it is safe to run Nginx with this option turned off. It is not possible to do a binary upgrade of Nginx without stopping it, if this option is off.

Nginx's master process is responsible for nonstop binary upgrades. The signal that is used for this purpose is SIGUSR2. However, when the daemon mode is off, this signal is ignored because the master process will still have the old binary. This is unlike the daemon mode, where the parent of the new worker process is switched to the Init process, and therefore, you can start a new worker process with new binaries. The only reason you might want to run the daemon mode with master\_process off would be for debugging purposes. Turning these options off will run Nginx in the foreground without a master process, and you can terminate it simply by pressing Ctrl + R. However, you should not run Nginx in production without the daemon mode and master process.

#### master process

The master\_process directive determines if Nginx will run with a master process. It has many responsibilities in Nginx, including spawning off worker processes. Nginx will run in the single-process mode if you set master\_process off. You should always run in production with the master\_process option turned on. The only reason you might want to turn master\_process off is for debugging reasons, as it might be much simpler to debug the code in a single-process mode.

#### timer\_resolution

Setting the timer\_resolution directive will reduce the number of gettimeofday() system calls. Instead of doing this system call for each kernel event, gettimeofday() is only called once per specified interval. You might want to turn this option off if gettimeofday() shows up as an overhead on a busy server. You won't notice any difference on an idle server though. One good reason to use timer\_resolution is to get the exact time in logs for the upstream response times.

#### pid

The pid directive specifies the filename for the PID file of the master process. The default value is relative to the --prefix configure option.

#### lock file

The <code>lock\_file</code> directive specifies the filename of the lock file. The default value is relative to the <code>--prefix</code> configure option. You can also specify this option during the compile time through the following configure script:

```
./configure --lock-path=/var/log/nginx.lock
```

#### worker\_processes

The worker\_processes directive defines the maximum number of worker processes. A worker process is a single-threaded process spawned by the master process. If you set this option to auto, Nginx will automatically try to determine the number of CPUs/core and set this option equal to that number. The auto parameter is supported starting from Versions 1.3.8 and 1.2.5. If you want Nginx to only use a limited number of cores on your server, setting this value explicitly would be a good idea.

#### debug\_points

The debug\_points directive is useful to debug Nginx. If you set this directive to abort, Nginx will produce a core dump file whenever there is an internal error. You can use this core dump file to obtain an error trace in a system debugger such as gdb. In order to obtain the core dump file, you will also need to configure the working rlimit core and working directory directives.

If this directive is set to stop, any internal error will lead to the stopping of the process.

#### user

The user directive is used to specify the user and the group of the worker processes. If no group name is specified, the same group name as that of the user is used. You can override the default nobody nobody by specifying the user and the group with the following configure script:

```
./configure --user=www --group=users
```

#### worker\_priority

The worker\_priority directive allows you to set the nice priority of the worker processes. Nginx will use the setpriority() system call to set the priority. Setting the priority to a lower value can result in favorable scheduling of the worker processes.

The actual priority range varies between kernel versions. Before 1.3.36, Linux had a range from –infinity to 15. Since kernel 1.3.43, Linux has the range from -20 to 19. On some systems, the range of nice values is from -20 to 20.

#### worker\_cpu\_affinity

The worker\_cpu\_affinity directive allows you to set the affinity masks for the worker processes. Affinity masks are bit masks, which can bind a process to a certain CPU. This can lead to better performance on some systems such as Windows, where several system processes are restricted to the first CPU/core. Therefore, excluding the first CPU/core can lead to better performance. We can bind each worker process to a different CPU with the following code snippet:

```
worker_processes 4;
worker_cpu_affinity 0001 0010 0100 1000;
```

You can set the CPU affinity value to up to 64 CPU/core.

#### worker\_rlimit\_nofile

The worker\_rlimit\_nofile directive sets the maximum limit on open files (RLIMIT\_NOFILE) that a worker process can use. When this directive is set, the setrlimit() system call is used to set the resource limit. Any attempt to exceed this limit will result in an error EFILE (signifying too many open files).

#### worker\_rlimit\_core

The worker\_rlimit\_core directive sets the maximum size of the core dump file created by a worker process. When this option is set, the setrlimit() system call is used to set the resource limit of the file size. When this option is 0, no core dump files are created.

#### worker rlimit sigpending

The worker\_rlimit\_sigpending directive specifies the limit on the number of signals that may be queued for the real user ID of the calling process. If you are using a Linux kernel version newer than 2.6.6, it will support real-time signals (rtsig), and each process will have its own queue as opposed to a system-wide queue in the earlier implementations. When this option is set, a setrlimit() system call is used

to set the resource limit RLIMIT\_SIGPENDING. In order to enforce this limit, both standard and real-time signals are counted.

#### working\_directory

The working\_directory directive specifies the path where the core dump files are created. This path should be an absolute path. You must make sure that the user or group specified via the user option has a write permission in this folder.

#### env

The env directive allows you to set some environment variables, which will be inherited by the worker processes. If you set some environment variables on a shell, they will be erased by Nginx, except TZ. This directive allows you to preserve some of the inherited variables, change their values, or create new environment variables. The environment variable NGINX is used internally by the server and should not be set by the user.

If you specify an environment variable's name without specifying its value, the value from the parent process, that is, the shell will be retained by Nginx. But if you specify a value as well, this new value will be used by the server.

```
env MALLOC_OPTIONS;
env PERL5LIB=/data/site/modules;
env OPENSSL ALLOW PROXY CERTS=1;
```

In the preceding code snippet, the value of the environment variable MALLOC\_OPTIONS is retained from the parent process, while the other two environment variables are defined or redefined and any value set by the parent process is wiped off.

#### **Understanding the Events module**

The Events module deals with the configuration of epoll, kqueue, select, poll, and more. This module consists of the following directives:

Name	Value	Default	Example
accept_mutex	on, off	on	off
accept_mutex_delay	interval (ms)	500ms	500ms
debug_connection	ip, cidr	none	192.168.1.1
devpoll_changes	number	32	64
devpoll_events	number	32	64
kqueue_changes	number	512	512

Configuring Core Modules

Name	Value	Default	Example
kqueue_events	number	512	512
epoll_events	number	512	512
multi_accept	on, off	off	on
rtsig_signo	signal number	SIGRTMIN+10	
rtsig_overflow_events	number	16	24
rtsig_overflow_test	number	32	40
rtsig_overflow_threshold	number	10	3
use	Kqueue, rtsig, epoll, /dev/poll, select	decided by the configure script	rtsig
worker_connections	number	512	200

#### **Explaining directives**

We will now discuss the Events module's directives summarized in the preceding table, in detail.

#### accept\_mutex

The accept\_mutex directive tries to prevent workers from competing over accept () for listing sockets (in the kernel). In other words, without accept\_mutex, workers may try to simultaneously check for new events on sockets, which may lead to a slight increase in the CPU usage. Depending on your OS and the event-notification mechanisms, the results may vary. If you are using rtsig as the signal-processing mechanism, this option needs to be enabled.

#### accept\_mutex\_delay

As enabling accept\_mutex serializes the accept () call from worker processes, that is, one worker process does one accept at a time, the accept\_mutex\_delay directive determines how long the other worker processes will wait before they are ready to accept new connections while another process is already doing it.

#### debug\_connection

In order to use the <code>debug\_connection</code> directive, Nginx needs to be built with the <code>--debug-enabled</code> option while running the configure script. You can specify the IPv4 or IPv6 address of the clients for which the debugging log will be enabled. You can also provide a domain name or unix: for Unix domain socket connections. The log level for the rest of the clients is determined through the <code>error\_log</code> option. The

debug log is written to the logfile specified in the error\_log option as defined in the following code snippet:

```
error_log /var/log/nginx-error.log;
events {
    debug_connection 127.0.0.1;
    debug_connection localhost;
    debug_connection 192.0.2.0/24;
    debug_connection ::1;
    debug_connection 2001:0db8::/32;
    debug_connection unix:;
    ...
}
```

#### devpoll\_changes and devpoll\_events

The /dev/poll directive is an efficient method used in Solaris 7 11/99+, HP/UX 11.22+ (eventport), IRIX 6.5.15+, and Tru64 UNIX 5.1A+. The devpoll\_changes and devpoll\_events parameters define the number of changes and events that can move to and from the kernel. Nginx only writes the devpoll\_changes or devpoll\_events number of events and changes to /dev/poll at a time while processing events.

#### kqueue\_changes and kqueue\_events

The kqueue directive is an efficient event-notification interface used in FreeBSD 4.1+, OpenBSD 2.9+, NetBSD 2.0, and Mac OS X. It provides efficient input and output event pipelines between the kernel and user processes. It is possible to receive pending events while using only a single system call kevent (). This contrasts with older traditional polling system calls such as poll and select, which are less efficient, especially while polling for events on a large number of file descriptors. Other advanced event mechanisms such as /dev/poll and epoll allow you to do the same.

These parameters control how many changes and events are passed at a time to the kevent () system call.

#### epoll\_events

The epoll\_events directive is an efficient event-notification method used in Linux 2.6+. There are patches present to port this functionality to older kernels as well. This parameter determines the buffer size where the events are returned at a time before they are processed.

#### multi\_accept

The worker process will try to accept all or as many incoming connections as possible when the multi\_accept directive is enabled. Turning this option off will result in worker processes only accepting one connection at a time. This option is ignored if the kqueue\_events notification method is used. If you use the rtsig method, this option is automatically enabled. By default, this option is turned off. It can be a high-performance tweak; however, the bad thing with multi\_accept is that if you have a constant stream of incoming connections at a high rate, it may overflow your worker\_connections directive without any chance of processing the already-accepted connections.

#### rtsig\_signo

Linux supports 32 real-time signals, numbered from 32 (SIGRTMIN) to 63 (SIGRTMAX). Programs should always refer to real-time signals using the notation SIGRTMIN+n, since the range of real-time signal numbers varies across \*nix platforms. Nginx uses two signals when the rtsig method is used. The directive specifies the first signal number. The second signal number is one more than the first signal number. By default, rtsig\_signo is SIGRTMIN+10 (42), and the second signal number in this case would be 43.

# rtsig\_overflow\_events, rtsig\_overflow\_test, and rtsig\_overflow\_threshold

The rtsig\_overflow\_events, rtsig\_overflow\_test, and rtsig\_overflow\_threshold directives define how the queue overflow is handled while using real-time signals. When overflow occurs, Nginx flushes the rtsig queue, then handles the switching of events between poll() and rtsig poll(), and handles all the unhandled events consecutively, while rtsig periodically drains the queues to prevent a new overflow. When the overflow is handled completely, Nginx switches to the rtsig method again.

The rtsig\_overflow\_events directive specifies the number of events to be passed via poll().

The rtsig\_overflow\_test directive specifies the number of events handled by poll(), after which, Nginx will drain the rtsig queue.

The rtsig\_overflow\_threshold directive works in Linux 2.4.x only. Before draining the rtsig queue, Nginx looks at the extent to which the queue has been filled up. The default is 1/10. rtsig overflow threshold 3 means a value of 1/3.

#### use

The use directive specifies the event-notification method that should be used (kqueue, epoll, and more). This is useful for platforms where multiple options are available. During the configuration time, the best method for event notification is selected automatically, so in most cases, you don't need to set this directive.

#### worker\_connections

The worker\_connections directive specifies the maximum number of simultaneous connections that can be opened by a worker process.

It should be kept in mind that this number includes all the connections and not just the client connections. Another consideration is that the actual number of simultaneous connections should not exceed the current limit on the maximum number of open files that can be changed by worker rlimit nofile.

#### **Summary**

In this chapter, we have looked at the configuration details of the two core modules of Nginx, that is, the Main and Events modules. These modules can't be opted out of, and you can't disable them. So, we went through each option and the suitable situations to use them.

In the next chapter, we will look at installing and configuring HTTP modules and the configuration options related to those modules.

# 3 Installing and Configuring HTTP Modules

In this chapter, we will explore the installation and configuration of standard HTTP modules. Standard HTTP modules are built into Nginx by default unless you disable them while running the configure script. The optional HTTP modules are only installed if you specify them explicitly while running configure. These modules deal with functionalities such as SSL, HTTP authentication, HTTP proxy, gzip compression, and many others. We will look at some optional HTTP modules in the next chapter.

All the configuration directives we have talked about so far and the ones that we will be discussing in this and the remaining chapters are specified in the nginx.conf file. The default location of this file is /usr/local/conf/nginx.conf.

#### **Standard HTTP modules**

As mentioned earlier, standard HTTP modules are built into Nginx by default unless you explicitly disable them. As the name suggests, these modules provide standard HTTP functionality to the web server. We will now have a look at some of the important standard HTTP modules.

#### The core module (HttpCoreModule)

The core module deals with the core HTTP features. This includes the protocol version, HTTP keepalive, location (different configurations based on URI), documents' roots, and so on. There are over 74 configuration directives and over 30 environment variables related to the HTTP Core module. We will discuss the most important ones briefly.

# **Explaining directives**

The following is an explanation of some of the key core module directives. This list is not exhaustive, and you can find the full list at http://wiki.nginx.org/HttpCoreModule.

#### server

The server directive defines the server context. It is defined as a server {...} block in the configuration file. Each server block refers to a virtual server. You have to specify a listen directive inside a server block to define the host IP and the port for this virtual server. Alternatively, you can specify a server\_name directive to define all the hostnames of this virtual server.

```
server {
   server_name www.acme.com *.acme.com www.acme.org;
   ...
}
server {
   listen myserver.com:8001;
   ...
}
```

### server name

The server\_name directive defines the name of the virtual server. It can contain a list of hostnames, and the first one becomes the default name of the server. The hostnames can be exact string literals, wildcards, regular expressions, or a combination of all of these. You can also define an empty hostname as "". This allows the processing of requests when the host HTTP header is empty.

The wildcard name can only use the asterisk (\*) on the dot border and at the beginning or ending of the name. For example, \*.example.com is a valid name; however, ac\*e.example.com is an invalid name.

The regular expression server name can be any PCRE-compatible regular expression that must start with ~.

```
server name ~^www\d+\.acme\.org$
```

If you specify the environment variable \$hostname in this directive, the hostname of the machine is used.

#### listen

The listen directive specifies the listen address of the server. The listen address can be a combination of an IP address and a port, hostname and port, or just a port.

```
server {
  listen 8001
  server_name www.acme.com *.acme.com www.acme.org
  ...
}
```

If no port is specified in the listen directive, the port 80 is used by default if the Nginx server is running as a superuser, otherwise the port 8000 is used.

Nginx can also listen on a UNIX socket using the following syntax:

```
listen unix:/var/lock/nginx
```

IPv6 addresses can be specified using the [] brackets:

```
listen [::]:80
listen [2001:db8::1]
```

Specifying an IPv6 address can enable the IPv4 address as well. In the first of the preceding examples, when you enable the [::]:80 address, binding port 80 using IPv6 in the listen directive, the IPv4 port 80 is also enabled by default in Linux.

The listen directive accepts several parameters as well; a couple of important ones are stated in the following paragraphs.

### SSL

The listen parameter allows you to specify that the connection accepted on this listen address will work in the SSL mode.

# default\_server

The default\_server parameter sets the listen address as the default location. If none of the listen addresses have a default specification, the first listen declaration becomes the default. For an HTTP request, Nginx tests the request's header field, Host, to determine which server the request should be routed. If its value does not match any server name or the request does not contain this header field at all, Nginx will route the request to the default server.

```
listen 8001
listen 443 default server ssl
```

The ssl option specifies that all connections on this address should work with SSL. The ssl option will only work if the server was compiled using SSL support.

There are other parameters of the listen directive that correspond to the listen and bind system calls. For example, you can modify the send and receive buffers of the listening socket by providing the rcvbuf and sndbuf parameters. You can read about them in more detail in the official documentation at http://nginx.org/en/docs/http/ngx http core module.html.

### **location**

The location directive is a server context configuration. There can be several location configuration blocks inside the server block, each referring to a unique URI within that server. It is one of the most important and widely used directives, which allows you to specify a configuration based on a URI. A location matching the user request URI will result in that specific configuration block to be the handler of user request. You have a lot of flexibility in how you want to specify the configuration. This can be a string literal or a regular expression. The regular expressions can be used to do a case-sensitive (prefixed with ~) or a case-insensitive comparison (prefixed with ~\*). You can also disable the regular expression matching by prefixing the string with ^~.

The order of matching is as follows:

- 1. First, string literals with = are evaluated, and the searching stops on a match.
- 2. Remaining strings are matched; a match encountering ^~ also stops the search. Among all the non-regular-expression strings, the one with the longest matched prefix is chosen.
- 3. Regular expressions are searched in the order in which they appear in the nginx.conf file.
- 4. In case there are two matches, one from a regular expression and one from a string, the string is used.

```
location = / matches only /
location / matches any URI
location ~/index matches a lower case /index as a subsring in any
   position
```

It does not matter in which order the configurations are defined. They will always be evaluated in the order mentioned previously.

```
location ^~/index/main.jpg
location ~^/index/.*\.jpg$
```

In the example, a URI such as /index/main.jpg will select the first rule even though both the patterns match. This is due to the ^~ prefix, which disables regular expression search.

It is also possible to define named locations with @, which are for internal use. For example:

```
location @internalerror (
   proxy_pass http://myserver/internalerror.html
)
```

You can then use the @internalerror in another configuration, that is:

```
location / (
  error_page /500.html @internalerror;
)
```

### server\_names\_hash\_bucket\_size

Nginx stores static data in hash tables for quick access. There is a hash table maintained for each set of static data, such as server names. The identical names go into a hash bucket, and the <code>server\_names\_hash\_bucket\_size</code> parameter controls the size of a hash bucket in the server name hash table.

This parameter (and other hash\_bucket\_size parameters) should be a multiple of the processor's cache line size. This allows for an optimized search within a hash bucket ensuring that any entry can be found in a maximum of two memory reads. On Linux, you can find the cache line size as follows:

```
$ getconf LEVEL1_DCACHE_LINESIZE
```

## server names hash max size

The server\_names\_hash\_max\_size directive specifies the maximum size of the hash table, which contains the server names. The size of the hash table calculated using the server\_names\_hash\_bucket\_size parameter cannot exceed this value. The default value is 512.

```
http {
    ...
    ...
    server_names_hash_bucket_size 128;
    server_names_hash_max_size 1024;
    server {
    ...
    ...
    }
}
```

## tcp\_nodelay/tcp\_nopush

The tcp\_nodelay and tcp\_nopush directives allow you to control the socket settings of tcp\_nodelay and tcp\_nopush or tcp\_nocork for Linux. tcp\_nodelay is useful for servers that send frequent small bursts of packets without caring about the response. This directive essentially disables the Nagle algorithm on the TCP/IP socket. tcp\_nopush or tcp\_nocork will only have an effect if you use the sendfile() kernel option.

#### sendfile

The sendfile directive activates or deactivates the usage of Linux kernel's sendfile(). This offers significant performance benefits to applications such as web servers that need to efficiently transfer files. A web server spends much of its time transferring files stored on a disk to a network connection connected to a client running a web browser. Typically, this includes the read() and write() calls, which require context switching and data copying to and from user or kernel buffers. The sendfile system call allows Nginx to copy files from the disk to the socket using the fast track sendfile(), which stays within the kernel space. As of Linux 2.6.22, if you want to use the Aio with direct I/O (O\_DIRECT) you should turn off sendfile. This can be more efficient if the web server serves large files (> 4 MB). In FreeBSD before 5.2.1 and Nginx 0.8.12, you must disable sendfile support as well.

### sendfile max chunk

When set to a nonzero value, the sendfile\_max\_chunk directive limits the amount of data that can be transferred in a single sendfile() call.

#### root

root specifies the document root for the requests by appending a path to the request. For example, with the following configuration:

```
location /images/ {
  root /var/www;
}
```

A request for /web/logo.gif will return the file /var/www/images/logo.gif.

## resolver/resolver\_timeout

This allows you to specify the DNS server address or name. You can also define the timeout for name resolution, for example:

```
resolver 192.168.220.1;
resolver_timeout 2s;
```

### aio

The aio directive allows Nginx to use the POSIX aio support in Linux. This asynchronous I/O mechanism allows multiple nonblocking reads and writes.

```
location /audio {
  aio on;
  directio 512;
  output_buffers 1 128k;
}
```

On Linux this will disable the sendfile support. In FreeBSD before 5.2.1 and Nginx 0.8.12, you must disable the sendfile support.

```
location /audio {
  aio on;
  sendfile off;
}
```

As of FreeBSD 5.2.1 and Nginx 0.8.12, you can use it with sendfile.

### alias

The alias directive is similar to the root directive with a subtle difference. When you define an alias for a location, the alias path is searched instead of the actual location. This is slightly different from the root directive where the root path is appended to the location. For example:

```
location /img/ {
  alias /var/www/images/;
}
```

A request for /img/logo.gif will instruct Nginx to serve the file /var/www/images/logo.gif.

Aliases can also be used in a location specified by a regular expression.

### error\_page

The error\_page directive allows you to show error pages based on error code. For example:

```
error_page 404 /404.html;
error_page 502 503 504 /50x.html;
```

It is possible to show a different error code instead of the original error. It is also possible to specify a script like a php file (which in turn generates the content of the error page). This can allow you to write one generic error handler that creates a customized page depending on the error code and type:

```
error_page 404 =200 /empty.gif;
error_page 500 =errors.php;
```

If there is no need to change the URL in the browser during redirection, it is possible to redirect the processing of error pages to a named location:

```
location / (
  error_page 404 @errorhandler;
)
location @ errorhandler (
  proxy_pass http://backend/errors.php;
)
```

# keepalive\_disable, keepalive\_timeout, and keepalive\_requests

The keepalive\_disable directive allows you to disable the HTTP keepalive for certain browsers.

keepalive\_timeout assigns the timeout for the keepalive connections with the client. The server will close connections after this time. You can also specify a zero value to disable the keepalive for client connections. This adds an HTTP header Keep-Alive: timeout=time to the response.

keepalive\_requests parameter determines how many client requests will be served through a single keepalive connection. Once this limit is reached the connection is closed, and new keepalive session will be initiated.

# Controlling access (HttpAccessModule)

The HttpAccessModule allows IP-based access control. You can specify both IPv4 and IPv6 addresses. Another alternative is using the GeoIP module.

Rules are checked according to the order of their declaration. There are two directives called allow and deny which control the access. The first rule that matches a particular address or a set of addresses is the one that is obeyed.

```
location / {
  deny    192.168.1.1;
  allow    192.168.1.0/24;
  allow    10.1.1.0/16;
```

```
allow 2620:100:e000::8001;
  deny all;
}
```

In this example access is granted to the networks 10.1.1.0/16 and 192.168.1.0/24 with the exception of the address 192.168.1.1, which is denied access together with all the other addresses as defined by the deny all rule that is matched last in this location block. In addition, it allows one specific IPv6 address. All others would be denied.

The order is of utmost importance. The rules are interpreted according to the order. So, if you move deny all to the top of the list, all requests will be denied because that's the first rule that is encountered, and therefore, it takes precedence.

# Authenticating users (HttpBasicAuthModule)

You can use the HttpBasicAuthModule to protect your site or parts of it with a username and password based on HTTP Basic authentication. It is the simplest technique for enforcing access controls to web resources because it doesn't require cookies, session identifier, and login pages. Rather, HTTP Basic authentication uses static, standard HTTP headers, which mean that no handshakes have to be done in anticipation.

The following is an example configuration:

# **Explaining directives**

Now let us look at some of the important directives of this module.

# auth\_basic

This auth\_basic directive includes testing the name and password with HTTP Basic authentication. The assigned value is used as authentication realm.

# auth\_basic\_user\_file

The auth\_basic\_user\_file directive sets the password filename for the authentication realm. The path is relative to the directory of the Nginx configuration file.

The format of the file is as follows:

```
user:pass
user2:pass2:comment
user3:pass3
```

Passwords must be encoded by the function crypt (3). You can use PLAIN, MD5, SSHA, and SHA1 encryption methods. If you have Apache installed on your system, you can use the htpasswd utility to generate the htpasswd file.

This file should be readable by Nginx worker processes, running from an unprivileged user.

# Load balancing (HttpUpstreamModule)

The HttpUpstreamModule allows simple load balancing based on a variety of techniques such as Round-robin, weight, IP address, and so on to a collection of upstream servers.

Example:

```
upstream servers {
  server server1.example.com weight=5;
  server server2.example.com:8080;
  server unix:/tmp/server3;
}
server {
  location / {
    proxy_pass http://servers;
  }
}
```

# **Explaining directives**

Some of the important directives of the HttpUpstreamModule are as follows:

# ip\_hash

The ip\_hash directive causes requests to be distributed between servers based on the IP address of the client.

The key for the hash is the IP address (IPv4 or IPv6) of the client. This method guarantees that the client request will always be transferred to the same server. If the server is not available, the request is transferred to another server.

You can combine ip\_hash and weight based methods. If one of the servers needs to be taken offline, you must mark that server as down.

For example:

```
upstream backend {
  ip_hash;
  server server1.example.com weight=2;
  server server2.example.com;
  server server3.example.com down;
  server server4.example.com;
}
```

#### server

The server directive is used to specify the name of the upstream server. It is possible to use a domain name, address, port, or UNIX socket. If the domain name resolves to several addresses, all are used.

This directive accepts several parameters, which are given as follows:

- weight: This sets the weight of the server. If it is not set, weight is equal to one.
- max\_fails: This is the number of unsuccessful attempts at communicating with the server within the time period fail\_timeout after which it is considered down. If it is not set, only one attempt is made. A value of 0 turns off this check. What is considered a failure is defined by proxy\_next\_upstream or fastcgi\_next\_upstream (except http\_404 errors, which do not count toward max fails).
- fail\_timeout: The time period within which failed attempts to connect to an upstream server are attempted before the server is considered down. It is also the time for which the server will be considered inoperative (before another attempt is made). The default value is 10 seconds.
- down: This parameter marks the server as offline.

If you use only one upstream server, Nginx will ignore the max\_fails and fail\_timeout parameters. This may cause your request to be lost if the upstream server is not available. You can use the same server name several times to simulate retries.

### upstream

The upstream directive describes a set of upstream or backend servers to which the requests are sent. These are the servers that can be used in the directives proxy\_pass and fastcgi\_pass as a single entity. Each of the defined servers can be on different ports. You can also specify servers listening on local sockets.

Servers can be assigned different weights. If it is not specified, the weight is equal to one.

Requests are distributed according to the servers in the Round-robin manner with respect to the server weight.

For example, for every seven requests given previously, their distribution will be as follows: five requests will be sent to serverl.example.com and one request each to the second and the third server. If there is an error in connecting to the server, the request is sent to the next server. In the previous example, there will be three tries within 30 s for server 2 in case of a failure before the request is forwarded to server 3.

# Acting as a proxy (HttpProxyModule)

The HttpProxyModule allows Nginx to act as a proxy and pass requests to another server.

```
location / {
  proxy_pass http://app.localhost:8000;
}
```

Note when using the HttpProxyModule (or even when using FastCGI), the entire client request will be buffered in Nginx before being passed on to the proxy server.

# **Explaining directives**

Some of the important directives of the HttpProxyModule are as follows:

## proxy\_pass

The proxy\_pass directive sets the address of the proxy server and the URI to which the location will be mapped. The address may be given as a hostname or an address and port, for example:

```
proxy_pass http://localhost:8000/uri/;
```

Or, the address may be given as an UNIX socket path:

```
proxy_pass http://unix:/path/to/backend.socket:/uri/;
```

path is given after the word unix between two colons.

You can use the proxy\_pass directive to forward headers from the client request to the proxied server.

```
proxy_set_header Host $host;
```

While passing requests, Nginx replaces the location in the URI with the location specified by the proxy pass directive.

If inside the proxied location, URI is changed by the rewrite directive and this configuration will be used to process the request. For example:

```
location /name/ {
  rewrite     /name/([^/] +) /users?name=$1 break;
  proxy_pass http://127.0.0.1;
}
```

A request URI is passed to the proxy server after normalization as follows:

- Double slashes are replaced by a single slash
- Any references to current directory like "./" are removed
- Any references to the previous directory like "../" are removed.

If proxy\_pass is specified without a URI (for example in "http://example.com/request", /request is the URI part), the request URI is passed to the server in the same form as sent by a client.

```
location /some/path/ {
    proxy_pass http://127.0.0.1;
}
```

If you need the proxy connection to an upstream server group to use SSL, your proxy\_pass rule should use https:// and you will also have to set your SSL port explicitly in the upstream definition. For example:

```
upstream https-backend {
   server 10.220.129.20:443;
}
server {
   listen 10.220.129.1:443;
   location / {
      proxy_pass https://backend-secure;
   }
}
```

### proxy\_pass\_header

The proxy\_pass\_header directive allows transferring header lines forbidden for response.

```
For example:
location / {
  proxy_pass_header X-Accel-Redirect;
}
```

### proxy\_connect\_timeout

The proxy\_connect\_timeout directive sets a connection timeout to the upstream server. You can't set this timeout value to be more than 75 seconds. Please remember that this is not the response timeout, but only a connection timeout.

This is not the time until the server returns the pages which is configured through proxy\_read\_timeout directive. If your upstream server is up but hanging, this statement will not help as the connection to the server has been made.

### proxy\_next\_upstream

The proxy\_next\_upstream directive determines in which cases the request will be transmitted to the next server:

- error: An error occurred while connecting to the server, sending a request to it, or reading its response
- timeout: The timeout occurred during the connection with the server, transferring the request, or while reading the response from the server
- invalid header: The server returned an empty or incorrect response
- http 500: The server responded with code 500
- http 502: The server responded with code 502
- http 503: The server responded with code 503
- http 504: The server responded with code 504
- http\_404: The server responded with code 404
- off: Disables request forwarding

Transferring the request to the next server is only possible if there is an error sending the request to one of the servers. If the request sending was interrupted due to an error or some other reason, the transfer of request will not take place.

## proxy\_redirect

The proxy\_redirect directive allows you to manipulate the HTTP redirection by replacing the text in the response from the upstream server. Specifically, it replaces text in the Location and Refresh headers.

The HTTP Location header field is returned in response from a proxied server for the following reasons:

- To indicate that a resource has moved temporarily or permanently.
- To provide information about the location of a newly created resource. This could be the result of an HTTP PUT.

Let us suppose that the proxied server returned the following:

```
Location: http://localhost:8080/images/new_folder
```

If you have the proxy\_redirect directive set to the following:

```
proxy redirect http://localhost:8080/images/ http://xyz/;
```

The Location text will be rewritten to be similar to the following:

```
Location: http://xyz/new_folder/.
```

It is possible to use some variables in the redirected address:

```
proxy_redirect http://localhost:8000/ http://$location:8000;
```

You can also use regular expressions in this directive:

```
proxy_redirect ~^(http://[^:]+):\d+(/.+)$ $1$2;
```

The value off disables all the proxy\_redirect directives at its level.

```
proxy redirect off;
```

## proxy\_set\_header

The proxy\_set\_header directive allows you to redefine and add new HTTP headers to the request sent to the proxied server.

You can use a combination of static text and variables as the value of the proxy\_set\_header directive.

By default, the following two headers will be redefined:

```
proxy_set_header Host $proxy_host;
proxy set header Connection Close;
```

You can forward the original Host header value to the server as follows:

```
proxy_set_header Host $http_host;
```

However, if this header is absent in the client request, nothing will be transferred.

It is better to use the variable \$host; its value is equal to the request header Host or to the basic name of the server in case the header is absent from the client request.

```
proxy set header Host $host;
```

You can transmit the name of the server together with the port of the proxied server:

```
proxy_set_header Host $host:$proxy_port;
```

If you set the value to an empty string, the header is not passed to the upstream proxied server. For example, if you want to disable the gzip compression on upstream, you can do the following:

```
proxy set header Accept-Encoding "";
```

### proxy\_store

The proxy\_store directive sets the path in which upstream files are stored, with paths corresponding to the directives alias or root. The off directive value disables local file storage. Please note that proxy\_store is different from proxy\_cache. It is just a method to store proxied files on disk. It may be used to construct cache-like setups (usually involving error\_page-based fallback). This proxy\_store directive parameter is off by default. The value can contain a mix of static strings and variables.

```
proxy_store /data/www$uri;
```

The modification date of the file will be set to the value of the Last-Modified header in the response. A response is first written to a temporary file in the path specified by proxy\_temp\_path and then renamed. It is recommended to keep this location path and the path to store files the same to make sure it is a simple renaming instead of creating two copies of the file.

#### Example:

```
proxy_store on;
proxy_store_access user:rw group:rw all:r;
proxy_temp_path /data/temp;
alias /data/www;
}
```

In this example, proxy store access defines the access rights of the created file.

In the case of an error 404, the fetch internal location proxies to a remote server and stores the local copies in the /data/temp folder.

### proxy\_cache

The proxy\_cache directive either turns off caching when you use the value off or sets the name of the cache. This name can then be used subsequently in other places as well. Let's look at the following example to enable caching on the Nginx server:

```
http {
  proxy_cache_path /var/www/cache levels=1:2 keys_zone=my-
    cache:8m max_size=1000m inactive=600m;
  proxy_temp_path /var/www/cache/tmp;

server {
  location / {
    proxy_pass http://example.net;
    proxy_cache my-cache;
    proxy_cache_valid 200 302 60m;
    proxy_cache_valid 404 1m;
  }
  }
}
```

The previous example creates a named cache called my-cache. It sets up the validity of the cache for response codes 200 and 302 to 60m, and for 404 to 1m, respectively.

The cached data is stored in the /var/www/cache folder. The levels parameter sets the number of subdirectory levels in the cache. You can define up to three levels.

The name of key\_zone is followed by an inactive interval. All the inactive items in my-cache will be purged after 600m. The default value for inactive intervals is 10 minutes.

# Compressing content (HttpGzipModule)

The HttpGzipModule allows for on-the-fly gzip compression.

```
gzip on;
gzip_min_length 1000;
gzip_proxied expired no-cache no-store private auth;
gzip_types text/plain application/xml;
```

The achieved compression ratio, computed as the ratio between the original and the compressed response size, is available via the variable \$gzip\_ratio.

# **Explaining directives**

Some of the important directives of the HttpGzipModule are as follows:

### gzip

The gzip directive enables or disables gzip compression.

## gzip\_buffers

The gzip\_buffers directive assigns the number and size of the buffers in which the compressed response will be stored. If unset, the size of one buffer is equal to the size of the page; depending on the platform, this is either 4K or 8K.

### gzip\_comp\_level

The gzip\_comp\_level directive sets a gzip compression level of a response. The compression level, between 1 and 9, where 1 is the least compression (fastest) and 9 is the most compression (slowest).

# gzip\_disable

The gzip\_disable directive disables gzip compression for browsers or user agents matching the given regular expression. For example, to disable gzip compression for Internet Explorer 6 use:

```
gzip disable "msie6";
```

This is a useful setting to have since some browsers such as MS Internet Explorer 6 don't handle the compressed response correctly.

# gzip\_http\_version

The gzip\_http\_version directive turns gzip compression on or off depending on the HTTP request version, which is 1.0 or 1.1.

### gzip\_min\_length

The gzip\_min\_length directive sets the minimum length, in bytes, of the response that will be compressed. Responses shorter than this byte length will not be compressed. Length is determined from the Content-Length header.

### gzip proxied

The gzip\_proxied directive enables or disables compression for proxied requests. The proxied requests are identified through the Via HTTP header. This header informs the server of proxies through which the request was sent. Depending on various HTTP headers, we can enable or disable the compression for proxied requests as follows:

- off: This disables compression for requests having a Via header
- expired: This enables compression if a response header includes the field Expires with a value that disables caching
- no-cache: This enables compression if the Cache-Control header is set to no-cache
- no-store: This enables compression if the Cache-Control header is set to no-store
- private: This enables compression if the Cache-Control header is set to private
- no\_last\_modified: This enables compression if Last-Modified isn't set
- no etag: This enables compression if there is no ETag header
- auth: This enables compression if there is an Authorization header
- any: This enables compression for all proxied requests

# gzip\_types

The gzip\_types directive enables compression for additional MIME types besides text or html. text/html is always compressed.

# Controlling logging (HttpLogModule)

The HttpLogModule controls how Nginx logs the requests for resources, for example:

```
access_log /var/log/nginx/access.log gzip buffer=32k;
```

Please note that this does not include logging errors.

# **Explaining directives**

Some of the important directives of HttpLogModule are the following.

### access\_log

The access\_log directive sets the path, format, and buffer size for the access logfile. Using off as the value disables logging at the current level. If the format is not indicated, it defaults to combined. The size of the buffer must not exceed the size of the atomic record for writing into the disk file. This size is not limited for FreeBSD 3.0-6.0. If you specify gzip, the log is compressed before it's written to the disk. The default buffer size is 64K with compression level as 1.

The atomic size that can be written is called PIPE\_BUF. The capacity of a pipe buffer varies across systems.

Mac OS X, for example, uses a capacity of 16,384 bytes by default but can switch to 65,336 byte capacities if large writes are made to the pipe. Or it will switch to a capacity of a single system page if too much kernel memory is already being used by pipe buffers (see xnu/bsd/sys/pipe.h and xnu/bsd/kern/sys\_pipe.c; since these are from FreeBSD, the same behavior may happen here too).

According to the Linux pipe(7) man page, pipe capacity is 65,536 bytes since Linux 2.6.11 and a single system page prior to that (for example, 4096 bytes on 32-bit x86 systems). The buffer for each pipe can be changed using fcntl system call to the maximum of /proc/sys/fs/pipe-max-size.

## log\_format

The log\_format directive describes the format of a log entry. You can use general variables in the format as well as variables that exist only at the moment of writing into the log. An example of log\_format is as follows:

```
log_format gzip '$msec $request $remote-addr $status $bytes_sent';
```

You can specify the format of a log entry by specifying what information should be logged. Some of the options you can specify are as follows:

- \$body\_bytes\_sent: This is the number of bytes transmitted to the client minus the response headers
- \$bytes sent: This is the number of bytes transmitted to the client
- \$connection: This is the number of connections
- \$msec: This is the current time at the moment of writing the log entry (microsecond accuracy)
- \$pipe: This is p if request was pipelined

- \$request\_length: This is the length of the body of the request
- \$request\_time: This is the time it took Nginx to work on the request, in seconds, with millisecond precision
- \$status: This is the status of the answer
- \$time\_iso8601: This is the time in ISO 8601 format, for example, 2011-03-21T18:52:25+03
- \$time local: This is the local time in common log format

# Setting response headers (HttpHeadersModule)

The HttpHeadersModule allows setting arbitrary HTTP headers.

# **Explaining directives**

Some of the important directives of the HttpHeadersModule are the following:

### add\_header

The add\_header directive adds a header to the header list of the response when the response code is 200, 201, 204, 206, 301, 302, 303, 304, or 307. The value can contain variables and can contain negative or positive time value.

Note that you should not use this directive to replace or override the value of a header. The headers specified with this directive are simply appended to the header list.

## expires

The expires directive is used to set the Expires and Cache-Control headers in the response. You can set the value to off to leave these headers as it is. The time in this field is computed as a sum of the current time and the time specified in the directive. If the modified parameter is used, time is computed as a sum of the file's modification time and the time specified in the directive.

- epoch: This sets the Expires header to the absolute value of 1 January, 1970 00:00:01 GMT.
- max: This sets the Expires header to 31 December 2037 23:59:59 GMT, and the Cache-Control header to 10 years.

You can specify a time interval using @:

@5h40m

The contents of the Cache-Control header depend on the sign of the specified time. A negative value of time sets it to no-cache. A positive value sets it to time in seconds.

The following is an example configuration:

```
expires 12h;
expires modified +14h;
expires @5h;
expires 0;
expires -1;
expires epoch;
add header X-Name example.org
```

# Rewriting requests (HttpRewriteModule)

The HttpRewriteModule is used to change request URIs using regular expressions, redirect the client, and select different configurations based on conditions and variable values. In order to use this module, you should compile Nginx with PCRE support.

The processing of the directives starts at the server level. After this, the location block matching the request is searched and any rewrite directives there are executed. If this processing results in further rewrites, a new location block is search for the changed URI. This cycle continues 10 times before the server throws the 500 error.

# **Explaining directives**

Some of the important directives of the HttpRewriteModule are the following:

### break

The break directive stops the processing of any other rewrite block directives in the current block.

```
if ($slow) {
   limit_rate 10k;
   break;
}
```

#### if

The if directive checks a condition. If the condition evaluates to true, the code indicated in the curly braces is carried out and the request is processed in accordance with the configuration within the following block. The configuration inside the if block is inherited from the previous level.

Following are considered to be valid conditions.

- The name of a variable is a condition. The condition evaluates to false if the variable contains an empty string "" or a 0.
- Using comparison operator with the variable to compare it to another variable or a string.
- Matching a variable against a regular expression using ~, \*~, or !~ operator.
   \*~ is used for case-insensitive comparison, while !~ is a not-equals operator.
- You can check for the existence of a file using the -f or !-f operators (similar to BASH tests).
- Checking for the existence of a directory using -d or !-d.
- Checking for the existence of a file, directory, or symbolic link using -e or
   !-e.
- Checking whether a file is executable using -x or !-x.

By placing part of a regular expression inside round brackets or parentheses, you can group that part of the regular expression together. This allows you to apply a quantifier to the entire group or to restrict alternation to part of the regular expression. These parts can be accessed in the \$1 to \$9 variables.

### Example:

```
if ($http_user_agent ~ MSIE) {
  rewrite ^(.*)$ /msie/$1 break;
}
if ($http_cookie ~* "val=([^;] +)(?:;|$)" ) {
  set $val $1;
}
if ($request_method = GET ) {
  return 405;
}
if ($args ~ post=140){
  rewrite ^ http://acme.com/ permanent
}
```

#### return

The return directive stops execution and returns a status code. It is possible to use any HTTP return code ranging in number from 0 to 999.

If you want to terminate the connection and don't want to send any headers in response, use the return code 444.

### rewrite

The rewrite directive does the actual rewrite and changes URI according to the regular expression and the replacement string. Directives are carried out in the order of definition in the configuration file. The flag parameter makes it possible to stop the rewriting process in the current block.

If the replacement string begins with http://, the client will be redirected and any further rewrite directives will be terminated.

The value of the flag parameter can be one of the following:

- last: This completes the processing of current rewrite directives and searches for a new block that matches the rewritten URI
- break: This stops the rewriting process in the current block
- redirect: This returns a temporary redirect with the code 302, and is used if a replacement string does not start with http://orhttps://
- permanent: This returns a permanent redirect with code 301

Note that outside location blocks, last and break are effectively the same.

### Example:

```
rewrite ^(/media/.*)/video/(.*)\..*$ $1/mp3/$2.avi last;
rewrite ^(/media/.*)/audio/(.*)\..*$ $1/mp3/$2.ra break;
return 403;
```

But if we place these directives in the location block, it is necessary to replace the flag last by break, otherwise Nginx will hit the 10-cycle limit and return error 500:

```
location /download/ {
  rewrite ^(/media/.*)/video/(.*)\..*$ $1/mp3/$2.avi break;
  rewrite ^(/media/.*)/audio/(.*)\..*$ $1/mp3/$2.ra break;
  return 403;
}
```

If there are arguments in the replacement string, the rest of the request arguments are appended to them. To avoid having them appended, place a question mark as the last character:

```
rewrite ^/pages/(.*)$ /show?page=$1? last;
```

Note that for curly braces ({ and }), as they are used both in regex and for block control, to avoid conflicts, regex with curly braces are to be enclosed with double quotes (or single quotes). For example, to rewrite URLs such as /users/123456 to /path/to/users/12/1234/123456.html, use the following (note the quotes):

```
rewrite "/users/([0-9]{2})([0-9]{2})"
/path/to/users/$1/$1$2/$1$2$3.html;
```

If you specify a ? at the end of a rewrite, Nginx will drop the original query string. A good use case is when using <code>\$request\_uri</code>, you should specify the ? at the end of the rewrite to avoid Nginx doubling the query string.

An example of using \$request\_uri in a rewrite from www.acme.com to acme.com:

```
server {
   server_name www.acme.com;
   rewrite ^ http://acme.com$request_uri? permanent;
}
```

Also, rewrite operates only on paths, not on parameters. To rewrite a URL with parameters to another URL, use the following instead:

```
if ($args ~ post=200) {
  rewrite ^ http://acme.com/new-address.html?;
}
```

## rewrite\_log

The rewrite\_log directive enables the logging of information about rewrites to the error log at notice level.

#### set

The set directive establishes the value for the variable indicated. It is possible to use text, variables, and their combination as the value.

You can use set to define a new variable. Note that you can't set the value of a \$http xxx header variable.

### uninitialized\_variable\_warn

The uninitialized\_variable\_warn directive enables or disables warnings of variables that are not initialized.

# Interacting with FastCGI (HttpFastcgiModule)

The HttpFastcgiModule allows Nginx to interact with the FastCGI processes (that is, PHP) and controls which parameters will be passed to the process.

#### Example:

The name of the FastCGI server is provided in the fastcgi\_pass parameter. This name can be an IP address or a domain name with a port. This can also be an UNIX domain socket.

If you want to pass a parameter to the FastCGI server, you use the fastcgi\_param parameter. The value of this parameter can be a static value, a variable, or a combination of both.

Following is a minimum configuration for PHP:

# Simple caching (HttpMemcachedModule)

You can use this module to perform simple caching using memcached. Memcached is an in-memory, key-value store for small chunks of arbitrary data (strings, objects) from the results of database calls, API calls, or page rendering.

#### Example:

```
server {
  location / {
    set $memcached_key $uri$args;
    memcached_pass http://mem-server:1211
  default_type text/html;
    error_page 404 502 504 @error;
}
```

```
location @error {
   proxy_pass http://backend;
}
```

# **Explaining directives**

Some of the important directives of the HttpMemcachedModule are as follows:

## memcached\_pass

The memcached\_pass directive specifies the memcached server name as an IP or domain name. It can also contain a port. If the domain name translates into various addresses, all of them are tried in the Round-robin fashion.

### memcached\_connect\_timeout

The memcached\_connect\_timeout directive is the timeout for connecting to the memcached server. The time of the timeout usually can be 75s at maximum. The default value is 60s.

### memcached read timeout

The memcached\_read\_timeout directive is the timeout for reading keys from the memcached server. This time is measured between two successive reads, and if the memcached server does not respond, the timeout occurs. The default value is 60s.

## memcached\_send\_timeout

The memcached\_send\_timeout directive is the timeout for sending a request to the memcached server. A timeout is only set between two successive write operations and not for the transmission of the whole request. If a memcached server does not receive anything within this time, a connection is closed.

# memcached\_buffer\_size

The memcached\_buffer\_size directive is the receive or send buffer size in bytes. It sets the size of the buffer used for reading a response received from the memcached server. A response is passed to a client synchronously and immediately when it is received. Default value is 4K or 8K.

# memcached\_next\_upstream

Which failure conditions should cause the request to be forwarded to another memcached upstream server? The answer is only when the value in memcached pass is an upstream block with two or more servers.

# Limiting requests (HttpLimitReqModule)

The HttpLimitReqModule allows limiting the request processing rate by key, in particular by the address. The limitation is done using the leaky bucket method. A counter associated with each address transmitting on a connection is incremented whenever the user sends a request and is decremented periodically. If the counter exceeds a threshold upon being incremented, Nginx delays the request.

The following is an example configuration:

```
http {
    limit_req_zone $binary_remote_addr zone=one:10m rate=1r/s;
    ...
    server {
        ...
        location /search/ {
             limit_req zone=one burst=5;
        }
}
```

# **Explaining directives**

Some of the important directives of the HttpLimitReqModule are as follows:

## limit\_req

The limit\_req directive sets a shared memory zone and the maximum burst size of requests. Excessive requests are delayed until their number exceeds the maximum burst size in which case the request is terminated with an error 503 (Service Temporarily Unavailable). By default, the maximum burst size is equal to zero. For example, for the directive limit\_req\_zone:

```
$binary_remote_addr zone=one:10m rate=1r/s;
server {
   location /search/ {
      limit_req zone=one burst=5;
   }
```

It allows a user no more than one request per second on average with bursts of no more than five requests.

If delaying excess requests within a burst is not necessary, you should use the option nodelay:

```
limit_req zone=one burst=5 nodelay;
```

### limit\_req\_log\_level

The limit\_req\_log\_level directive controls the log level of the delayed or rejected requests. The log levels can be info, notice, warn, or error. The default log level is error for rejected requests. Delays are logged at the next lower level, for example when limit\_req\_log\_level is set to "error", delayed requests are logged at "warn".

### limit\_req\_zone

The limit\_req\_zone directive sets the name and parameters of a shared memory zone that keeps states for various keys. The state stores the current number of excessive requests in particular. The key is any nonempty value of the specified variable (empty values are not accounted). An example usage of this is as follows:

```
limit_req_zone $binary_remote_addr zone=myzone:20m rate=5r/s;
```

In this case, there is a 20 MB zone called myzone, and the average speed of queries for this zone is limited to 5 requests per second.

The sessions are tracked per user in this case. A 1 MB zone can hold approximately 16,000 states of 64 bytes. If the storage for a zone is exhausted, the server will return error 503 (Service Temporarily Unavailable) to all further requests.

The speed is set in requests per second or requests per minute. The rate must be an integer; so if you need to specify less than one request per second, say, one request every two seconds, you would specify it as 30r/m.

# Limiting connections (HttpLimitConnModule)

The HttpLimitConnModule makes it possible to limit the number of concurrent connections for a key such as an IP address.

An example configuration:

```
http {
    limit_conn_zone $binary_remote_addr zone=addr:10m;
    ...
    server {
        ...
        location /download/ {
            limit_conn addr 1;
        }
}
```

# **Explaining directives**

Some of the important directives of HttpLimitConnModule are as follows:

### limit\_conn

The value of the limit\_conn directive defines the limit of connection per zone. When this limit is exceeded, the server will return a status error 503 (Service Temporarily Unavailable) in reply to the request.

Multiple limit directives for different zones can be used in the same context. For example:

```
limit_conn_zone $binary_remote_addr zone=addr:10m;
server {
    location /download/ {
        limit_conn addr 1;
    }
```

This is allowed for only a single connection at a time per unique IP address.

### limit\_conn\_zone

The limit\_conn\_zone directive sets the parameters for a zone that keeps the state for various keys. This state stores the current number of connections in particular. The key is the value of the specified variable. For example:

```
limit conn zone $binary remote addr zone=addr:10m;
```

Here, an IP address of the client serves as a key. If the storage for a zone is exhausted, the server will return error 503 (Service Temporarily Unavailable) to all further requests.

# limit\_conn\_log\_level

The limit\_conn\_log\_level directive sets the error log level, which is used when a connection limit is reached. The default log level is error.

## limit\_conn\_status

The limit\_conn\_status directive defines the response code when a limit is reached. The default value is 503 (Service Unavailable).

# **Summary**

In this chapter we looked at several standard HTTP modules. These modules provide a very rich set of functionalities by default. You can disable these modules if you please at the time of configuration. However, they will be installed by default if you don't. The list of modules and their directives in this chapter is by no means exhaustive. Nginx's online documentation can provide you with more details.

In the next chapter we will look into some optional HTTP modules.

4

# **Installing Third-party Modules**

In this chapter we will explore the installation of third-party modules. Third-party modules are developed by a vast variety of developers around the world and are hosted on various open source repositories such as GitHub and SourceForge. Some of these modules are well tested while others are not quite ready for production. These modules are not officially supported by Nginx developers and might have issues across different Nginx versions. In this chapter, we will talk about some of the most well-known Nginx modules. A bigger list of available options can be browsed on the Nginx website at http://wiki.nginx.org/3rdPartyModules.

All the configuration directives that we have discussed so far, and the ones that we will discuss in this and the remaining chapters, are specified in the nginx.conf file. The default location of the nginx.conf file is /usr/local/conf/.

# Compiling third-party modules

None of the third-party modules that we will be covering in this chapter are distributed with the source code. You will have to download the source code and compile it by specifying its location while compiling Nginx. You can do that by specifying the --add-module parameters while running configure. For example, if you downloaded the module's source code present in /opt/downloads, you can compile it in the Nginx binary with the following code:

configure --add-module=/opt/downloads/module-folder

Some of these modules may have additional dependencies, which you will have to resolve. Please refer to the documentation of the module you are trying to install, to make sure you understand the consequences and dependencies of the module you are about to compile.

# Communicating with PostgreSQL (ngx\_postgres)

The Nginx PostgreSQL module is currently hosted at http://labs.frickle.com/nginx\_ngx\_postgres/ and maintained by Frickle Labs. It is an upstream module that allows direct communication with the PostgreSQL database. The output of this module is in a custom binary format named **Resty DBD Stream (RDS)**. This module is useful if you want to directly connect Nginx to a PostgreSQL database. There can be several use-cases of why you would want to do that. You might want to serve pages by directly querying results from a table. You might also want to log things in a database or check certain conditions by querying a database table. Or you might want to authenticate a user from an upstream PostgreSQL database. For all such situations and more, the ngx\_postgres module will be useful.

An example configuration is as follows:

# **Explaining directives**

Some important directives of the ngx postgres module are as follows:

### postgres\_server

The postgres\_server directive sets the details of the database server. You can specify the hostname or IP address along with a port, username, and password.

An example configuration is as follows:

```
postgres_server 127.0.0.1 dbname=test user=test password=test;
```

### postgres\_keepalive

The postgres\_keepalive directive is used to configure keepalive parameters. The syntax is as follows:

```
postgres_keepalive off | max=count [mode=single|multi]
[overflow=ignore|reject]
default: max=10 mode=single overflow=ignore
```

Here, the max parameter determines the maximum number of keepalive connections. The mode parameter has two possible values, multi and single. The single mode means that the connection pool will not differentiate between multiple postgres\_server definitions in the current block and will apply to all of them, that is, you have one pool for all the postgres\_server definitions. In the multi mode, the pool will re-use connections that have identical server hostnames and ports. The default value is single. The overflow option specifies what to do when the connection pool is already full and a new database connection is required. Either reject or ignore can be specified. In case of reject, it will reject the current request and return the 503 Service Unavailable error page. On using ignore, this module will create a new database connection.

### postgres\_pass

The postgres\_pass directive holds the name of the upstream block that contains the PostgreSQL connection's configurations. It can also contain variables.

## postgres\_query

The postgres\_query directive is used to specify a PostgreSQL query. If an HTTP method such as GET, POST, PUT, or DELETE is specified, the query is used only for the specified methods; otherwise, it will run for all the methods. A query can contain variables and you can specify multiple query directives in one location. An example configuration is as follows:

```
postgres_query    GET POST "SELECT * FROM employees";
```

### postgres\_rewrite

The postgres\_rewrite directive should be used to send a specific response code when a condition is met. The condition can be one of the following:

- no changes: This is the condition when no rows are affected by the query
- changes: This is the condition when at least one row is affected by the query
- no rows: This is the condition when no rows are returned in the result set
- rows: This is the condition when at least one row is returned in the result set

If you want to send the original response body to the client, prefix the code with = as shown in the following example configuration:

```
postgres_rewrite no_rows =403;
```

### postgres\_output

The postgres\_output directive determines the output type of the response. The possible values are rds, text, binary, value, and none. The none value is used when you don't want any output. value is used when you want a single value as an output in the text format. All response types set the appropriate HTTP header.

### postgres\_set

The postgres\_set directive is used to set a variable from a single value from the result set. You can specify the row and column to pick the value from. An example configuration is as follows:

```
postgres_set $empname 00 required
```

If you set this directive to required, the module will generate a 500 internal server error if the value to be set is null or out of range.

### postgres\_escape

The postgres\_escape directive will escape, quote a value in the \$unquoted variable, and store the result in the \$escaped variable, which can be safely used in SQL queries. An example configuration is given as follows:

```
postgres_escape $user $remote_user;
postgres_escape $pass $remote_passwd;
```

# postgres\_connect\_timeout

The postgres\_connect\_timeout directive sets a timeout value for connecting to the database.

# postgres\_result\_timeout

The postgres\_result\_timeout directive sets a timeout value for receiving results from the database.

# Communicating with MySQL and drizzle (drizzle-nginx)

The drizzle-nginx module is an upstream module to communicate with a MySQL or drizzle server. Drizzle is a fork of MySQL, which is optimized for multicore processing and scalability. This module essentially integrates libdrizzle into an Nginx module. Like the Nginx PostgreSQL module, this module does not create human-readable text output, but rather a Resty DB format, which is a custom binary format.

You can download the source code for this module from the GitHub repository at https://github.com/chaoslawful/drizzle-nginx-module. Please note that you will need to install drizzle and libdrizzle in order to be able to successfully compile this module. You can download drizzle from launchpad at https://launchpad.net/drizzle.

This module is useful if you want to directly connect Nginx with a MySQL database. There can be several use-cases of why you would want to do that. You might want to serve pages by directly querying results from a table. You might also want to log things in a database or check certain conditions by querying a database table. Or else, you might want to authenticate a user from an upstream MySQL database. For all such situations and more, this module will be useful.

# **Explaining directives**

The most important directives from the drizzle-nginx module are as follows:

## drizzle server

We use the drizzle\_server directive to specify the drizzle server's name in the form of an IP address or a domain name, and optionally a port. The default port number is 3306. You can also specify a username and a password. The following options are supported by this directive:

- user=: This option defines the database username for login
- password=: This option defines the database password, optionally enclosed in quotes, for special characters as shown in the following example configuration:

#### Installing Third-party Modules

- dbname=: This option defines the database to be used for the default connection
- protocol=: This option defines the target database type, drizzle, or mysql (the default value is drizzle)
- charset=: This option is used to explicitly specify the character set for the MySQL connections as shown in the following example configuration:

#### drizzle\_keepalive

The drizzle\_keepalive directive is used to maintain a keepalive pool for the target database. The following options are supported by this directive:

- max=: This option is set to 0 by default, which means that the keepalive connection pooling is disabled. In order to enable it, you must set this value to a value greater than 0.
- mode=: The possible values for this parameter are multi and single. The single mode means that the connection pool will not differentiate between multiple drizzle\_server definitions in the current block, and the pool will apply to all of them, that is, you have one pool for all the drizzle\_server definitions. In the multi mode, the pool will re-use connections that have identical server host names and ports. The default value is single.
- overflow=: This option specifies what to do when the connection pool is already full while a new database connection is required. Either reject or ignore can be specified. In case of reject, it will reject the current request and return the **503 Service Unavailable** error page. For ignore, this module will create a new database connection.

#### drizzle\_query

The drizzle\_query directive defines the SQL query to be run on the database's backend.

You are allowed to use Nginx variables in place of queries, but you must be careful with SQL injection attacks. You are, therefore, advised to properly sanitize and quote your SQL queries. An example configuration is as follows:

```
location /employees {
    set_unescape_uri $name $arg_name;
    set_quote_sql_str $quoted_name $name;

    drizzle_query "select * from empl where name = $quoted_name";
    drizzle_pass my_backend;
}
```

#### drizzle\_pass

Using the drizzle\_pass directive, you can pass the current location to another defined MySQL or drizzle-upstream block.

You can use the Nginx variables as values to perform dynamic passing. An example configuration is as follows:

```
upstream backend { localhost:3306 dbname=mydb; }
server {
   location /emp {
      set $srv backend;

      drizzle_query ...;
      drizzle_pass $srv;
   }
}
```

#### drizzle\_connect\_timeout

The drizzle\_connect\_timeout directive specifies the timeout value for connecting to the remote server. The value can be an integer with an optional time unit, such as s (second), ms (millisecond), or m (minute). The default time unit is s and the default value is 60 s.

#### drizzle\_send\_query\_timeout

The drizzle\_send\_query\_timeout directive specifies the timeout value for sending a SQL query to a remote server. The value can be an integer with an optional time unit, such as s (second), ms (millisecond), or m (minute). The default time unit is s and the default value is 60 s.

#### drizzle\_recv\_cols\_timeout

The drizzle\_recv\_cols\_timeout directive specifies the timeout value for receiving the columns' metadata of the result set to a remote server. The value can be an integer with an optional time unit, such as s (second), ms (millisecond), or m (minute). The default time unit is s and the default value is 60 s.

#### drizzle\_recv\_rows\_timeout

The drizzle\_recv\_rows\_timeout directive specifies the timeout value for receiving the rows' data of the result set (if any) to a remote server. The value can be an integer with an optional time unit, such as s (second), ms (millisecond), or m (minute). The default time unit is s and the default value is 60 s.

#### drizzle\_buffer\_size

The drizzle\_buffer\_size directive specifies the buffer size for server outputs. The default value of this directive depends on the OS page size which would be 4K/8K normally. Larger buffer sizes can result in lower network overheads. However, you have to find the correct value for your workload by experimenting with this number.

#### drizzle\_module\_header

The drizzle\_module\_header directive controls whether to output the drizzle header in the response or not. By default, the sending of the header is enabled. This directive can be configured with the following script:

```
X-Resty-DBD-Module: ngx_drizzle 0.1.0
```

# Digest Authentication (ngx\_http\_auth\_digest)

In today's world, HTTP basic authentication is too basic and doesn't provide adequate security required by the modern web servers. The reason is that usernames and passwords are sent in clear text unless you use HTTPS. The ngx\_http\_auth\_digest module can be used to protect your resources using the HTTP Digest Authentication based on RFC 2617.

The digest authentication module works, and is considered quite stable. However, it is perhaps not tested enough for the real world, so make sure it works in your situation. As this module deals with security, it is always a good idea to test the software thoroughly.

You can download the source code at https://github.com/samizdatco/nginx-http-auth-digest.

You can password-protect a directory tree by adding the following code lines into a server section in your Nginx configuration file:

```
auth_digest_user_file /opt/passwd.digest;
location /members{
   auth_digest 'members area; # set the realm for this location block
}
```

Currently, the digest authentication module works with a file generated through the htdigest script. The htdigest script can be found in your Apache installation or source code. There is also an htdigest.py script in this module's source code, which will help you generate a compatible file.

## **Explaining directives**

Some of the most important directives of ngx\_http\_auth\_digest are as follows:

#### auth\_digest

The auth\_digest directive can be defined in the contexts of the server and location. This parameter defines the realm name for authentication. This name should match the name used in creating the htdigest file. To selectively disable authentication, set auth digest to off. The default value for this directive is off.

#### auth\_digest\_user\_file

The auth\_digest\_user\_file directive can be defined in the contexts of the server and location. This directive is used to specify the name of the password file. The password file should be created by the Apache htdigest command (or the included htdigest.py script).

#### auth\_digest\_timeout

The auth\_digest\_timeout directive can be defined in the contexts of the server and location. This timeout value defines the expiry time of the challenge sent to the client. If the user does not provide the response within this time, the challenge is considered stale, and a new challenge is sent to the client when a resource is requested again or the response comes from the client. The default timeout value is 60 s.

#### auth\_digest\_expires

The auth\_digest\_expires directive can be defined in the contexts of the server and location. This parameter is used to define the expiry time of the nonce value. Once a client successfully authenticates, the nonce value is cached and subsequent requests use the cached value. This parameter defines the duration for which a client can continue to use the nonce value. The default digest expiry value is 10 s.

#### auth\_digest\_replays

The auth\_digest\_replays directive can be defined in the contexts of the server and location. The validity of a cached nonce can also be specified in terms of the number of requests instead of time, by using this directive. Having a high value will increase your shared memory requirements. The default value is 20 replays per nonce.

#### auth\_digest\_shm\_size

The auth\_digest\_shm\_size directive can only be defined in the server's context. This directive specifies the fixed size memory cache used to store information about the active authenticated requests. Once this cache is full, no further authentication will be possible until the active sessions expire. The default size is about 4 MB. The default value allows around 82,000 non-replay requests every 70 seconds.

An example configuration is as follows:

```
auth_digest_user_file /opt/htdigest;
auth_digest_shm_size 4m;  # the storage space allocated for tracking
active sessions

location /restricted {
   auth_digest 'this is a restricted location';
   auth_digest_timeout 60s;
   auth_digest_expires 10s;
   auth_digest_replays 20;
}

location / {
   auth_digest 'restricted';
   location /img {
     auth_digest off; # this location will be accessible }
}
```

# Speeding up web pages (ngx\_pagespeed)

The ngx\_pagespeed module optimizes the web pages and associated resources to reduce latency and bandwidth. It is capable of rewriting HTML pages and automatically eliminates deficiencies that reduce the performance of your website or web pages. This module is written by Google and is similar to Apache's mod\_pagespeed module.

This module reduces the page's load time by automatically applying web performance best practices to pages and associated assets (CSS, JavaScript, and images). It can perform the following types of optimizations:

- Image optimization
- CSS and JavaScript optimization
- Resource inlining
- HTML rewriting
- Cache lifetime extension

In order to enable the module, you have to put pagespeed On in the server or the HTTP block. In addition, you should define the FileCache location and specify which rewrite filters you would like to enable. The following is an example configuration:

```
http {
  pagespeed On;
  pagespeed FileCachePath "/var/cache/ngx_pagespeed/";
  pagespeed EnableFilters combine_css,combine_javascript, add_
instrumentation;
  ...
  ...
}
```

The FileCachePath parameter provides the location where rewritten files are cached, and should be a valid path. The EnableFilters parameter defines which optimizations will be enabled for the specific location.

#### **Configuring handlers**

When the ngx\_pagespeed module is configured and enabled, a default handler is automatically created, but there are additional handlers in order to monitor the module's activity in more details, which are as follows:

- Statistics handler: This handler shows the statistics related to page or resource optimizations, including which pages have been optimized so far, as well as various latency and cache-effectiveness metrics. You can also view the summary of the current configuration that is active at the moment.
- Messages handler: If you have enabled and specified a size for the MessageBufferSize parameter, this handler will contain a server-wide history of recent logging output from pagespeed, including messages that are omitted from the server's logfile based on its log level.
- Console handler: This handler shows graphs of issue metrics over time.
- **Beacon handler**: This handler can be used by the add\_instrumentation filter to report the loading time of pages for your sites, which you can then view via the statistics page.

The following is an example configuration from the module's documentation page:

```
pagespeed on;

# Needs to exist and be writable by nginx.
pagespeed FileCachePath /var/ngx_pagespeed_cache;

# Ensure requests for pagespeed optimized resources go to the pagespeed handler

# and no extraneous headers get set.
location ~ "\.pagespeed\.([a-z]\.)?[a-z]{2}\.[^.]{10}\.[^.]+" {
   add_header "" "";
```

#### Installing Third-party Modules

```
}
location ~ "^/ngx_pagespeed_static/" { }
location ~ "^/ngx_pagespeed_beacon$" { }
location /ngx_pagespeed_statistics { allow 127.0.0.1; deny all; }
# Recent log messages. Like statistics, these are generally not to be
shown to the public, so this has access controls as well.
pagespeed MessageBufferSize 100000;
location /ngx_pagespeed_message { allow 127.0.0.1; deny all; }
```

In order to check if the module is processing your pages or not, you can check the source of a page, which you should be able to see at the X-Page-Speed header through the following code lines:

```
$ curl -I 'http://localhost /index.html/' | grep X-Page-Speed
X-Page-Speed: 1.6.29.5-...
```

You can find a complete list of pagespeed filters in the online documentation available at https://developers.google.com/speed/pagespeed/module/using.

# Lua scripting (ngx\_lua)

If you want the ability to write scripts in your Nginx configuration file, then utilizing the power of Lua by using the ngx\_lua module can be a great move. This is a very powerful module with a large number of uses, and provides you with a full programming capability inside the Nginx configuration. It has the following advantages and features:

- This will allow you to perform complicated processing on the incoming request before it's executed, or change the response afterwards
- You can add new headers or remove the existing ones
- You can perform redirects and routing based on complicated program-like logic
- You can create a sophisticated logging framework entirely based on Lua scripts
- You can either block or allow IP addresses
- You can build your own authentication or preprocessing layer on top,
   without having to write your own C modules and recompiling the Nginx code

Lua is a lightweight, embeddable scripting language, which makes it very suitable for scripting in the configuration file.

This module allows you to run the Lua code during different phases in the Nginx request handling. Before we look at more details of Lua scripting, it is worth looking at the different phases of Nginx request handling.

Each request handled by Nginx goes through the following phases:

S1. No.	Nginx request-handling phase	Description
1	server selection	A server block is selected based on the request.
2	post read	This phase is executed after a request is read. This allows you to perform actions on the request before it is processed. For example, HttpRealIpModule can use this phase to add IP addresses in the request headers.
3	server rewrite	During this phase, URL rewriting can take place. You can select the configuration based on variable values. The HttpRewrite module allows you to do so.
4	location selection	During this phase, a location configuration block is selected or matched based on the requested URL.
5	location rewrite	This phase allows you to do rewrites within a selected location-configuration block.
6	preaccess	This phase allows you to carry out certain filters, that is, limit the number of requests per session.
7	access	This phase runs authentications, such as auth_basic or auth_digest. You can also allow or deny requests based on criteria, such as IP addresses.
8	try files	The core module's try_files directive is executed in this phase.
9	content	The actual content generation takes place in this phase. All upstream modules are executed in this phase.
10	log	During this phase, information is logged in the logfiles. Modules such as access_log operate within this phase.
11	post action	During this phase, the post_action directive of the core module is executed, which allows you to send subrequests to a location or upstream when a request is finished, for example, logging competed requests in a remote MySQL database.

#### Installing Third-party Modules

The nginx\_lua module embeds Lua via the standard Lua interpreter or LuaJIT into Nginx. Please note that you need to install Lua or LuaJIT before you can use this module. This module also has a dependency on another Nginx module called ngx\_devel\_kit. It facilitates the development of new Nginx modules. We will have a detailed look at this module in this chapter as well as in *Chapter 5, Creating Your Own Module*, where we will learn to write our own Nginx module.

Using the Lua API for Nginx, you can communicate with upstream servers in a non-blocking manner in your Lua script. The Lua VM is shared across all the requests handled by a single Nginx worker process to minimize memory usage.

It is possible to use a number of upstream Nginx modules with the nginx\_lua module. These modules are as follows:

- lua-resty-memcached
- lua-resty-mysql
- lua-resty-redis
- lua-resty-dns
- lua-resty-upload
- ngx memc
- ngx postgres
- ngx redis2
- ngx redis
- ngx proxy
- ngx fastcgi

An example configuration of the ngx lua module is as follows:

```
# set search paths for pure Lua external libraries (';;' is the
default path):
    lua_package_path '/home/user/?.lua;/scripts/?.lua;;';

# set search paths for Lua external libraries written in C (can
also use ';;'):
    lua_package_cpath '/bar/for/?.so;/blah/blah/?.so;;';

server {
    location /inline_concat {
        # MIME type determined by default_type:
        default type 'text/plain';
```

```
set $a "hello";
set $b "world";
# inline Lua script
set_by_lua $res "return ngx.arg[1]..ngx.arg[2]" $a $b;
echo $res;
}
```

#### **Explaining directives**

Some of the most important directives of ngx\_lua are as follows:

#### lua\_package\_path

The lua\_package\_path directive is used to specify the path of the Lua scripts. This value is used by the directives such as set\_by\_lua and content\_by\_lua.

You can use the special notation \$prefix or \${prefix} in the search path string to indicate the path of the server prefix usually determined by the -p PATH command-line option while starting the Nginx server.

The default value is taken from the LUA\_PATH environment variable. If this variable is not defined, then the default search path is used to locate Lua scripts.

#### set\_by\_lua or set\_by\_lua\_file

The set\_by\_lua or set\_by\_lua\_file directives are used to execute a small embedded and blocked Lua script provided as a string. This script can take two parameters as an input and return the result through a return variable. The Nginx event loop is blocked when this code gets executed. You should, therefore, not use this directive to execute long-running codes.

Note that the following API functions are currently disabled within this context. This directive can only write out a value to a single Nginx variable at a time, as shown in the following code snippet:

```
location /testlua {
    set_by_lua $sum '
        local a = 32
        local b = 56
        return a + b;
-- return the $sum value normally
    ';
    echo "sum = $sum
}
```

#### Installing Third-party Modules

This directive can be freely mixed with all directives of the HttpRewriteModule, HttpSetMiscModule, and HttpArrayVarModule modules. All these directives will be executed in the same order as they appear in the configuration file. An example configuration is given as follows:

```
set $num 32;
set_by_lua $num2 'tonumber(ngx.var.num) + 1';
```

You can freely use the \$ sign inside the Lua scripts provided in this directive as the Nginx variable interpolation is disabled. This directive requires the ngx devel kit module.

The set\_by\_lua\_file directive is similar to the set\_by\_lua directive. The only difference is that the Lua script here is provided in a file. This file can also contain Lua or LuaJIT bytecode instead of a text script.

When a relative path such as path/file.lua is given, it will be turned into an absolute path relative to the server prefix path determined by the -p PATH command-line option while starting the Nginx server.

By default, the Lua code cache is turned on. This means that the script file is loaded the first time. If you make changes, Nginx configuration will be reloaded. If you are in a development cycle, the code cache can be turned off by using the <code>lua\_code\_cache\_off</code> parameter in the configuration file. The following is an example configuration:

```
location /rel_file_concat {
    set $a "foo";
    set $b "bar";
    # script path relative to nginx prefix
    # $ngx_prefix/conf/concat.lua contents:
    #
        return ngx.arg[1]..ngx.arg[2]
    #
    set_by_lua_file $res conf/concat.lua $a $b;
    echo $res;
}
```

#### content\_by\_lua or content\_by\_lua\_file

The content\_by\_lua or content\_by\_lua\_file directives are used to specify a Lua script to execute for every request during the content phase. You can use API calls in this script, and the script is executed in an independent global sandbox.

Since this directive is a content handler, do not use it and the other content handler directives at the same location. For example, this directive and the proxy\_pass directive should not be used at the same location.

The content\_by\_lua\_file directive is equivalent to content\_by\_lua, except that in this directive you have to provide the path to a Lua script file instead of writing inline codes. The code in this file is loaded only once if the code cache is turned on, and the relative paths are resolved to absolute paths using the server prefix. An example configuration is shown as follows:

```
location /request body {
     # force reading request body (default off)
     lua need request body on;
     client max body size 50k;
     client body buffer size 50k;
     content_by_lua 'ngx.print(ngx.var.request_body)';
}
# transparent non-blocking I/O in Lua via subrequests
location /lua {
    # MIME type determined by default type:
    default_type 'text/plain';
    content by lua '
        local res = ngx.location.capture("/some_other_location")
        if res.status == 200 then
            ngx.print(res.body)
        end';
}
```

#### rewrite\_by\_lua or rewrite\_by\_lua\_file

The rewrite\_by\_lua or rewrite\_by\_lua\_file directive executes the Lua code during the rewrite phase. The Lua code can use API calls and is run in a spawned global sandbox.

Note that this handler always runs after the standard HTTP rewrite. So, the following piece of code will not work as expected:

```
location /foo {
    set $a 5; # create and initialize $a
    set $b 13; # create and initialize $b
    rewrite_by_lua 'ngx.var.b = tonumber(ngx.var.a) + 1';
    if ($b = '6') {
        rewrite ^ /bar redirect;
        break;
    }
    echo "res = $b";
}
```

This is because the if condition runs before rewrite\_by\_lua even if it is placed after rewrite by lua in the configuration script.

The correct way of doing this by using Nginx API calls is as follows:

```
location /foo {
    set $a 5; # create and initialize $a
    set $b 13; # create and initialize $b
    rewrite_by_lua '
        ngx.var.b = tonumber(ngx.var.a) + 1
        if tonumber(ngx.var.b) == 6 then
            return ngx.redirect("/bar");
        end
    ';
    echo "res = $b";
}
```

The rewrite\_by\_lua code will always run at the end of the rewrite-request-processing phase unless rewrite\_by\_lua\_no\_postpone is turned on.

The rewrite\_by\_lua\_file directive also runs in the rewrite phase after the standard HTTP rewrite. However, the code is executed from a Lua script file or a bytecode file as shown in the following configuration script:

#### access\_by\_lua or access\_by\_lua\_file

The access\_by\_lua or access\_by\_lua\_file directive executes the Lua code during the access phase. This means that the code in this directive will run once per request, and no subrequest will be able to trigger the code.

The Lua code is run after the standard HttpAccessModule. Therefore, if you have any blacklisted IPs, they will be denied before this code is executed.

You can use these directives to implement more complex access mechanisms, that is, the ones that communicate with upstream servers, such as a database.

Let us now have a look at a sample ngx\_lua configuration to understand the usage of access\_by\_lua:

```
location / {
    access_by_lua '
```

In the preceding example configuration, the Lua code will run the configuration for a defined location called ldap\_auth, which will authenticate the user against an LDAP server, and based on a return value, the request either exits with a proper error code (403) or returns normally.

The access\_by\_lua directive allows you to run a Lua script or bytecode using a file. You need to specify the path of the script file in the directive.

Nginx variables can be used in the file to provide flexibility. This, however, carries some risks, and is not ordinarily recommended.

Relative file paths are converted to absolute paths using the server prefix.

It is recommended that you turn on the code cache in the production environment, so that the Lua code is loaded only once. This can provide performance benefits. However, in a development environment, you should not enable the code cache in order to avoid reloading the server every time there is a code change.

The ngx\_lua module provides complete scripting capabilities while offering very high performance levels. This is especially true if you use the Just In Time (JIT) compilation using LuaJIT. This allows you a very wide range of use-cases where this module can be useful.

# Reverse IP lookup using the GeoIP module (ngx\_http\_geoip\_module)

The ngx\_http\_geoip\_module does a reverse lookup on the IP of the client using the MaxMind IP database. It resolves the IP address to the place of origin and sets a number for the variables.

This module is not built by default; it should be enabled with the --with-http\_geoip\_module configuration parameter. As already mentioned, this module has dependency on the MaxMind GeoIP library.

You need an account with MaxMind and will also need to download several database files that map IP addresses to countries, cities, and even organizations.

One of the key applications, in addition to providing you with more information about the clients, can also be against DDOS attacks. Using the information looked up by this module, you can block or allow traffic coming from countries, cities, regions, and so on. This is a bit crude, but it works. You can use this module as a complement to <code>HttpLimitReqModule</code> and <code>HttpLimitZoneModule</code>. An example configuration is as follows:

#### **Explaining directives**

The following is a list of directives you can use for configuring this module:

#### geoip\_country

The <code>geoip\_country</code> directive allows you to specify the name and path of the database file that contains the IP for a country's lookup information. The following variables are available (as well as set by this module) while using this database:

- \$geoip\_country\_code: This is a two-letter country code, for example, DE or US. These codes correspond to ISO 3166-1 alpha-2 standard.
- \$geoip\_country\_code3: This is a three-letter country code, for example, DEU or USA. These codes correspond to ISO 3166-1 alpha-3 standard.

• \$geoip\_country\_name: This gives the complete country name, for example, Russian Federation or United States.

#### geoip\_city

The geoip\_city directive allows you to set the name and path of a database file to lookup the city's and region's information based on the client's IP address. The following variables are available and set as well while using this database:

- \$geoip\_area\_code: This gives the telephone area code (US only) associated with the client's IP address. This field in the MaxMind database has been depreciated, so you might not get any information or get outdated information.
- \$geoip\_city\_continent\_code: This is a two-letter continent code, for example, EU or AS.
- \$geoip\_city\_country\_code: This is a two-letter country code, for example, DE or US. These codes correspond to ISO 3166-1 alpha-2 standard.
- \$geoip\_city\_country\_code3: This is a three-letter country code, for example, DEU or USA. These codes correspond to ISO 3166-1 alpha-3 standard.
- \$geoip\_city\_country\_name: This gives the country name, for example, Russian Federation or United States.
- \$geoip\_dma\_code: This gives the DMA region code in the US (also known as metro code), which can be found at https://developers.google.com/adwords/api/docs/appendix/cities-DMAregions.
- \$geoip latitude: This gives the latitudinal value of the city.
- \$geoip longitude: This gives the longitudinal value of the city.
- \$geoip\_region: This is a two-symbol country region code (region, territory, state, province, federal land, and the like), for example, 48 or DC.
- \$geoip\_region\_name: This gives the country's region name (region, territory, state, province, federal land, and the like), for example, Bavaria or District of Columbia.
- \$qeoip city: This gives the full city name, for example, Munich or London.
- \$geoip\_postal\_code: This gives the postal code information if available.

#### geoip\_org

The <code>geoip\_org</code> directive allows you to specify the name and path of the database file to resolve the IP address to an organization. This can be a company name or an institution. Normally, this kind of information is available through the <code>whois</code> databases. The following variable is available and set as well while using this option:

• \$geoip\_org: This contains the organization's name, for example, Facebook, Inc.

#### geoip\_proxy

The <code>geoip\_proxy</code> directive allows you to specify the IP addresses or CIDR of the proxy servers that you "trust". If the client IP address matches this trusted address, the IP address sent in the HTTP header <code>X-Forwarded-For</code> is used to do the IP lookup. The <code>X-Forwarded-For</code> header is a standard header that is sent by proxy servers to reveal the real IP address of the client. If the proxy server does not choose to do so, it is essentially an anonymizer. The correctness of the IP sent in this header is purely up to the proxy server; therefore, if you trust a specific proxy server to send correct information, you can use this directive to enable lookup on the IP address sent in the <code>X-Forwarded-For</code> header.

#### geoip\_proxy\_recursive

The geoip\_proxy\_recursive directive allows you to enable recursive IP lookup. If recursive lookup is enabled, the last untrusted address sent in the X-Forwarded-For header will be used for the IP lookup.

If Nginx is working behind a proxy, you can also use HttpRealIpModule. This module allows you to change the client's IP address to a value from the request header (for example, X-Real-IP or X-Forwarded-For).

#### **Doing healthchecks**

Here we will learn about various modules to keep a track of the healthy upstreams.

## ngx\_http\_healthcheck\_module

If your Nginx server works with a lot of upstream servers for providing various services and content, keeping track of which upstream servers are still healthy and working is very important, especially if they are third-party or external servers. This module allows you to keep track of healthy backends.

This is how it works. When an upstream server responds with a 200+ status code, and the response optionally comes back with a body, it is marked as good; otherwise, it is marked as bad. This module also has an HTTP healthcheck page where you can see the current status of the backends. This is quite similar to the haproxy or varnish healthchecks.

This module inserts a healthcheck event into Nginx's event tree. When that triggers, it starts a peer connection with the backend and sends as well as receives data. When the heathcheck is over or gets timed out, it updates the health of the backend in a shared memory area. The following is an example configuration:

```
http {
  upstream check_upstreams {
    server server1.com;
    server server2.com;
    healthcheck enabled;
    healthcheck delay 1000;
    healthcheck timeout 1000;
    healthcheck_failcount 1;
    healthcheck_expected 'BACKEND_ALIVE';
    healthcheck send "GET /health HTTP/1.0" 'Host: www.websitename.
com';
}
. . .
location /health_status {
      healthcheck status;
 }
}
```

#### **Explaining directives**

Some of the most important directives of the ngx\_http\_healthcheck\_module are as follows:

#### healthcheck\_enabled

The healthcheck\_enabled module's context is upstream and enables health checking on the upstream servers defined in the specific upstream block. This, in the preceding example, would be server1 and server2.

Installing Third-party Modules

#### healthcheck\_delay

For each upstream server, the healthcheck\_delay directive defines the delay between two healthchecks. The default value is 1000 ms.

#### healthcheck\_timeout

The healthcheck\_timeout directive defines the timeout value for the healthcheck operation. If the healthcheck operation is taking too long because the backend is slow in responding, the process will stop after the timeout has elapsed. The default value is 2000 ms.

#### healthcheck\_failcount

The healthcheck\_failcount directive gives the number of good or bad healthchecks in a row it takes to switch the current health status (good to bad or bad to good). The default value is 2.

#### healthcheck\_send

The healthcheck\_send directive is a required directive that allows you to decide what to send to do a healthcheck. This can be a simple HTTP GET command or something more complex. Each argument is appended by \r\n and the entire block is suffixed with another \r\n. The following is an example configuration:

```
healthcheck_send 'GET /health HTTP/1.0'
    'Host: www.yourhost.com';
```

Note that you probably want to end your healthcheck with some directive that closes the connection, for example, Connection: close.

#### healthcheck\_expected

The healthcheck\_expected directive allows you to specify what to expect in return from the upstream server as a response to mark it as healthy. Any other response or no response will mark the host as down. This refers to the response in the HTTP body and not the headers. If this directive is missing, a simple response code of 200 will be enough.

#### healthcheck\_buffer

The healthcheck\_buffer directive gives the size of the buffer where the response from the backend will be temporarily stored for checking. Make sure you allocate enough memory not only for the body but also for the headers that you expect to receive back in response.

#### Load balancing

There are a number of third-party Nginx modules available, which allow you to distribute load among upstream servers based on a hashing mechanism or on a least-busy basis. There are various hashing mechanisms available for load balancing, some of which are available via third-party modules. Here, we will just take a brief look at some of the options available to you.

#### **Consistent hashing**

The ngx\_http\_upstream\_consistent\_hash module allows you to load balance using a consistent hash ring. Consistent hashing is a special hashing algorithm that is quite good when you have to rehash frequently because a new machine or server is added or removed from the pool.

This module is compatible with the php-memcached module, and you can store values in the memcached cluster that this module can read from. You can find more details about this module at http://wiki.nginx.org/HttpUpstreamConsistentHash.

There is another similar module that uses the Ketama consistent hashing library to compute a hash on a configuration variable, that is, Request URI. Check out more information about this at http://wiki.nginx.org/HttpUpstreamKetamaCHashModule.

#### Least busy

The ngx\_http\_upstream\_fair\_module module allows you to do load balancing based on which upstream is least busy.

This module also provides a status page where you can view the current status of load balancing.

This module uses **Weighted Least-Connection Round Robin (WLC-RR)** with a number of possible variations. More information on this module is available at http://wiki.nginx.org/HttpUpstreamFairModule.

#### Configuration variable hashing

Configuration variable hashing is probably the most random hashing you can do. You can choose to do a hash on one of the available variables, that is, <code>\$request\_uri</code> or HTTP headers or a combination of both. This module uses CRC-32 to compute the hash on a specified variable.

More information on this is available at http://wiki.nginx.org/ HttpUpstreamRequestHashModule. Installing Third-party Modules

# **Summary**

In this chapter, we looked at various useful third-party Nginx modules that are not distributed with the source code by default. There are many more useful modules available that you can find on GitHub. Please do pay attention to the fact that the module is stable enough to be used in the production environment. Always do some testing first and then carefully move the modules in the production environments. The Nginx community will take no responsibility for any problems that you may encounter as a result of using these modules.

In the next chapter, we will discuss developing our own Nginx module, which will be the first step into the world of custom module development.

# 5 Creating Your Own Module

Nginx allows you to extend functionality by writing new modules in plain C. This chapter gives a brief introduction to creating your own modules. It is a quick reference to the module system in Nginx, and the internal architecture of Nginx, which makes extension possible. It introduces different categories of modules and add-ons you can create at a high level. This chapter will also contain a quick introduction of NDK, a special module in Nginx used as a basis of other modules.

The topics covered are as follows:

- Concept of module chaining and delegation in Nginx
- Handler modules
- Filter modules
- Load balancer modules
- **Nginx Development Toolkit** (**NDK**): The NDK is an Nginx module that is designed to extend the core functionality of the excellent Nginx web server, in a way that can be used as a basis of other Nginx modules
- Sample source code of a custom Nginx module

At the end of this chapter, the advanced users will have an idea about internal Nginx architecture, and what is the basis of creating your own third-party module. Readers should be able to know how to use NDK; the source code will help them see a very simple self-written module in action.

# Nginx module delegation

Nginx has a very modular architecture. All major operations that Nginx performs are carried out by modules. All Nginx modules are built in at compile time and are not loaded dynamically.

#### Creating Your Own Module

Module delegation can also be called **module chaining**. The core pretty much does the basic stuff related to setting up the connection and taking care of things related to the protocol. It then sets up a chain of modules to execute, each taking care of a certain phase or stage of request processing.

The module-based noncentralized architecture makes it possible for advanced users to develop a module that does something they want.

The following are the different types of Nginx modules.

#### **Handlers**

There is a handler for each defined location in the configuration file. When the server starts up, handlers are attached or bound to a location. Ideally there should only be one handler to a location; if there are more than one defined in the configuration file, only one of them will be valid (typically the last one). Handlers end in the following three ways: successfully when all is good, fail when there is an error, or they will not process the request and will let the default handler process it.

#### **Load balancers**

The load balancer or upstream module forwards your requests to one of the many configured backends or upstreams. Nginx, by default, has two load-balancing modules built in: **Round Robin** and the **IP Hash** method (look at ngx\_http\_upstream\_module). There are other third-party modules available that allow you to do load balancing based on various hashing mechanisms, for example, Consistent Hashing.

#### **Filters**

After a handler produces a response, the filters are executed. Filters do the postprocessing on the handler's response. One example can be that you need to compress the response, or add certain headers to it. Multiple filters can associate with each location.

#### Order of execution

The order of execution of Nginx filters is determined when they are compiled. You can see the order of the execution after compiling the code in ngx\_modules.c. This file is generated on the fly by the modules script, which is found at nginx/auto/. This script makes sure that it maintains the correct order of the module and filter execution.

The built-in modules do need a specific order, for example, a gzip filter should run after the header and body filters have been executed. The new custom modules are generally executed in the end.

Filters do not execute in a fully blocked manner, rather the output of the filters is streamed through the chain of filters. By default, one filter processes some data and passes it on to the next module and so on. The amount of data processed at a time is usually a multiple of the page size. Different modules, for example, gzip, allow you to adjust this value.

#### The extended "Hello world" module

Now we will proceed towards creating a simple Nginx module. This module will print a configurable text in your browser whenever you enter a specific location. This is a very simple module and the idea is to just introduce the core concepts of how to create an Nginx module. This is based on and is an enhanced version of the simple Hello world module found at http://blog.zhuzhaoyuan.com/2009/08/creating-a-hello-world-nginx-module/. This module is an example of a handler module.

# Writing and compiling a module

The first thing you have to do is to obviously create a folder for your new module. Create it anywhere other than the Nginx source tree. You should create the following two files to start with:

- config
- ngx http hello module.c

The contents of the config file will depend on what kind of module you are writing.

For this simple module, it will look like the following code:

```
ngx_addon_name=ngx_http_hello_module
HTTP_MODULES="$HTTP_MODULES ngx_http_hello_module"
NGX_ADDON_SRCS="$NGX_ADDON_SRCS $ngx_addon_dir/ngx_http_hello_module.c"
```

The file is quite self-explanatory. In the second line we are adding the module to a list of HTTP modules. Depending on which module type you are writing, you will need to add it to a different list. You can see the full list in the modules script found at nginx/auto/.

Before compiling, the module needs to be explicitly specified using the configure script as in the following code. The add-module list should contain a list of all third-party modules you want to include in the compilation.

```
./configure --add-module=path/to/your/new/module/directory
```

This has to be followed by make and make install as usual.

#### The "Hello world" source code

The following code is from ngx http hello module.c:

```
#include <ngx_config.h>
#include <ngx core.h>
#include <ngx_http.h>
static char *ngx_http_hello(ngx_conf_t *cf, void *post, void
  *data);
static ngx conf post handler pt ngx http hello p = ngx http hello;
 * The structure will hold the value of the
* module directive hello
typedef struct {
            name;
 ngx_str_t
} ngx_http_hello_loc_conf_t;
/* The function which initializes memory for the module configuration
structure
*/
static void *
ngx_http_hello_create_loc_conf(ngx_conf_t *cf)
 ngx_http_hello_loc_conf_t *conf;
 conf = ngx_pcalloc(cf->pool, sizeof(ngx_http_hello_loc_conf_t));
 if (conf == NULL) {
   return NULL;
 return conf;
```

```
/*
 * The command array or array, which holds one subarray for each
module
* directive along with a function which validates the value of the
 * directive and also initializes the main handler of this module
static ngx command t ngx http hello commands[] = {
  { ngx string("hello"),
    NGX HTTP LOC CONF NGX CONF TAKE1,
    ngx_conf_set_str_slot,
    NGX_HTTP_LOC_CONF_OFFSET,
    offsetof(ngx_http_hello_loc_conf_t, name),
    &ngx_http_hello_p },
 ngx null command
};
static ngx_str_t hello_string;
* The module context has hooks , here we have a hook for creating
 * location configuration
static ngx_http_module_t ngx_http_hello_module_ctx = {
                                 /* preconfiguration */
 NULL,
 NULL,
                                 /* postconfiguration */
                                 /* create main configuration */
 NULL,
                                 /* init main configuration */
 NULL,
 NULL,
                                 /* create server configuration */
 NULL,
                                 /* merge server configuration */
 ngx_http_hello_create_loc_conf, /* create location configuration */
 NULL
                                 /* merge location configuration */
};
 * The module which binds the context and commands
ngx_module_t ngx_http_hello_module = {
 NGX_MODULE_V1,
```

#### Creating Your Own Module

```
&ngx http hello module ctx,
                                 /* module context */
 ngx_http_hello_commands,
                                 /* module directives */
 NGX HTTP MODULE,
                                 /* module type */
 NULL,
                                 /* init master */
 NULL,
                                 /* init module */
                                 /* init process */
 NULL,
 NULL,
                                 /* init thread */
 NULL,
                                 /* exit thread */
                                 /* exit process */
 NULL,
                                 /* exit master */
 NULL.
 NGX MODULE V1 PADDING
};
/*
 * Main handler function of the module.
*/
static ngx int t
ngx http hello handler(ngx http request t *r)
 ngx_int_t
             rc;
 ngx buf t *b;
 ngx_chain_t out;
  /* we response to 'GET' and 'HEAD' requests only */
 if (!(r->method & (NGX_HTTP_GET | NGX_HTTP_HEAD))) {
   return NGX HTTP NOT ALLOWED;
  /* discard request body, since we don't need it here */
 rc = ngx_http_discard_request_body(r);
  if (rc != NGX OK) {
   return rc;
  /* set the 'Content-type' header */
  r->headers_out.content_type_len = sizeof("text/html") - 1;
 r->headers_out.content_type.len = sizeof("text/html") - 1;
 r->headers_out.content_type.data = (u_char *) "text/html";
  /* send the header only, if the request type is http 'HEAD' */
 if (r->method == NGX HTTP HEAD) {
   r->headers out.status = NGX HTTP OK;
   r->headers out.content length n = hello string.len;
```

```
return ngx http send header(r);
  /* allocate a buffer for your response body */
 b = ngx_pcalloc(r->pool, sizeof(ngx_buf_t));
 if (b == NULL) {
   return NGX HTTP INTERNAL SERVER ERROR;
  /* attach this buffer to the buffer chain */
 out.buf = b;
 out.next = NULL;
 /* adjust the pointers of the buffer */
 b->pos = hello string.data;
 b->last = hello_string.data + hello_string.len;
 b->memory = 1; /* this buffer is in memory */
 b->last_buf = 1; /* this is the last buffer in the buffer chain
   */
 /* set the status line */
 r->headers out.status = NGX HTTP OK;
 r->headers_out.content_length_n = hello_string.len;
 /* send the headers of your response */
 rc = ngx_http_send_header(r);
 if (rc == NGX ERROR | | rc > NGX OK | | r->header only) {
   return rc;
  }
 /* send the buffer chain of your response */
 return ngx_http_output_filter(r, &out);
}
/*
\star Function for the directive hello , it validates its value
* and copies it to a static variable to be printed later
static char *
ngx http hello(ngx conf t *cf, void *post, void *data)
 ngx_http_core_loc_conf_t *clcf;
```

#### Creating Your Own Module

```
clcf = ngx_http_conf_get_module_loc_conf(cf,
    ngx_http_core_module);
clcf->handler = ngx_http_hello_handler;

ngx_str_t *name = data; // i.e., first field of
    ngx_http_hello_loc_conf_t

if (ngx_strcmp(name->data, "") == 0) {
    return NGX_CONF_ERROR;
}
hello_string.data = name->data;
hello_string.len = ngx_strlen(hello_string.data);

return NGX_CONF_OK;
}
```

A sample configuration for this extended hello world module could look as follows:

```
server {
listen 8080;
server_name localhost;

location / {
hello 'Hello World';
    }
}
```

# Components of the Nginx module

There are many components on an Nginx module depending on the type of the module. We will now discuss those parts that are common to almost all the modules. The intention is to present to you a reference in an easy to understand way so that you can be ready to write your own module.

#### Module configuration structures

Modules can define one configuration for each of the configuration file's configuration contexts—there is an individual structure for the main, server, and location contexts. It is OK for most modules to simply have a location structure. These structures should be named as convention <code>ngx\_http\_<module name>\_(main|srv|loc)\_conf\_t</code>. The following is the code snippet from the sample module:

```
typedef struct {
  ngx_str_t name;
} ngx_http_hello_loc_conf_t;
```

The members of this structure should use Nginx's special data types (ngx\_uint\_t, ngx\_flag\_t, and ngx\_str\_t), which are simply aliases for basic/primitive types. You can look into core/nginx\_config.h in the source tree for the data type definitions.

There should be as many members of this structure as the module directives. In the preceding example our module only has one directive, so we can already tell that this module will support a single directive/option at the location level, which will populate the member name of this structure.

As it must be obvious by now, that the elements in the configuration structure are filled by module directives defined in the configuration file.

#### **Module directives**

After you have defined the place where the value of the module directives will be stored, it is time to define the name of the module directives and what kind and type of arguments they will accept. A module's directives are defined in a static array of the ngx\_command\_t type structure. Looking at the example code we previously wrote, the following is what the directives structure looks like:

The preceding structure may look a little bit complicated. However, we will now look at each one of those to understand them a little better.

The first argument defines the name of the directive. This is of type <code>ngx\_str</code> and is instantiated with the directive name, for example, <code>ngx\_str("hello")</code>. An <code>ngx\_str\_t</code> data type is a struct type with data and length elements. Nginx uses this data structure for all the strings.

The second argument defines the type of the directive, and what kind of arguments it accepts. The acceptable values for these parameters should be bitwise ordered with each other. The possibilities are as follows:

```
NGX_HTTP_MAIN_CONF: directive should be used in main section
NGX_HTTP_SRV_CONF : directive should be used in the server section
NGX HTTP LOC CONF : directive should be used in the location
 section
NGX HTTP UPS CONF : directive should be used in the upstream
 section
NGX CONF NOARGS : directive will take no arguments
NGX CONF TAKE1 : directive will take 1 argument
NGX CONF TAKE2 : directive will take 2 arguments
NGX_CONF_TAKE7 : directive will take 7 arguments
NGX_CONF_TAKE12 : directive will take 1 or 2 arguments
NGX_CONF_TAKE13 : directive will take 1 or 3 arguments
NGX CONF TAKE23 : directive will take 2 or 3 arguments
NGX_CONF_TAKE123 : directive will take 1, 2 or 3 arguments
NGX CONF TAKE1234 : directive will take 1, 2 , 3 or 4 arguments
NGX CONF FLAG : directive accepts a boolean value from "on" or
 "off"
NGX CONF_1MORE : directive requires at least one argument
NGX CONF 2MORE : directive requires at least at least two
  arguments
```

Please see the full details in ngx conf file.h found in the core folder.

The maximum number of arguments that a directive can take is eight (0-7) as defined in core/ngx conf file.h, as shown in the following code:

```
#define NGX_CONF_MAX_ARGS 8
```

In the preceding example, we only use a single element in the array, as we are providing values for a single ngx\_command\_t structure.

The third argument is a function pointer. This is a setup function that takes the value provided for the directive in the configuration file and stores it in the appropriate element of the structure. This function can take the following three arguments:

- Pointer to ngx\_conf\_t (main, srv, or loc) structure, which contains the values of the directive in the configuration file
- Pointer to the target ngx command t structure where the value will be stored
- Pointer to the module's custom configuration structure (can be NULL)

Nginx provides a number of functions that can be used to set the values for the built-in data types. These functions include:

- ngx\_conf\_set\_flag\_slot
- ngx conf set str slot
- ngx\_conf\_set\_str\_array\_slot
- ngx conf set keyval slot
- ngx conf set num slot
- ngx\_conf\_set\_size\_slot
- ngx\_conf\_set\_off slot
- ngx\_conf\_set\_msec\_slot
- ngx conf set sec slot
- ngx conf set bufs slot
- ngx conf set enum slot
- ngx conf set bitmask slot

#### Some of these are described as follows:

- ngx conf set flag slot: This translates on or off to 1 or 0
- ngx conf set str slot: This saves a string as ngx str t
- ngx\_conf\_set\_num\_slot: This parses a number and saves it to an integer
- ngx\_conf\_set\_size\_slot: This parses a data size (5k, 2m, and so on) and saves it to size\_t

Module authors can also pass the pointer to their own function here, if the built-in functions are not sufficient for their purpose, for example, if the string needs to be interpreted in a certain way instead of just being stored as it is.

In order to specify where these built-in (or custom) functions will store the directive values, you have to specify conf and offset as the next two arguments. conf specifies the type of the structure where the value will be stored (main, srv, loc) and offset specifies which part of this configuration structure to store it in. The following is the offset of the element in the structure, that is, offsetof (ngx\_http\_hello loc conf t, name).

The last element is often NULL, and at the moment we can choose to ignore it.

The last element of the command array is ngx\_null\_command, which indicates the termination.

#### The module context

The third structure in an Nginx module that needs to be defined is a static ngx\_http\_module\_t structure, which just has the function pointers for creating the main, srv, and loc configurations, and merging them together. Its name is ngx\_http\_<module name>\_module\_ctx. The function references that you can provide are as follows:

- Pre configuration
- Post configuration
- Creating the main conf
- Initializing the main conf
- Creating the server conf
- Merging it with the main conf
- Creating the location conf
- Merging it with the server conf

These take different arguments depending on what they're doing. The following is the structure definition, taken from http/ngx\_http\_config.h, so you can see the different function signatures of the callbacks:

```
typedef struct {
 ngx_int_t (*preconfiguration)(ngx_conf_t *cf);
 ngx int t
              (*postconfiguration) (ngx conf t *cf);
 void
             *(*create main conf)(ngx conf t *cf);
  char
             *(*init main conf)(ngx conf t *cf, void *conf);
             *(*create_srv_conf)(ngx_conf_t *cf);
 void
 char
             *(*merge srv conf)(ngx conf t *cf, void *prev, void
    *conf);
             *(*create_loc_conf)(ngx_conf_t *cf);
 void
             *(*merge_loc_conf)(ngx_conf_t *cf, void *prev, void
  char
    *conf);
} ngx http module t;
```

You can set functions you don't need to NULL, and Nginx will accept it, and do the right thing.

The create functions such as create main <code>conf</code>, create server <code>conf</code>, and create location <code>conf</code> normally just allocate memory for the structures (such as <code>malloc())</code> and initialize the elements as default values. The functions such as initialize main <code>conf</code>, and merge with main <code>conf</code> provide the opportunity to override the default values.

During merging, the module authors can look for duplicate definitions of elements and throw errors if there is a problem with directives provided by configuration authors in the configuration file.

Most module authors just use the last two elements as such: a function to allocate memory for ngx\_loc\_conf (main, srv, or loc) configuration, and a function to set defaults and merge this configuration into a merged location configuration (called ngx\_http\_<module name >\_merge\_loc\_conf).

The following is an example module context structure:

```
* The module context has hooks , here we have a hook for creating
* location configuration
static ngx http module t ngx http hello module ctx = {
                                 /* preconfiguration */
                                 /* postconfiguration */
 NULL.
 NULL,
                                 /* create main configuration */
 NULL,
                                 /* init main configuration */
 NULL,
                                 /* create server configuration */
                                 /* merge server configuration */
 NULL,
 ngx_http_hello_create_loc_conf, /* create location configuration
 */
 NULL
                                 /* merge location configuration
  */
};
```

We can have a closer look now at these functions, which set up the location based on configuration.

#### create\_loc\_conf

The following is what a basic <code>create\_loc\_conf</code> function looks like. It takes a directive structure (<code>ngx\_conf\_t</code>) and returns a module configuration structure that is newly allocated.

```
/* The function which initializes memory for the module configuration
structure
   */
static void *
ngx_http_hello_create_loc_conf(ngx_conf_t *cf)
{
   ngx_http_hello_loc_conf_t *conf;

   conf = ngx_pcalloc(cf->pool, sizeof(ngx_http_hello_loc_conf_t));
   if (conf == NULL) {
```

#### Creating Your Own Module

```
return NULL;
}
return conf;
}
```

The Nginx memory allocation takes care of freeing the memory if you use the built-ins ngx palloc (a malloc wrapper) or ngx pcalloc (a calloc wrapper).

#### merge\_loc\_conf

The sample module we created does not contain a merge location conf function. However, we can look at the following sample code just to explain some basic concepts. You generally need a merge function if a directive can be defined multiple times. It is your job to define a merge function that can set the appropriate value in case it is defined multiple times or in multiple locations.

```
static char *
 ngx http example merge loc conf(ngx conf t *cf, void *parent,
  void *child)
 ngx http example loc conf t *prev = parent;
 ngx http example loc conf t *conf = child;
 ngx conf merge uint value(conf->val1, prev->val1, 10);
 ngx_conf_merge_uint_value(conf->val2, prev->val2, 20);
  if (conf->val1 < 1) {
    ngx_conf_log_error(NGX_LOG_EMERG, cf, 0,
      "value 1 must be equal or more than 1");
    return NGX_CONF_ERROR;
  if (conf->val2 < conf->val1) {
    ngx_conf_log_error(NGX_LOG_EMERG, cf, 0,
      "val2 must be equal or more than val1");
    return NGX CONF ERROR;
  return NGX_CONF_OK;
```

Nginx provides very useful merging built-in functions for various data types (ngx\_conf\_merge\_<data type>\_value). These functions take the arguments as follows:

- The location's value (can refer to an element in a structure)
- The value to use if the first value is not set
- The default value if both first and second values are not set

The first argument stores the result. See <code>core/ngx\_conf\_file.h</code> for a full list of available merge functions. The following is an extract from the file:

```
#define ngx_conf_merge_value(conf, prev, default) \
  if (conf == NGX_CONF_UNSET) { \
  conf = (prev == NGX_CONF_UNSET) ? default : prev; \
#define ngx_conf_merge_ptr_value(conf, prev, default) \
  if (conf == NGX_CONF_UNSET_PTR) { \
   conf = (prev == NGX CONF UNSET PTR) ? default : prev; \
#define ngx_conf_merge_uint_value(conf, prev, default) \
  if (conf == NGX_CONF_UNSET_UINT) { \
    conf = (prev == NGX_CONF_UNSET_UINT) ? default : prev; \
#define ngx_conf_merge_msec_value(conf, prev, default) \
  if (conf == NGX_CONF_UNSET_MSEC) { \
    conf = (prev == NGX_CONF_UNSET_MSEC) ? default : prev; \
#define ngx conf_merge_sec_value(conf, prev, default) \
  if (conf == NGX CONF UNSET) { \
   conf = (prev == NGX CONF UNSET) ? default : prev; \
#define ngx_conf_merge_size_value(conf, prev, default) \
  if (conf == NGX_CONF_UNSET_SIZE) { \
    conf = (prev == NGX_CONF_UNSET_SIZE) ? default : prev; \
#define ngx_conf_merge_off_value(conf, prev, default) \
  if (conf == NGX CONF UNSET) { \
    conf = (prev == NGX CONF UNSET) ? default : prev; \
#define ngx_conf_merge_str_value(conf, prev, default) \
 if (conf.data == NULL) { \
  if (prev.data) { \
   conf.len = prev.len; \
     conf.data = prev.data; \
    } else { \
   conf.len = sizeof(default) - 1; \
    conf.data = (u_char *) default; \
#define ngx_conf_merge_bufs_value(conf, prev, default_num,
```

#### Creating Your Own Module

```
default_size)
if (conf.num == 0) {
  if (prev.num) {
    conf.num = prev.num; \
    conf.size = prev.size; \
    } else { \
    conf.num = default_num; \
    conf.size = default_size; \
    } \
}
```

As you can see these functions are defined as macros, and they are expanded and placed inline in the code during compilation.

Another thing to learn is how to log errors. The function outputs to the log file using the ngx\_conf\_log\_error function—where you specify a log level—and returns NGX\_CONF\_ERROR, which stops server startup.

There are several log levels defined in Nginx. These are defined in ngx\_log.h. The following is an extract from the code:

```
#define NGX_LOG_STDERR 0
#define NGX_LOG_EMERG 1
#define NGX_LOG_ALERT 2
#define NGX_LOG_CRIT 3
#define NGX_LOG_ERR 4
#define NGX_LOG_WARN 5
#define NGX_LOG_NOTICE 6
#define NGX_LOG_INFO 7
#define NGX_LOG_DEBUG 8
```

### The module definition

The next structure a new module should define is the module definition structure or the ngx\_module\_t structure. The variable is called ngx\_http\_<module name>\_ module. This structure binds together the structures we have been defining until now. You have to provide the pointers to the context and directives structures, as well as the remaining callbacks (exit thread, exit process, and so on). The module definition can act like a key to look up data associated with a particular module. The module definition of our custom module looks as follows:

```
ngx uint t
                       spare1;
ngx_uint_t
                       spare2;
ngx_uint_t
                       spare3;
                       version;
ngx_uint_t
                      *ctx;
void
ngx command t
                      *commands;
ngx_uint_t
                       type;
ngx_int_t
                     (*init_master)(ngx_log_t *log);
ngx int t
                     (*init module) (ngx cycle t *cycle);
ngx int t
                     (*init process) (ngx cycle t *cycle);
ngx int t
                     (*init thread) (ngx cycle t *cycle);
void
                     (*exit_thread) (ngx_cycle_t *cycle);
void
                     (*exit_process) (ngx_cycle_t *cycle);
void
                     (*exit_master) (ngx_cycle_t *cycle);
uintptr t
                       spare hook0;
uintptr_t
                       spare_hook1;
                       spare hook2;
uintptr_t
                       spare_hook3;
uintptr_t
uintptr\_t
                       spare_hook4;
uintptr t
                       spare hook5;
                       spare hook6;
uintptr t
uintptr t
                       spare hook7;
```

You can see that the macros NGX\_MODULE\_V1 and NGX\_MODULE\_V1\_PADDING provide the values for the structure elements before and after the highlighted section in the preceding code. This is a detail we don't need to get into at the moment. For now, look at the following example on how to use them:

```
* The module which binds the context and commands
 */
ngx module t ngx http hello module = {
 NGX MODULE V1,
 &ngx http hello module ctx,
                                  /* module context */
 ngx_http_hello_commands,
                                  /* module directives */
                                  /* module type */
 NGX HTTP MODULE,
                                  /* init master */
 NULL,
                                  /* init module */
 NULL,
 NULL,
                                  /* init process */
 NULL,
                                  /* init thread */
 NULL,
                                 /* exit thread */
 NULL,
                                  /* exit process */
                                 /* exit master */
 NGX MODULE V1 PADDING
};
```

You can see from the comments in the preceding code what each argument means. The first and last elements are the masks that hide the additional structure elements mainly because we don't need them, and they are place holders for the future. We also provide a module type, which in this case is HTTP. Most of the user-defined custom modules will be of this type. You can define other types such as CORE, MAIL, EVENT and so on; however, they are mostly not used as add-on module types.

#### The handler function

The final piece of the puzzle after all the preparation work and configuration structures is the actual handler function which does all the work. The handler function for our sample module is as follows:

```
* Main handler function of the module.
static ngx int t
 ngx http hello handler(ngx http request t *r)
 ngx int t
             rc;
 ngx_buf_t *b;
 ngx_chain_t out;
  /* we response to 'GET' and 'HEAD' requests only */
 if (!(r->method & (NGX HTTP GET NGX HTTP HEAD))) {
   return NGX_HTTP_NOT_ALLOWED;
  /* discard request body, since we don't need it here */
  rc = ngx_http_discard_request_body(r);
  if (rc != NGX_OK) {
   return rc;
  /* set the 'Content-type' header */
  r->headers_out.content_type_len = sizeof("text/html") - 1;
  r->headers out.content type.data = (u char *) "text/html";
  /* send the header only, if the request type is http 'HEAD' */
 if (r->method == NGX HTTP HEAD) {
    r->headers out.status = NGX HTTP OK;
    r->headers_out.content_length_n = hello_string.len;
  return ngx http send header(r);
  /* allocate a buffer for your response body */
 b = ngx pcalloc(r->pool, sizeof(ngx buf t));
```

```
if (b == NULL) {
  return NGX_HTTP_INTERNAL_SERVER_ERROR;
/* attach this buffer to the buffer chain */
out.buf = b;
out.next = NULL;
/* adjust the pointers of the buffer */
b->pos = hello string.data;
b->last = hello_string.data + hello_string.len;
b->memory = 1; /* this buffer is in memory */
b->last_buf = 1; /* this is the last buffer in the buffer chain
/* set the status line */
r->headers_out.status = NGX_HTTP_OK;
r->headers_out.content_length_n = hello_string.len;
/* send the headers of your response */
rc = ngx_http_send_header(r);
if (rc == NGX_ERROR || rc > NGX_OK || r->header_only) {
  return rc;
/* send the buffer chain of your response */
return ngx_http_output_filter(r, &out);
```

There are a few things to learn in the code. As explained earlier, this module basically prints whatever you had provided in the configuration. For example, according to the following configuration, this module will make sure that it prints **Hello World** whenever you open http://localhost:8080:

```
server {
listen 8080;
server_name localhost;
location / {
hello 'Hello World';
    }
}
```

#### Creating Your Own Module

This method receives the HTTP request as an argument. If your module only responds to a certain type of HTTP requests, you can check by looking at the HTTP request structure. For example, our module only responds to HTTP GET and HEAD requests as checked by this chunk of code; otherwise it returns "error code 405 (not allowed)".

All the HTTP error codes are defined in ngx http request.h as follows:

```
/* we response to 'GET' and 'HEAD' requests only */
if (!(r->method & (NGX_HTTP_GET|NGX_HTTP_HEAD))) {
   return NGX_HTTP_NOT_ALLOWED;
}
```

Next, we discard the request body as in this module we don't need it. In several modules, one will write a body that will be important, however, right now we don't care about it. By discarding the request body, Nginx will not read the request body fully for processing and will not allocate memory for it internally.

Next we set some HTTP headers in our response. All headers you can set in the response can be accessed through the headers\_out member of the HTTP request structure. The headers\_out structure allows you to set a number of outgoing headers. The extract from ngx http request.h is as follows:

```
typedef struct {
 ngx list t
                                     headers;
 ngx_uint_t
                                     status;
                                     status line;
 ngx str t
 ngx_table_elt_t
                                    *server;
 ngx table elt t
                                    *date;
 ngx table elt t
                                    *content_length;
                                    *content_encoding;
 ngx_table_elt_t
 ngx table elt t
                                    *location;
 ngx table_elt_t
                                    *refresh;
                                    *last_modified;
 ngx_table_elt_t
 ngx table elt t
                                    *content range;
                                    *accept ranges;
 ngx table elt t
                                    *www authenticate;
 ngx_table_elt_t
 ngx table elt t
                                    *expires;
 ngx_table_elt_t
                                    *etag;
 ngx_str_t
                                    *override_charset;
  size t
                                     content_type_len;
 ngx_str_t
                                     content_type;
```

The next important step in our module is allocating memory for the response buffer. This memory should be allocated using Nginx's own APIs as mentioned in earlier chapters (since it also automatically takes care of freeing it). This can be done because the memory is allocated from a local memory pool, so that all memory allocations are tracked.

The response is created in a linked list or *chain* of buffers, each of which is of the size of ngx\_buf\_s. This allows Nginx to process the response in a parallel way. If there are other handlers or filters that need to postprocess the response, they can start their work as soon as the first buffer in the chain is ready, while you are filling up the second buffer. This allows Nginx to keep operating in a parallel fashion without waiting for any module to completely finish processing first.

When you are finished with creating the response in the last buffer, you should set b->last\_buf = 1. This, as it is obvious from the name, will tell Nginx that this is the last response buffer from your module.

If the response processing was successful, you would want to set the status of the response header to http\_ok. This is done by r->headers\_out.status = NGX\_HTTP\_OK.

You will then need to initiate the chain of header filters by calling ngx\_http\_send\_header. This will indicate to Nginx that processing of the output headers has finished, and now Nginx can pass them to a chain of filters, which might want to do further postprocessing to the headers.

The final step is returning from the function by calling ngx\_http\_output\_filter. This will initiate the process of the HTTP body filter chain. That is, Nginx or custom filter modules that might have been installed to do postprocessing on the HTTP response body you have just created in the buffer.

The summary of creating the Nginx custom module can be as follows:

- 1. Create a module configuration that is structured either for location, main, or server; each with a specific naming convention (see ngx\_http\_hello\_loc\_conf\_t).
  - The allowed directives of the module are in a static array of typengx\_command\_t (see ngx\_http\_hello\_commands). This will also have the function's pointers that will have the code to validate the value of each directive as well as initialize the handler.
- 2. Create a module context struct such as ngx\_http\_<module name>\_module\_ctx of type ngx\_http\_module\_t which has a bunch of hooks for setting up configuration. Here you can have the post configuration hook, for example, to set up the main handler of your module (see ngx http hello module ctx).
- 3. Then we do the module definition, which is also a struct of type ngx\_module\_t and contains references to the module context and module commands that you created in the previous steps (see ngx\_http\_hello\_module).
- 4. Create the main module handler function that processes the HTTP request. This function also outputs the response headers and body in a series of fixed size buffers.

## Nginx Development Toolkit (NDK)

NDK is an Nginx module that makes it easier for the module developers to develop Nginx modules. As you have seen in this chapter so far, there are certain generic tasks that are repetitive as you are developing modules. NDK provides you with some built-in macros and functions that will reduce the amount of code you will have to write to develop a module.

In order to use NDK, you will have to add it as a module just like any other module. If you wish to use the macros and functions provided by this module, you will have to include the ndk. h file in your module source as well.

NDK provides useful utilities such as conf set functions for complex types such as paths and regular expressions, utility methods for NULL checking, returning values, and setting data to zero.

NDK also includes an **Auto Lib Core** that allows the developers and users to include external libraries in Nginx in a consistent, cross-platform manner.

You can see more details and documentation at https://github.com/simpl/ngx\_devel kit.

### **Summary**

In this chapter we have learned the process of creating a simple Nginx handler module. We also looked at which basic structures a new module should define, and how to link them to each other. Finally, we looked at a small handler function that does a basic task, but provides you the basis of writing a much more complicated module.

If you are an Nginx module developer, you must extensively browse other modules and Nginx source code, which will help you learn how to do different things within your code and which API to use in general.

You will also find Nginx Development Kit at https://github.com/simpl/ngx\_devel\_kit. This will provide you additional conf\_set functions for regexes, complex/script values, paths, and macros to simplify tasks such as checking for NULL values when doing ngx\_array\_push and much more, which will simplify your life while writing custom Nginx modules.

# Index

### **Symbols**

--conf-path=path 10
--error-log-path=path 10
--group=name 10
--http-log-path=path 10
--pid-path=path option 10
--prefix=path 10
--sbin-path=path 10
--user=USER 10
--with-debug 13
--with-http\_ssl\_module option 11
--without-http\_gzip\_module option 11
--without-http\_rewrite\_module option 11
--without-http\_rewrite\_module option 11
--with-pcre-jit option 12
--with-pcre=path option 12

#### Α

accept\_mutex\_delay directive 20 accept\_mutex directive 20 access\_by\_lua directive 74, 75 access\_by\_lua\_file directive 74, 75 access\_log directive 44 add\_header directive 45 aio directive 31 alias directive 31 auth\_basic directive 33 auth\_basic\_user\_file directive 33 auth digest directives 65 auth digest expires directives 65 auth digest replays directives 65 auth digest timeout directives 65 auth\_digest\_user\_file directives 65 Auto Lib Core 105

#### В

# **Binary Distribution**FreeBSD 7

installing 5 Official Win32 binaries 8 OpenBSD 8

#### Binary Distribution installation

CentOS 6
Fedora 6
RedHat 6
break directive 46

#### C

#### compilation controls

--with-cc-opt=parameters 12

configuring options

compilation controls 12

custom module 13

debugging 13

event loop 11

files and permissions 10

optional modules 11, 12

parameter usage examples 12

content\_by\_lua directive 72, 73

content\_by\_lua\_file directive 72, 73

content\_by\_lua or content\_by\_lua\_file

directive 73

create\_loc\_conf function 95, 96

#### D

daemon directive 16 debug\_connection directive 20 debug-enabled option 20 debug\_points directive 17

default_server parameter 27	drizzle_query 62
devpoll_changes directive 21	drizzle_recv_cols_timeout 63
devpoll_events directive 21	drizzle_recv_rows_timeout 63
directives, Events module	drizzle_send_query_timeout 63
accept_mutex 20	drizzle_server 61, 62
accept_mutex_delay 20	drizzle_pass directive 63
debug_connection 20	drizzle_query directive 62
devpoll_changes 21	drizzle_recv_cols_timeout directive 63
devpoll_events 21	drizzle_recv_rows_timeout directive 63
epoll_events 21	drizzle_send_query_timeout directive 63
kqueue_changes 21	drizzle_server directive 61, 62
kqueue_events 21	dribble_server directive oi, oz
multi_accept 22	E
rtsig_overflow_events 22	_
rtsig_overflow_test 22	env directive 19
rtsig_overflow_threshold 22	epoll_events directive 21
rtsig_signo 22	error_page directive 31
use 23	event loop 11
worker connections 23	Events module
directives, Main module	accept_mutex 19
daemon 16	accept_mutex_delay 19
debug_points 17	debug_connection 19
env 19	devpoll_changes 19
lock_file 17	devpoll_events 19
	directives 20
master_process 16	epoll_events 20
pid 17	kqueue_changes 20
timer_resolution 16	kqueue_events 20
user 17	multi_accept 20
worker_cpu_affinity 18	rtsig_overflow_events 20
worker_priority 18	rtsig_overflow_test 20
worker_processes 17	rtsig_overflow_threshold 20
worker_rlimit_core 18	rtsig_signo 20
worker_rlimit_nofile 18	use 20
worker_rlimit_sigpending 18	worker_connections 20
working_directory 19	expires directive 45
drizzle_buffer_size directive 64	extended hello world module
drizzle_connect_timeout directive 63	about 85
drizzle_module_header directive 64	Hello world source code 86, 90
drizzle-nginx module	
about 61	modules 85, 86
directives 61-64	Nginx module, components 90
drizzle-nginx module, directives	writing 85, 86
drizzle_buffer_size 64	F
drizzle_connect_timeout 63	Г
drizzle_keepalive 62	fastcgi_param parameter 50
drizzle_module_header 64	filters
drizzle_pass 63	about 84
	about 01

order of execution 84, 85	gzip_buffers directive 42
flag parameter 48	gzip_comp_level directive 42
FreeBSD 7	gzip directive 42
_	gzip_disable directive 42
G	gzip_http_version directive 42
	gzip_min_length directive 43
geoip_city directive 77	gzip_proxied directive 43
geoip_country directive 76,77	gzip_types directive 43
geoip_org directive 78	using 42
geoip_proxy directive 78	HttpHeadersModule
geoip_proxy_recursive directive 78	about 45
GPG error 6	add_header directive 45
gzip_buffers directive 42	directives 45
gzip_comp_level directive 42	expires directive 45
gzip_disable directive 42	HttpLimitConnModule
gzip_http_version directive 42	directives 54
gzip_min_length directive 43	limit_conn directive 54
gzip_proxied directive 43	limit_conn_log_level directive 54
gzip_types directive 43	limit_conn_status directive 54
	limit_conn_zone directive 54
Н	using 53
handler (	HttpLimitReqModule
handler function 100-103 handlers 84	about 52
	directives 52, 53
healthcheck_buffer directive 80	HttpLogModule
healthcheck_delay directive 80	access_log directive 44
healthcheck_enabled directive 79	directives 44
healthcheck_enabled module 79	log_format directive 44
healthcheck_expected directive 80	using 43
healthcheck_failcount directive 80	HttpMemcachedModule
healthcheck_send directive 80	directives 51
healthcheck_timeout directive 80	memcached_buffer_size directive 51
HttpAccessModule 32	memcached_connect_timeout directive 51
HttpBasicAuthModule	memcached_next_upstream directive 51
auth_basic directive 33	memcached_pass directive 51
auth_basic_user_file directive 33 directives 33	memcached_read_timeout directive 51
	memcached_send_timeout directive 51
using 33	using 50
HttpCoreModule	HttpProxyModule
about 25	directives 36-41
directives 26-31	proxy_cache directive 41
HttpCoreModule, directives server 26	proxy_connect_timeout directive 38
	proxy_next_upstream directive 38
server_name 26	proxy_pass directive 36
HttpFastcgiModule	proxy_pass_header directive 38
using 50	proxy_redirect directive 39
HttpGzipModule	proxy_set_header directive 39
directives 42, 43	r

proxy_store directive 40	ngx_http_upstream_consistent_hash
using 36	module 81
HttpRewriteModule	ngx_http_upstream_fair_module module
break directive 46	81
directives 46-49	variable hashing, configuring 81
if directive 46, 47	location directive 28
rewrite directive 48	lock_file directive 17
rewrite_log directive 49	log_format directive 44
set directive 49	lua_package_path directive 71
using 46	<b>-1</b> 0 -1
HttpUpstreamModule	M
directives 34-36	
ip_hash directive 34	Main module
server directive 35	daemon 15
upstream directive 35	debug_points 15
using 34	directives 16
using of	env 15
1	lock_file 15
•	master_process 15
if directive 46	pid 15
ip_hash directive 34	timer_resolution 15
IP Hash load-balancing modules 84	user 15
8	worker_cpu_affinity 15
K	worker_priority 15
	worker_processes 15
keepalive_disable directive 32	worker_rlimit_core 15
keepalive_timeout directive 32	worker_rlimit_core 15 worker_rlimit_nofile 15
kqueue_changes directive 21	worker_rlimit_sigpending 15
kqueue_events directive 21	
1 –	working_directory 15 master_process directive 16
L	Memcached 50
_	
limit_conn directive 54	memcached_buffer_size directive 51
limit_conn_log_level directive 54	memcached_connect_timeout directive 51
limit_conn_status directive 54	memcached_next_upstream directive 51
limit_conn_zone directive 54	memcached_pass directive 51
limit_req directive 52	memcached_read_timeout directive 51
limit_req_log_level directive 53	memcached_send_timeout directive 51
limit_req_zone directive 53	merge_loc_conf function 96, 98
listen directive	module chaining 84
about 27	module context
default_server parameter 27	about 94, 95
listen parameter 27	create_loc_conf function 95, 96
load balancers 84	example 95
load balancing	function references 94
about 81	merge_loc_conf function 96, 97, 98
about or	module definition 98-100
	multi_accept directive 22

N	post action 69
	post read 69
NDK	pre-access 69
about 83, 104	server rewrite 69
Auto Lib Core 105	server selection 69
Nginx	try files 69
about 83	nginx -V command 14
Events module 19	Nginx yum repository
installing, on Gentoo 13	adding, for CentOS 6
installing, on MacOSX 13	adding, for RHEL 6
Main module 15	official Debian/Ubuntu packages 6
modules, delegating 83	ngx_conf_log_error function 98
nginx.conf file 14	ngx_conf_set_flag_slot function 93
Nginx custom module	ngx_conf_set_num_slot function 93
creating 104	ngx_conf_set_size_slot function 93
Nginx Development Toolkit. See NDK	ngx_conf_set_str_slot function 93
Nginx library	ngx_http_auth_digest module
dependencies 9	about 64
nginx_lua module	directives 64,65
directives 71-75	ngx_http_auth_digest module, directives
rewrite_by_lua_file directive 73	auth_digest 65
upstream Nginx modules, using 70	auth_digest_expires 65
nginx_lua module, directives	auth_digest_replays 65
access_by_lua 75	auth_digest_timeout 65
access_by_lua directive 74	auth_digest_user_file 65
content_by_lua 72	ngx_http_geoip_module
lua_package_path 71	directives 76-80
rewrite_by_lua directive 73	using, for reverse IP lookup 76, 79
set_by_lua 71, 72	using, for reverse IP lookup 77-80
Nginx module, components	ngx_http_healthcheck_module 78, 79
configuration structures 90	ngx_http_upstream_consistent_hash
directives 91-93	module 81
handler function 100-103	ngx_lua module
module context 94	features 68
module definition 98-100	Nginx request-handling phases 69
Nginx modules	ngx_pagespeed module
about 83, 84	Beacon handler, configuring 67
filters 84	console handler, configuring 67
handlers 84	handlers, configuring 67, 68
load balancers 84	message handler, configuring 67
Nginx PPA 7	optimizations 66
Nginx request-handling phases	speeding up 66
access 69	statics handler, configuring 67
content 69	ngx_postgres module
location rewrite 69	about 58
location selection 69	directives 58-60
log 69	

ngx_postgres module, directives	proxy_pass_header directive 38
postgres_connect_timeout 60	proxy_redirect directive 39
postgres_escape 60	proxy_set_header directive 39
postgres_keepalive 59	proxy_store directive 40
postgres_output 60	
postgres_pass 59	R
postgres_query 59	
postgres_result_timeout 60	Resty DBD Stream (RDS) 58
postgres_rewrite 59	return directive 47
postgres_server 58	rewrite_by_lua directive 73,74
postgres_set 60	rewrite_by_lua_file directive 73, 74
1 0 =	rewrite directive 48
0	rewrite_log directive 49
	Round Robin load-balancing modules 84
official Debian/Ubuntu packages	rtsig_overflow_events 22
for Debian 6 7	rtsig_overflow_test directive 22
for Ubuntu 10.04 7	rtsig_overflow_threshold directive 22
for Ubuntu 12.10 6	rtsig_signo directive 22
for Ubuntu PPA 7	
official Win32 binaries 8	S
OpenBSD 8	
optional modules	select() method 11
with-http_ssl_module option 11	sendfile directive 30
without-http_gzip_module option 11	sendfile_max_chunk 30
without-http_proxy_module option 11	server directive
without-http_rewrite_module option 11	about 26, 35
with-pcre-jit option 12	down parameter 35
with-pcre=path option 12	fail_timeout parameter 35
• •	max_fails parameter 35
P	weight parameter 35
	server_name directive
php-memcached module 81	about 26
pid directive 17	aio 31
postgres_connect_timeout directive 60	alias 31
postgres_escape directive 60	error_page 31, 32
postgres_keepalive directive 59	keepalive_disable 32
postgres_output directive 60	keepalive_requests 32
postgres_pass directive 59	keepalive_timeout 32
PostgreSQL. See ngx_postgres module	listen 27
postgres_query directive 59	location 28
postgres_result_timeout directive 60	resolver/resolver_timeout 30
postgres_rewrite directive 59, 60	root 30
postgres_server directive 58	sendfile 30
postgres_set directive 60	sendfile_max_chunk 30
proxy_cache directive 41	server_names_hash_bucket_size 29
proxy_connect_timeout directive 38	server_names_hash_max_size 29
proxy_next_upstream directive 38	tcp_nodelay/tcp_nopush 30
proxy_pass directive 36	

server\_names\_hash\_bucket\_size directive 29
server\_names\_hash\_max\_size directive 29
set\_by\_lua directive 71, 72
set\_by\_lua\_file directive 71, 72
set directive 49
source distribution
installing 8, 9
source distribution installation
configuring options 10
Nginx installation, verifying 14
Nginx, installing on other platforms 13
Nginx library dependencies 9

#### T

tcp\_nodelay directive 30
tcp\_nopush directives 30
third-party modules
compiling 57
drizzle-nginx module 61
drizzle-nginx module , communicating 61
MySQL, communicating 61
ngx\_http\_auth\_digest module 64
ngx\_http\_geoip\_module 76
ngx\_http\_healthcheck\_module 78, 79
ngx\_lua module 68, 70

ngx\_pagespeed module, speeding up 66 ngx\_postgres, communicating 58 timer\_resolution directive 16

#### U

uninitialized\_variable\_warn directive 49 upstream directive 35, 36 use directive 23 user directive 17

#### W

Weighted Least-Connection Round Robin
(WLC-RR) 81
worker\_connections 23
worker\_cpu\_affinity directive 18
worker\_priority directive 18
worker\_processes directive 17
worker\_rlimit\_core directive 18
worker\_rlimit\_nofile directive 18
worker\_rlimit\_sigpending directive 18
working\_directory directive 19



# Thank you for buying Nginx Module Extension

### **About Packt Publishing**

Packt, pronounced 'packed', published its first book "*Mastering phpMyAdmin for Effective MySQL Management*" in April 2004 and subsequently continued to specialize in publishing highly focused books on specific technologies and solutions.

Our books and publications share the experiences of your fellow IT professionals in adapting and customizing today's systems, applications, and frameworks. Our solution based books give you the knowledge and power to customize the software and technologies you're using to get the job done. Packt books are more specific and less general than the IT books you have seen in the past. Our unique business model allows us to bring you more focused information, giving you more of what you need to know, and less of what you don't.

Packt is a modern, yet unique publishing company, which focuses on producing quality, cutting-edge books for communities of developers, administrators, and newbies alike. For more information, please visit our website: www.packtpub.com.

### **About Packt Open Source**


In 2010, Packt launched two new brands, Packt Open Source and Packt Enterprise, in order to continue its focus on specialization. This book is part of the Packt Open Source brand, home to books published on software built around Open Source licences, and offering information to anybody from advanced developers to budding web designers. The Open Source brand also runs Packt's Open Source Royalty Scheme, by which Packt gives a royalty to each Open Source project about whose software a book is sold.

### Writing for Packt

We welcome all inquiries from people who are interested in authoring. Book proposals should be sent to author@packtpub.com. If your book idea is still at an early stage and you would like to discuss it first before writing a formal book proposal, contact us; one of our commissioning editors will get in touch with you.

We're not just looking for published authors; if you have strong technical skills but no writing experience, our experienced editors can help you develop a writing career, or simply get some additional reward for your expertise.






#### **Instant Nginx Starter**

ISBN: 978-1-78216-512-5 Paperback: 48 pages

Implement the nifty features of nginx with this focused guide

- Learn something new in an Instant! A short, fast, focused guide delivering immediate results
- 2. Understand Nginx and its relevance to the modern web
- 3. Install Nginx and explore the different methods of installation
- 4. Configure and customize Nginx



# Nginx HTTP Server Second Edition


ISBN: 978-1-78216-232-2 Paperback: 318 pages

Make the most of your infrastructure and serve pages faster than ever with Nginx

- 1. Complete configuration directive and module reference
- 2. Discover possible interactions between Nginx and Apache to get the best of both worlds
- 3. Learn to configure your servers and virtual hosts efficiently
- 4. A step-by-step guide to switching from Apache to Nginx

Please check www.PacktPub.com for information on our titles






#### **Mastering NGINX**

ISBN: 978-1-84951-744-7 Paperback: 322 pages

An in-depth guide to configuring NGINX for any situation, including numerous examples and reference tables describing each directive

- An in-depth configuration guide to help you understand how to best configure NGINX for any situation
- 2. Includes useful code samples to help you integrate NGINX into your application architecture
- Full of example configuration snippets, bestpractice descriptions, and reference tables for each directive



# web2py Application Development Cookbook

ISBN: 978-1-84951-546-7 Paperback: 364 pages

Over 110 recipes to master this full-stack Python web framework

- Take your web2py skills to the next level by dipping into delicious, usable recipes in this cookbook
- 2. Learn advanced web2py usage from building advanced forms to creating PDF reports
- 3. Written by developers of the web2py project with plenty of code examples for interesting and comprehensive learning

Please check www.PacktPub.com for information on our titles