# Finding Shortest Vector using Quantum NV Sieve on Grover

Hyunji Kim<sup>1</sup>, Kyoungbae Jang<sup>1</sup>, Yujin Oh<sup>1</sup>, Woojin Seok<sup>2</sup>, Wonhuck Lee<sup>2</sup>, Kwangil Bae<sup>2</sup>, Ilkwon Sohn<sup>2</sup>, and Hwajeong Seo<sup>1</sup>

IT Department, Hansung University<sup>1</sup>
Korea Institute of Science and Technology Information (KISTI)<sup>2</sup>

### **Motivation and Contribution**

#### Motivation

- While the most of research has focused on the potential impact of Grover's algorithm on symmetric key cryptography,
   the field of quantum attacks on lattice-based cryptography on Grover's search remains underexplored.
- There is a solution search part of the Sieve algorithm to solve the Shortest Vector Problem.
- Let's apply Grover's search here and get the quantum advantage.

#### Contribution


- For the first time in our knowledge, Quantum NV Sieve implementation to solve SVP.
- Extension implementation considering multiple conditions (dimension, rank) of lattice-based cryptography.
- Resource estimation for Quantum NV Sieve logic and Grover's search.


# **Background**


: Grover's search, Lattice, SVP, Sieve algorithm

### **Grover's Search**

- Grover's search algorithm
  - For a task with a complexity of k-bit, Classical and Grover's search can find a solution with the complexity:  $O(2^k)$  (Classical) /  $O(\sqrt{2^k})$  (Quantum)
  - The search target exists in a state of quantum superposition.
    - → A state in which all search targets exist simultaneously as a probability.
  - Grover's search has two modules:
    - 1. Oracle: Return the solution (i.e. Logic for deriving solutions)
    - 2. Diffusion operator: Increases the probability of the returned solution.
  - Increases the probability of a solution through repetition of Oracle and Diffusion operator ( $\sqrt{2^k}$ )







$$f(x) = \begin{cases} 1 \text{ if } Oracle_{\psi(n)} = Solution \\ 0 \text{ if } Oracle_{\psi(n)} \neq Solution \end{cases}$$

### **Lattice and Basis**


- Lattice (L): a set of points made up of a linear combination of basis vectors (B).
- x is an integer, and  $(b_1, ..., bn)$  means the basis vector.

$$L(b_1, ..., b_n) = \sum_{i=1}^{n} (x_i \cdot b_i, x_i \in Z)$$

- Lattice has two elements: Rank (n) and Dimension (m)
  - Rank: the number of vectors constituting the basis vector
    - Rank=  $3 \rightarrow (00_{(2)}, 10_{(2)}, 11_{(2)})$
  - **Dimension**: the length of each vector
    - Dimension =  $4 \rightarrow (0000_{(2)}, 0100_{(2)}, 1100_{(2)})$
  - Generally, a full-rank lattice is used (m = n).
  - In Lattice-based Cryptography :  $m, n \ge 500$

# **Lattice and Basis**

- There are several **basis** for representing a **lattice**.
  - The basis vectors on the same lattice are different.



### Good and bad basis

#### Good basis vs bad basis

Generally composed of a short vector

Finding a good basis from a bad basis becomes a very difficult task.

Created by multiplying the good basis by a matrix such as an unimodular matrix several times.

Finding a bad basis from a good basis is easy because only matrix multiplication several times is required.




- In lattice-based cryptography:
  - a bad basis is used as the public key
  - a good basis is used as the private key
- The two basis are basis vectors that generate the same lattice.
- Constructing the public and private keys in this way makes it difficult to decrypt messages
  in lattice-based encryption.

# **Shortest Vector Problems (SVP)**

- The problem of finding the shortest vector on a lattice that is not a zero vector.
- Miklo's Ajtai [8] revealed that SVP is an NP-hard problem.
- Lattice-based cryptography is based on lattice problems (SVP, CVP, etc.)
  - The security level of lattice-based cryptography is based on the difficulty of solving the lattice problem.
- Solving SVP → lattice-based cryptosystems such as LWE can be threatened.
- Difficulty
  - If a bad basis vector is used as input, the difficulty of solving the SVP increases. → Hard
  - If a good basis is used as an input, there is a high possibility that the shortest vector will be included in the already input good basis. → Easy
  - Additionally, as the rank (n) and dimension (m) of the lattice increases, it becomes more difficult to solve.

### Lattice cryptanalysis and Shortest Vector Problems

After reducing the range of lattice through approximation in a high dimension, SVP is solved by performing the exact method with the reduced vectors as input.



- We have to solve SVP for Lattice cryptanalysis
  - In high dimensions, use the Approximate method for range reduction
  - In low dimension, use the Exact algorithm for finding the exact shortest vector
  - The best practical/theoretical SVP solution must be accurate and efficient in low dimensions.
  - After accurately solving the SVP in the lower dimensions, it is important to determine the highest dimension that can be solved.

# Survey on the exact algorithms for SVP

Well-known exact algorithms include AKS [11] and NV Sieve [12].

#### AKS


- The most famous early exact algorithm
- But it has the disadvantage of using many parameters and having high time and space complexity.
- It is deemed an impractical algorithm (due to the absence of optimal parameters and actual implementation)

#### NV Sieve

- An exact algorithm, was introduced to address these limitations of AKS.
- It offers benefits such as reduced time / space complexity and practicality
- The possibility for actual implementation and evaluation.
- Additionally, building upon the NV Sieve algorithm, several Sieve algorithms, including the List Sieve and Gaussian Sieve, have been presented [13,14,15,16,17].
- Only the theoretical complexity of the Sieve algorithm on quantum computers (using Grover's search)
  has been calculated [7].

# **NV Sieve Logic**

- Purpose: In order to avoid loss for short vectors, we randomly select c to reduce the range and obtain vectors shorter than γR.
- **Input**: Vector on the lattice with maximum length *R*
- Output: Vectors on the lattice shorter than  $\gamma R$
- Logic of NV Sieve
  - 1. Maximum length among vectors in  $S \rightarrow R$ Initiate C, S'
  - 2. Vectors with a length shorter than  $\gamma R$  are stored in S'.
  - 3. Vectors with a length longer than  $\gamma R$  are subtracted from the point c,
    - stored in S' if the length is shorter than γR
    - stored in C if the length is longer than  $\gamma R$ .
  - 4. Return S'




- That is, when a short vector that satisfies the conditions is found, it is stored in S' and then moved to the next input.
  - $\rightarrow$  Finding c has a significant impact on the complexity of the NV Sieve.
    - We do not know the many points that can be c
    - We do not know if any of them satisfy the conditions.

# **Quantum NV Sieve**


: Proposed method

# **Overview of Proposed Method**

SVP, NV Sieve, Lattice, Grover's search



**How to solve SVP** on Quantum Computer



- Through Grover's search, we can simultaneously search for c that satisfies the condition.
  - However, there may be multiple short vectors that satisfy the condition.
  - Therefore, since it is a task with multiple solutions, the number of Grover's iterations needs to be considered.

# **Overview of Proposed Method**

#### Overall Process of proposed method

- Input setting
- 2. Upscaling
- 3. Two's complement for the positive number
- 4. Addition
- Two's complement for the negative number
- 6. Duplicate qubit for squaring
- 7. Squaring
- 8. Addition for squared results
- Two's complement for the positive number
- 10. Addition for size comparison between  $((rR)^2)$  and  $(||v-c||^2)$


```
Algorithm 3: The quantum NV Sieve on the quantum circuit.
Input: Quantum circuit (QNV), A subset S in L and sieve factor \gamma (\frac{2}{3} < \gamma < 1)
Output: c_0, c_1
 1: Initiate quantum registers and classical registers. ▷ carry, qflag, sqr_result, etc.
 2: // Input setting (Each vector is allocated 3 qubits to address the overflow)
 3: v_0, v_1 \leftarrow \text{Data load from memory qubits}
 4: QNV.Hadamard(c0)
 5: QNV.Hadamard(c<sub>1</sub>)
 6: QNV.x(sqr_rR[i])
                                                                                       \triangleright 0 \le i < 6
 7: // To address the overflow of target qubits
 8: vflag[0] \leftarrow QNV.cx(v_0[1], vflag[0])
 9: v_0[2] \leftarrow QNV.cx(vflag[0], v_0[2])
10: cflag[0] \leftarrow QNV.cx(c_0[1], cflag[0])
11: c_0[2] \leftarrow QNV.cx(cflag[0], c_0[2])
12: vflag[1] \leftarrow QNV.cx(v_1[1], vflag[1])
13: v_1[2] \leftarrow QNV.cx(vflag[1], v_1[2])
14: cflag[1] \leftarrow QNV.cx(c_1[1], cflag[1])
15: c_1[2] \leftarrow QNV.cx(cflag[1], c_1[2])
16: // Two's complement for subtraction using adder
17: c_0 \leftarrow \text{Two's complement}(QNV, c_0, qflag0, zero)
18: c_1 \leftarrow \text{Two's complement}(QNV, c_1, qflag1, zero)
19: //v + \bar{c}
20: c_0 \leftarrow Addition(QNV, v_0, c_0, carry)
21: c_1 \leftarrow Addition(QNV, v_1, c_1, carry)
22: // Two's complement for correct squaring
23: c_0 \leftarrow \text{Two's complement\_negative}(QNV, c_0, qflag2, carry, zero)
24: c_1 \leftarrow \text{Two's complement\_negative}(QNV, c_1, qflag3, carry, zero)
25: // Duplicating qubit for squaring
26: dup_{-}c_0 \leftarrow QNV.cx(c_0, dup_{-}c_0)
27: dup_{-}c_1 \leftarrow QNV.cx(c_1, dup_{-}c_1)
28: // Squaring elements of vectors
29: sqr_result[2] ← Squaring(QNV, c<sub>0</sub>, dup_c<sub>0</sub>, sqr_result[0], sqr_result[1], sqr_result[2], carry, 6)
30: sqr_result[5] ← Squaring(QNV, c<sub>1</sub>, dup_c<sub>1</sub>, sqr_result[3], sqr_result[4], sqr_result[5], carry, 6)
31: // Addition for squared results to calculate the size of the vector
32: sqr\_result[5] \leftarrow Addition(QNV, sqr\_result[2], sqr\_result[5], carry, 6)
33: // Two's complement for subtraction using adder
34: sqr\_result[5] \leftarrow Two's complement\_6bit(QNV, sqr\_result[5], qflag4, carry, zero, zero1, zero2)
35: // Size comparison between (rR)^2 and (||v-c||)^2
                                                                          \triangleright ((rR)^2 - (||v - c||)^2)
36: sqr\_result[5] \leftarrow Addition(QNV, sqr\_rR, sqr\_result[5], carry, 6) \Rightarrow No square root
37: return co. c1
```

### **Data load on Quantum Circuit**

- Data load with QRAM
  - Load the input vector (v)

    Allocate qubits for quantum memory cell  $\Rightarrow v = (\mathbf{00}_{(2)}, \mathbf{01}_{(2)})$

Copy data stored in quantum memory cell to input qubit (using cx gate)




- Apply Grover's search repeatedly for each v (v is not a superposition)
- It is difficult to actually access QRAM.
  - Therefore, we implement a simple explicit QRAM on a quantum circuit.
  - This is actually close to QROM (Quantum Read-only Memory) because it can only read data to be used.

# **Input setting on Quantum Circuit**


#### Input setting

- Apply Hadamard gate on c (The target of Grover's search)
- Since rR is a classical value, we set it to its squared value  $((rR)^2)$ .
- $sqr_rR = (\mathbf{rR})^2 = (0001_{(2)}) = 1_{(10)}$



#### To handle overflow:

- We allocate 1 additional qubit for upscaling.
- If the dimension of v is 2:
  - Data can be represented by 2-qubits
  - But, we allocate 3-qubits for v, c and rR.
    - For c, Hadamard gate is applied only to 2-qubits among 3-qubits (Search range is the same)
  - The value of the second qubit is copied to the qflag.
  - Afterward, upscaling is completed by copying the qflag to the highest qubit.
  - Through this, the value expressed through 3-qubits can be expressed equally with 2 qubits.



# **Complement on Quantum Circuit**


#### Two's complement

- After 1's complement (bit flip), LSB+1
- Since the input vector has a sign, a sign bit is required.
- Since a sign bit exists, in order to perform NV Sieve Logic, complement is required for positive/negative numbers.
  - Since  $10_{(2)}$  is -2, not 2, complement operation is required to perform correct logic.
  - Complement for positive numbers
    - $\rightarrow$  Used for subtraction through an adder  $(v_0 c_0, v_1 c_1 \rightarrow v_0 + \overline{c}_0, v_1 + \overline{c}_1)$
  - Complement for negative numbers
    - $\rightarrow$  Used for integer squaring (11<sub>(2)</sub>is -1, not 3, so the squared result is different without complement operation.)
- Conditional statements (e.g. if) cannot be used in quantum circuits.
  - We utilize control qubits to implement a function that calculates the two's complement only if the number is positive or negative.
  - For this, **ancilla qubit** is used. (*qflag*)

# **Complement on Quantum Circuit**

- 2's complement only if positive (→ MSB = 0)
  - 1. MSB on qubits for  $c \rightarrow \text{Copy to control qubit } (qflag)$
  - 2. Since the cx gate is inverted when the control qubit is 1, x gate is applied to qflag.  $\rightarrow qflag = 1$
  - 3. Perform all bit inversions using cx (1's complement)
  - 4. Create new qubit for LSB+1 ( $a=[0,0,qflag] \rightarrow a=(0,0,1)$ )
  - 5. LSB+1 is performed using quantum adder. e.g.  $\mathbf{001}_{(2)} = +1_{(10)} \rightarrow 110_{(2)}$  (inverted)  $\rightarrow 110_{(2)} + 001_{(2)} = \mathbf{111}_{(2)} = -\mathbf{1}_{(10)}$
- The 2's complement, which applies only when negative, is not applied to the x gate on qflag.
- Except for this part, the rest of the logic is the same


Ripple carry adder is used\*.



# **NV Sieve Implementation on Quantum Circuit**

#### Squaring

- Integer squaring for values converted to positive numbers through complement.
- Multiplication operation between the same values
  - Cannot operate on same qubits → Copy the same value to other qubits (cx gate)
- Allocate qubits to store the squared result -> Add the multiplication result for each qubit and store it
  - Using a Toffoli gate, the target qubit will be 1 if and only if the target values being multiplied are both 1.
  - Each calculation result is stored in an array of 6 qubits.
    - $\rightarrow$  ex: In the *First* array, values are stored only in the lower 3 qubits and the upper 3 qubits are set to 0.



# **NV Sieve Oracle for Extended Rank/Dimension**

- Extended Rank version
  - Rank + 1
    - v = (2 qubit, 2 qubit, 2 qubit)
    - c = (2 qubit, 2 qubit, 2 qubit)
    - $(rR)^2 = (6 \ qubit)$
    - After scaling, perform the Quantum NV Sieve logic
    - The operation scale is the same, and only calculation on additional 1 vector is performed additionally.

- Extended Dimension version
  - Dimension x 2
    - v = (4 qubit, 4 qubit)
    - c = (4 qubit, 4 qubit)
    - $(rR)^2 = (10 \ qubit)$
    - After scaling, perform the Quantum NV Sieve logic
    - The calculation scale becomes larger, and the number of calculations remains the same.

These extended implementations ensure scalability when the size of the lattice vector increases.

### **Environments**

- Simulation on Qiskit (IBM Quantum Lab)
- 3 types of Oracle
  - Default Model (*Def*)
  - Extended Rank Model (ExRank)
  - Extended Dimension Model (ExDim)
- Used iteration and shots = 1

### **Result of NV Sieve on Quantum Circuit**

Calculation results for each step mentioned previously (Example case to confirm implementation suitability)

Table 1: Results from each step of quantum NV Sieve to check whether it has been implemented correctly. (Default: 2-dimension and 2-rank, Ex\_DIM: 4-dimension and 2-rank, Ex\_RANK: 2-dimension and 3-rank)

Output	Default	Ex_DIM	Ex_RANK	
$v_0$	000	00111	000	
$v_1$	001	00011	001	
$v_2$	None	None	001	
$c_0$	001	11001	001	
$c_1$	000	00101	001	
$c_2$	None	None	111	
$(\gamma R)^2$	000001	0000000001	000001	
$\overline{c_0}$ (when positive)	111	11001	111	
$\overline{c_1}$ (when positive)	000	11011	111	
$\overline{c_2}$ (when positive)	None	None	111	
$v_0 + \overline{c_0}$ : $(vc_0)$	111	00000	111	
$v_1+\overline{c_1}$ : $(vc_1)$	001	11110	000	
$v_2 + \overline{c_2}$ : $(vc_2)$	None	None	000	
$(vc_0)^2$	001	0000000000	001	
$(vc_1)^2$	001	0000000100	000	
$(vc_2)^2$	None	None	000	
$(vc_0)^2 + (vc_1)^2 + (vc_2)^2$ : $(Sum_v c)$	000010	0000000100	000001	
$\overline{Sum_vc}$	111110	1111111100	111111	
$\gamma R + \overline{Sum_v c}$	111111	11111111101	000000	
MSB	1	1	0	
Shots	100			

```
If MSB=1 \rightarrow wrong c
If MSB=0 \rightarrow correct c
```

### **Grover's search of NV Sieve**

- When performing Grover's search, only the correct solution should be derived.
  - This requires accurate implementation of the oracle and the proper number of iterations.
  - The correct iteration when multiple solutions exist is  $\left| \frac{\pi}{4} \sqrt{\frac{N}{M}} \right|$  \*Search range (N), the number of solutions (M)
  - Currently, iteration 1 is used in the 3 types of implementations.

### **Result of NV Sieve on Quantum Circuit**

Resource estimation of NV Sieve (Oracle) (Grover X, Only oracle)

Table 2: Resource Estimation of Quantum NV Sieve oracle.

Case	#CNOT	#1qCliff	#T	T-depth	full depth	# Qubit
Default	291	69	124	396	1126	74
Ex_RANK	420	90	181	576	1631	105
Ex_DIM	685	224	296	878	2342	179

- Resource estimation of NV Sieve (Grover O)
  - With Reverse, Diffusion operator and Hadamard gate (iteration = 1)

Table 3: Required quantum resources for Grover's search on NV Sieve.

Case	Total gates	Full depth	T-depth	Quantum cost	# Qubit
Default	972	2259	792	2195748	75
Ex_RANK	1403	3271	1152	4589213	106
Ex_DIM	2436	4714	1756	11483304	180

**\***: The appropriate iteration is 1.

**Quantum Cost** 



2<sup>22.13</sup>
2<sup>23.45</sup>

21.06

Smaller amount of quantum resources than a 16-bit symmetric key (on Grover)



However, considering the very small problem scale, quite a lot of quantum resources are required.

### **Further Discussion**

#### Grover's iteration

- Since iteration affects the cost, finding an iteration for a problem that has multiple solutions is the most important challenge in the practical implementation of Quantum NV Sieve.
- We get the proper iteration that ensures that only the correct answer is derived.

#### Increase the upper limit

- The important thing to solve the current SVP is to accurately find short vectors and increase the upper limit of the
  dimension that can be solved.
- In other words, the Sieve algorithm belongs to the exact algorithm, and it is important to solve it accurately starting from low dimensions.

#### Optimizing the oracle circuit

In order to improve the efficiency of the quantum NV Sieve and maximize the benefits that arise from applying quantum,
it is thought that optimal implementation of the oracle will be important.

#### NISQ era

- In NISQ era, it is difficult to use many quantum resources.
- As the resource estimation results indicate, quite a bit of attack cost is required despite the small dimensions and rank.
- It is thought that solving SVP for high dimensions ( $50\sim60$  dimensions) such as classical is difficult for now.

### **Conclusion and Future work**

#### Conclusion

- To solve SVP on quantum computers, our work introduces a practical implementation of Quantum NV Sieve, designed to solve the SVP for hacking lattice-based cryptography.
- We implemented Quantum NV Sieve using quantum circuit. (3 types of oracle)
- We **estimate the quantum resources** required for each case-specific oracle and the cost of Grover's attacks when applied with their Quantum NV Sieve.
- Despite the small problem scale, quite a bit of quantum cost is required.
  - → Currently, it is difficult to solve SVP for lattice of approximately 50-rank/dimensions that are actually used.

#### Future work

- We have improved research results based on this work.
  - More extended oracle implementation
  - Complexity comparison between Classical and Quantum
  - Discussion of each element of the Sieve algorithm, etc.
- In future work, by optimizing the oracle and implementing higher ranks and dimensions, we will increase the upper limit of SVP solution.
- Also, we will find the correct iteration for those, and estimate the quantum cost of Grover's search.

# Thank you for your attention!