



Instructions and Usage examples of *Accesible*

- **QLab configuration:** • A single patch: IP + port 3333 UDP; all cues send the string to that destination. It must be sent as plain text to the port 3333, with no password.



Automatic subtitle loading in QLab using the included script

If there are multiple Network patches, the script will use the one listed first. List the *Accesible* patch first (or whichever name you prefer).



Or change the script to:

```
tell application "TextEdit"
```

```
    set thetext to the text of the front document
```

```
    set thecount to the number of paragraphs in thetext
```

```
end tell
```

```
tell application id "com.figure53.QLab.5" to tell front workspace
```

```
    repeat with i from 1 to thecount
```

```
        set thetitle to paragraph i of thetext
```

```
        if thetitle is "" then
```

```
            -- salta líneas vacías
```

```

else
    make type "Network"
    set newCue to last item of (selected as list)


    set thetitle to "/SEP/" & thetitle
    set q name of newCue to thetitle
    set custom message of newCue to thetitle
    set network patch name of newCue to "Accesible"
end if
end repeat
end tell

```

...which uses the Network cue named *Accesible*. Use the method that suits you best.

The script loads the text from a `.txt` file that is open on screen.

Place the subtitles you want to use in that file. The script and QLab will handle the rest.



QLab's Record Cue Sequence tool

Using QLab's *Record Cue Sequence* tool, select the second option (or the first one if it better fits your workflow). The second option is particularly useful when making timing adjustments.

While watching a rehearsal or a video of the rehearsal, create groups of subtitle sequences synchronized with the different scenes.

With the subtitle server activated, you can now view the result in any browser.

Simply trigger the group of cues you just created, and you will see the subtitles in the browser — in this example: <http://192.168.0.22:3000> (yours will be different).

Accesible's own server displays the exact address where each server is running. A button to copy the address is available right next to it.



If you activate the subtitle translation server:



Choosing the Input and Output Language

You will also be able to view the subtitles in the selected output language in another tab or browser – in this case, <http://192.168.0.22:3010> — automatically translated from the original.

The output language can be changed at any time, whether daily, weekly, or whenever needed - for example for a scheduled visit.

A range of subtitle options is available in the **Help** menu, including font size, font color, background color, and more. You can also choose whether subtitles are displayed in **scroll mode**, allowing users to reread previous lines, for example) or in **non-scroll mode**.

Audio Description Server

The audio description server uses its own dedicated folder.

You can open and modify it using the icons inside *Accesible*, under **Projects**. Inside this folder, there is a file named **welcome.mp3**. This audio loops continuously from the moment the user connects until the first programmed audio needs to play. It allows you to provide a welcome message, instructions, etc. You can create your own file — it must be placed in the same working folder and have the same filename.

This is where you must place all the audio description files you will use during the show.

From QLab, the cue that sends the playback command will use the same patch as the subtitles, but starting with **/audio/** followed by the filename. For example: **/audio/1.mp3**.

That is all you need; the audio will then play in real time on the devices.

Signed Video Server

The video server for signed video works similarly to the audio description server.

Place the video files in the **video folder**, which you can open from the *Accesible* icon.

The commands to send are: **/video/filename**. For example: **/video/1.mp4**

Refer to the Help menu documentation for more information.

The recommended video format is **.mp4**.

The smaller the file size, the faster the playback, so choose the resolution that works best for your project.

Activating Accessibility Services

Clients of any of the servers must tap the dedicated **on-screen** button to activate subtitles, audio description, and signed video.

This is mandatory because web browsers require explicit user interaction to allow automated playback.

External Access and Closing

External access to these ports and IP addresses must be allowed.

If you have access to your router's configuration, this should be straightforward to set up. If you do not have access to the router's configuration, you will likely need to use a **VPN with a fixed IP address** that provides the required external access.

This configuration will allow *Accesible* to operate correctly within your network environment.