

RESTORE POINT

➤ How to create Granted restore point?

CREATE RESTORE POINT GRP_BEFORE_PATCH GUARANTEE FLASHBACK DATABASE;

This is the granted restore point creation command.

But main error is:-

ORA-38784: Cannot create restore point

Usually occurs when:

- Flashback Database is not enabled.
- FRA is not configured.
- FRA has insufficient space.

STEP 1: Check the flashback status.

```
SQL> SELECT FLASHBACK_ON FROM V$DATABASE;

FLASHBACK_ON
-----
NO
```

STEP 2: Open the flashback.

```
SQL> SHU IMMEDIATE;
Database closed.
Database dismounted.
ORACLE instance shut down.
SQL>
SQL> STARTUP MOUNT;
ORACLE instance started.

Total System Global Area  310377856 bytes
Fixed Size                  8895872 bytes
Variable Size              272629760 bytes
Database Buffers           25165824 bytes
Redo Buffers                3686400 bytes
Database mounted.
SQL>
SQL> ALTER DATABASE FLASHBACK ON;

Database altered.

SQL> ALTER DATABASE OPEN;

Database altered.

SQL> SELECT FLASHBACK_ON FROM V$DATABASE;

FLASHBACK_ON
-----
YES
```

STEP 3: Check FRA (Fast Recovery Area).

```
SQL> SHOW PARAMETER db_recovery_file_dest;

NAME                                TYPE        VALUE
-----
db_recovery_file_dest               string      /u01/app/oracle/fast_recovery_
area
db_recovery_file_dest_size          big integer 8200M
SQL>
SQL>
```

STEP 4: Create granted restore point

CREATE RESTORE POINT GRP_POINT GUARANTEE FLASHBACK DATABASE;

```
SQL>
SQL> CREATE RESTORE POINT GRP_POINT GUARANTEE FLASHBACK DATABASE;

Restore point created.
```

STEP 5: Check it

```
SQL> SELECT NAME,GUARANTEE_FLASHBACK_DATABASE,SCN,TIME FROM V$RESTORE_POINT;

NAME      GUA      SCN TIME
-----
GRP_POINT YES    3168195 11-JUN-26 09.08.46.000000000 PM
```

➤ How to check if Guranteed restore point is created or not?

```
SELECT NAME,GUARANTEE_FLASHBACK_DATABASE,SCN,TIME FROM V$RESTORE_POINT;
```

```
SQL> SELECT NAME,GUARANTEE_FLASHBACK_DATABASE,SCN,TIME FROM V$RESTORE_POINT;

NAME      GUA      SCN TIME
-----
GRP_POINT YES    3168195 11-JUN-26 09.08.46.000000000 PM
```

➤ How to Drop Guranteed restore point?

```
SQL> DROP RESTORE POINT GRP_POINT;

Restore point dropped.

SQL> SELECT NAME,GUARANTEE_FLASHBACK_DATABASE,SCN,TIME FROM V$RESTORE_POINT;

no rows selected
```