

__ExternalActors__\HervantaMapTemplate\Maps\HervantaSimulation\9\I4\BGBQG04YMYC9W9UZZBL2NA.uasset

GeoReferenceSystem actor added to map with coordinates pointing to exact world coordinates of 0,0,0 position of Hervanta map. This is used in cluster to reset the world origin to reduce issues with floating point precision when going further away from origin.

Not 100% necessary to add this actor.

It's only utilized when MQTT client is started.

Projected CRS: "EPSG:3067"

Geographic CRS: "EPSG:4979"

Origin Location in Projected CRS: "True"


Easting "332405,9146"

Northing "6816306,8018"

Up: "0,0"


TrafficSystems\Cars\ActorBlueprints\AnimCar03_Master.uasset

Collision was enabled in the end of SetVariantId event, so that rays used in blind spot alert would be blocked by cars:




The comment still saying “disable collision”.

SetVariantId call was disconnected in Construct Script. This seemed like old implementation and was having issues when resolving the id.



All AnimCars actors:

VariantId is now set as a property



Note: All cars that are spawned as parked cars have incorrect variantid even when they start moving.