


Last Time: Two-Channel PR Filter Banks



$$Y(z) = z^{-L} X(z)$$

$$= \frac{1}{2} X(z) \left[F_0(z) H_0(z) + F_1(z) H_1(z) \right]$$

Distortion

$$+ \frac{1}{2} X(-z) \left[F_0(z) H_0(-z) + F_1(z) H_1(-z) \right]$$

Aliasing

PR Conditions (Vetterli, 1986)

- $F_0(z) H_0(z) + F_1(z) H_1(z) = 2 z^{-L}$
- $F_0(z) H_0(-z) + F_1(z) H_1(-z) = 0$

Obs: The PR conditions are two equations with 4 unknowns (H_0, H_1, F_0, F_1).

$$\begin{bmatrix} H_0(z) & H_1(z) \\ H_0(-z) & H_1(-z) \end{bmatrix} \begin{bmatrix} F_0(z) \\ F_1(z) \end{bmatrix} = \begin{bmatrix} 2z^{-L} \\ 0 \end{bmatrix}$$

Given the analysis filters, we can find the synthesis filters by inverting this matrix.

$$\begin{bmatrix} F_0(z) \\ F_1(z) \end{bmatrix} = \frac{2z^{-L}}{\Delta(z)} \begin{bmatrix} H_1(-z) & -H_1(z) \\ -H_0(-z) & H_0(z) \end{bmatrix} \begin{bmatrix} 1 \\ 0 \end{bmatrix}$$

Synthesis

Filters

$$= \frac{2z^{-L}}{\Delta(z)} \begin{bmatrix} H_1(-z) \\ -H_0(-z) \end{bmatrix}$$

Analy sis
Filters

$$\Delta(z) = H_0(z)H_1(-z) - H_0(-z)H_1(z)$$

Q: Suppose that H_o & H_i are FIR.

Are F_o & F_i FIR?

A: Not necessarily. The issue is $\Delta(z)$.

Might not even have causal or stable

IIR F_o & F_i ...

FIR PR Filter Bank Design

Q: How do we force F_o & F_i to be FIR?

A: Force $\Delta(z) = 2z^{-L} \Rightarrow$ FIR soln.

could put

any gain

and delay

$$2z^{-L} = H_o(z) H_i(-z) - H_o(-z) H_i(z)$$

$$= \underbrace{H_o(z) F_o(z)}_{P_o(z)} - \underbrace{H_o(-z) F_o(-z)}_{P_o(-z)}$$

"product"

Design Procedure :

1. Find $P_o(z)$ that satisfies

$$P_o(z) - P_o(-z) = 2z^{-L}$$

How do
we do
this?

2. Factorize $P_o(z)$ into $H_o(z) \cdot F_o(z)$

3. Define $H_1(z) = F_o(-z)$

$$F_1(z) = -H_o(-z)$$

→ Different filter banks / wavelets / properties

$$P_o(z) = P_{o,\text{even}}(z^2) + z^{-1} P_{o,\text{odd}}(z^2)$$

$$- P_o(-z) = P_{o,\text{even}}(z^2) - z^{-1} P_{o,\text{odd}}(z^2)$$

$$P_o(z) - P_o(-z) = 2z^{-1} P_{o,\text{odd}}(z^2) = 2z^{-L}$$

$$\underbrace{\text{odd power}}_{\text{only even powers}} = 2z^{-(2k+1)}$$

⇒ L must be odd

$$P_{o, \text{odd}}(z^2) = z^{-2K} \Rightarrow P_{o, \text{odd}}(z) = z^{-K}$$


delay

Obs: $P_{o, \text{even}}(z)$ is the design choice even coeff.


$P_{o, \text{odd}}(z)$ must be a delay odd coeff.

Ex: Let


Is $p_o[n]$ valid? Yes



$P_{o, \text{even}}[n]$



$P_{o, \text{odd}}[n] = \delta[n]$




$$K=0, L=1$$

Ex: Let

$$p_0[n]$$



Is $p_0[n]$ valid?



Yes

$$p_{0,\text{even}}[n]$$

$$p_{0,\text{odd}}[n] = \delta[n - 1]$$



$$k = 1, L = 3$$

Q: What kind of filter is this?

A: It is a (shifted) half-band filter:

$$p_0[2n-L] = \delta[n]$$

Defn: A filter $p_o[n]$ of the form

$$p_o[2n-L] = \delta[n]$$

is called a half-band filter
centered at L.

Obs: The length of the filter is $2L+1$.

Obs: we have now reduced the problem
to designing half-band (interpolation)
filters.

Half-Band Filter Design

If p_o is a half-band filter centered
at L , then

$$p_o(z) - p_o(-z) = 2z^{-L}$$

Q: What do people typically do?

A: Assume $P_0(z)$ is Type I Linear-Phase

Why not Type II? L is odd.

$$P_0(e^{j\omega}) = e^{-jL\omega} P_{\text{amp}}(\omega) \quad \cancel{\star}$$

↑
real function
center of
symmetry


$P(-z)$

$$\begin{aligned} P_0(e^{j(\omega-\pi)}) &= e^{-jL(\omega-\pi)} P_{\text{amp}}(\omega-\pi) \\ &= e^{jL\pi} e^{-jL\omega} P_{\text{amp}}(\omega-\pi) \\ &= -e^{jL\omega} P_{\text{amp}}(\omega-\pi) \end{aligned}$$

$$e^{-jL\omega} P_{\text{amp}}(\omega) + e^{-jL\omega} P_{\text{amp}}(\omega - \pi) = 2 e^{-jL\omega}$$

$$P_{\text{amp}}(\omega) + P_{\text{amp}}(\omega - \pi) = 2$$

Ex:



$$\pi - \omega_s = \omega_p$$

$$\omega_p + \omega_s = \pi$$


$$\omega_s - \frac{\pi}{2} = \frac{\pi}{2} - \omega_p$$

ripples need to cancel out

ω
half-band

Ex: Ideal low-pass filter ($L = 0$)



$$P_o(e^{j\omega}) = H_o(e^{j\omega}) F_o(e^{j\omega})$$



$$H_o(e^{j\omega})$$

$$F_o(e^{j\omega})$$

guarantee
PR



Q: Why the gain factor of 2?

A: To account for the magnitude


being halved from down sampling.

Remark: You will explore this in MATLAB in the homework.

Q: If P_0 is of length $2L+1$,
how many coeffs do we have
to design?

A: We only need to design $P_{0,\text{even}}$,
which is itself symmetric.

L	# coeffs
1	1
3	2
5	3
7	4



Q: What is $P_{0,\text{even}}$?

A: Type II Linear-Phase with
Center of Symmetry $\frac{L}{2}$.

* $P_{0,\text{even}}(e^{j\omega}) = e^{-j\frac{L}{2}\omega} P_{\text{even, amp}}(\omega)$

Putting everything together,

$$P_o(z) = P_{o,\text{even}}(z^2) + z^{-1} P_{o,\text{odd}}(z^2)$$

$$P_o(e^{j\omega}) = P_{o,\text{even}}(e^{j2\omega}) + e^{-jL\omega}$$


By \star and \star ,

$$e^{-jL\omega} P_{\text{amp}}(\omega) = e^{-jL\omega} P_{\text{even, amp}}(2\omega) + e^{-jL\omega}$$


$$P_{\text{amp}}(\omega) = P_{\text{even, amp}}(2\omega) + 1$$

$$P_{\text{amp}}(\omega) - 1 = P_{\text{even, amp}}(2\omega)$$


Ex:



$P_{\text{amp}1, \text{even}}(2\omega)$



Type II
linear-phase
zero @ π



One band filter

ripples will
automatically
cancel by symmetry



Remark: We've reduced the problem
to designing a Type II
linear-phase filter.

Window-Based Design Method

Goal: Approximate an ideal low-pass filter with an FIR filter.

$$P_{\text{ideal}}(\omega)$$

$$P_{\text{ideal}}[n] = 2 \frac{\sin\left(\frac{\pi}{2}n\right)}{n}$$



$$w[n]$$



$$P_0[n] = P_{\text{ideal}}[n] w[n]$$
 ||-top half-band filter

Remark: There's a whole industry in designing window functions,