12. Principal Components Analysis

LPO.8800: Statistical Methods in Education Research

Sean P. Corcoran

LPO 8800 (Corcoran)

Lecture 1

Last update: December 2, 2024 1/25

What is principal components analysis (PCA)?

PCA is best thought of as a technique for data reduction.

- ullet For example, suppose you have a dataset of variables $X_1,...,X_k$
- Could be multiple student test scores, measures of school performance, or measures of neighborhood disadvantage. (Variables should be at least interval-measured).
- PCA is method of creating a smaller set of variables (scores) that contain much of the same information as the original set.
- These scores can be analyzed on their own, or used in place of the larger set of variables.

What is principal components analysis (PCA)?

Principal components are *linear combinations* of the X chosen in a specific way:

- They are mutually uncorrelated.
- They sequentially contain as much information from the original variables as possible.

Think of each component as a "recipe": a set of weights applied to the original Xs to produce a new score.

 With k variables there will generally be k principal components, unless n < k, in which case there are only n. (Exception: if there is perfect collinearity between any variables, there will be fewer than k components).

LPO.8800 (Corcoran)

Lecture 1

Last update: December 2, 2024 3 / 25

What is PCA used for?

It is most often used when many variables of interest in the dataset are highly correlated with each other:

- Creating indices from multiple measures: e.g., for student academic aptitude, school performance, student engagement, neighborhood disadvantage, SES.
- Easier data visualization or cluster analysis (identifying units with similar "profiles" as defined by the PC).
- Addressing multicollinearity in regression models

PCA can also be useful in identifying latent constructs.

First principal component (with 2 variables)

The first principal component (PC_1) is the linear combination of the X with the maximum variance (i.e., capturing as much of the underlying variation in X as possible). With two variables X_1 and X_2 :

$$PC_1 = w_1X_1 + w_2X_2$$

where w_1 and w_2 are the principal component weights (or **loadings**).

- Simulated data: X_1 and X_2 are mean zero and bivariate normal.
- $\sigma_1^2 = 4$, $\sigma_2^2 = 20$, $\sigma_{12} = 5$. In covariance matrix form:

$$\Sigma = \begin{bmatrix} 4 & 5 \\ 5 & 20 \end{bmatrix}$$


LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 5 / 25

Simulated data example

Scatter plot between x_2 and x_1 :



Simulated data example

Goal: Find w_1 , w_2 that **maximize the variance** in PC_1 . In this example, $w_1 = 0.286$ and $w_2 = 0.958$ (see next slide):

$$PC_1 = 0.286X_1 + 0.958X_2$$

Note: one could maximize variance of PC_1 by simply increasing w_1 and w_2 indefinitely. Thus, it is standard practice to constrain the weights, for example such that $w_1^2 + w_2^2 = 1$. That is the case here.

"Recipe" interpretation: PC_1 involves 0.958 units of X_2 and 0.286 units of X_1 . X_2 is more important to PC_1 in this example since it has greater variance


LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 7 / 25

Simulated data example

Scatter plot and PC1:



First principal component (with 2 variables)

Note the "best fit line" for PC_1 is not the same thing as the linear regression of x_2 on x_1 (see next slide). Why?

- PC₁ minimizes the perpendicular distances from the data points to the line—it is equally interested in x₁ and x₂.
- Regression finds the line that best predicts x₂ given x₁ (minimizes vertical distances from the point to the line)—the focus is on x₂.
- PC₁ is trying to maximize variance; if the variances of the two variables are different, the line will tilt toward the one with the greater variance.
- The lines will coincide only in special cases: if x₂ is an exact linear function of x₁; or equal variances and perfect correlation.


LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 9 / 25

Simulated data example

 PC_1 versus linear regression of X_2 on X_1 :



Second principal component (with 2 variables)

The second principal component (PC_2) is the linear combination of the X that is uncorrelated with PC_1 and captures as much of the underlying variation in X as possible, given PC_1 . In this example, $w_1=0.958$ and $w_2=-0.286$ (see next slide).

$$PC_2 = 0.958X_1 - 0.286X_2$$

- The sum of its squared weights is again equal to 1.
- In the case of two variables, PC2 simply captures residual variation.


LPO.8800 (Corcoran)

Lecture 1

Last update: December 2, 2024 11 / 25

Simulated data example

 PC_1 and PC_2 :



Principal components with k variables

The principal components of k variables $X_1, ..., X_k$ are linear combinations of those variables that:

- Are mutually uncorrelated.
- Have squared weights that sum to 1.
- Maximize the variance of the linear combination, controlling for the previous principal components.

LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 13 / 25

Principal components with k variables

Note the sum of the variances of the *PC*s equals the sum of the variances of the *X*s:

$$\sum_{j=1}^{k} Var(PC_j) = \sum_{j=1}^{k} Var(X_j)$$

- The PCs are uncorrelated, so one can calculate the fraction of the total variance "explained" by each PC (like an R²).
- Important: PCA is not scale invariant. Variables measured in different units can affect weights since variables with higher variance tend to get higher weight. Solution: convert variables to standardized (z) scores. Stata will do this by default.

LPO 8800 (Corcoran)

Lecture 1

Last update: December 2, 2024 14 / 25

Stata pca command

To perform a principal components analysis in Stata, use the pca command:

pca varnames, options

Output includes:

- Principal component weights ("eigenvectors")
- Variances of each principal component ("eigenvalues")—these add up to the total variance of the Xs (the "trace")
- Proportion of the total variance "explained" by each principal component.

Note: when all variables are in z-score form (the default) the total variance is the number of variables (1+1+...=k).

LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 15 / 25

Example: Duflo, Dupas, and Kremer (2011)

This was a RCT of primary school tracking in Kenya. Their dataset includes endline test scores for 5,795 first grade students. There is a *totalscore* variable but also 7 subtest scores (words, sentences, letters, spelling, addition, subtraction, multiplication). It is possible we could learn more from a PCA of these 7 scores than simply relying on the total score.

```
. corr wordscore sentscore letterscore spellscore additions_score ///
         substractions_score multiplications_score
(obs=5,789)
             wordsc~e sentsc~e letter~e spells~e additi~e substr~e multip~e
  wordscore
               1.0000
                       1.0000
  sentscore
               0.5510
                                1.0000
letterscore
               0.6230 0.4546
               0.7983 0.5479
                                        1.0000
spellscore
                                0.7081
additions ~e
               0.4886 0.3216
                                0.5318
                                        0.5215
                                                1.0000
substracti~e
               0.4085 0.2563 0.4764
                                        0.4486
                                                0.7038
                                                        1.0000
                                                                 1.0000
multiplica~e
               0.4131 0.2827
                                0.4285
                                        0.4506
                                                0.5141
                                                         0.5009
```

Example: Duflo, Dupas, and Kremer (2011)

tpai componen	c3/ c011 e1#c1011		Number of comp.	= 5,70
otation: (unre	otated = princ	ipal)	Rho	= 1.0000
Component	Eigenvalue	Difference	Proportion	Cumulative
Comp1	4.01783	2.97255	0.5740	0.5740
Comp2	1.04528	.48359	0.1493	0.7233
Comp3	.561694	.036229	0.0802	0.8035
Comp4	.525465	.152919	0.0751	0.8786
Comp5	.372546	.0829405	0.0532	0.9318
Comp6	.289606	.10203	0.0414	0.9732
Comp7	.187576		0.0268	1.0000

Principal components (eigenvectors)

Principal components/correlation

Variable	Comp1	Comp2	Comp3	Comp4	Comp5	Comp6	Comp7	Unexplained
wordscore	0.4104	-0.3221	-0.0829	-0.2202	-0.5641	0.0581	0.5923	6
sentscore	0.3160	-0.4940	0.3257	0.7197	0.1786	0.0077	-0.0052	e
letterscore	0.4040	-0.1265	-0.2761	-0.3277	0.7665	-0.0143	0.2222	e
spellscore	0.4295	-0.2767	-0.1149	-0.2812	-0.2081	0.0690	-0.7737	
dditions ~e	0.3848	0.4079	-0.2415	0.2576	-0.1192	-0.7390	-0.0239	
ubstracti~e	0.3548	0.5154	-0.2484	0.3149	-0.0463	0.6674	0.0070	
ultiplica~e	0.3317	0.3572	0.8231	-0.2856	0.0516	-0.0078	0.0234	

Number of obs

LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 17 / 25

Example: Duflo, Dupas, and Kremer (2011)

Things to note in the above output:


- The sum of the squared weights for each component equals 1.
- The sum of the eigenvalues equals 7 (the number of variables).

Interpretation:

- Over 80% of the total variance is accounted for by PC₁, PC₂, and PC₃ (72% by the first two components)
- PC₁: weights are all positive and roughly the same, implying a simple average of these 7 scores.
- PC₂: positive weights on math scores and negative weights on literacy scores. Similar to a difference between the math and literacy scores.

Loading plot (1)

Loading plot (PC_2 vs. PC_1): how the variables load in component space




LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 19 / 25


Loading plot (2)

Loading plot (all PCs):



Scree plot

Scree plot:



LPO.8800 (Corcoran)

Lecture 12

Last update: December 2, 2024 21 / 25

Scree plot

The **scree plot** shows the eigenvalues by component. (Sometimes this plot is shown using proportions of the total).

- Sometimes analysts use the threshold of 1—the mean eigenvalue—to decide which principal components to focus on.
- Alternatively, can take components up to the point where there is significant diminishing returns.

Calculating principal component scores

Given the principal component weights, you can calculate the scores and add them to your dataset:

pc1					
	5,789	-3.24e-09	2.004453	-2.693618	7.201586
pc2	5,789	1.77e-11	1.022391	-4.371	3.601964
pc3	5,789	9.72e-11	.7494623	-2.430281	3.34169
pc4	5,789	-6.75e-11	.7248895	-2.190043	3.32636
pc5	5,789	-2.92e-12	.6103655	-2.636242	2.570263
pc6	5,789	-3.13e-10	.5381502	-2.248965	1.990383
pc7	5,789	-1.71e-10	.4331005	-2.268605	2.190427
ne1	4.01783				
pc1 pc2 pc3 pc4 pc5 pc6 pc7	1.045284 .5616937 .5254648 .3725461 .2896056				

Mean Std. dev.

Min

Other notes on the Stata pca command

- You can choose to only report a limited number of components, e.g., the first three: pca varnames, components (3).
- You can choose to only report components with a minimum eigenvalue, e.g. 1: pca varnames, mineigen(1)
- You can show blank spaces for loadings below a certain threshold
 (#): pca varnames, blanks(#). This draws attention to groups of
 variables important for a factor.
- PCA can be used descriptively or inferentially. You may wish to view
 your principal component weights and eignenvalues as estimates of
 population values. Assuming normality, you can compute standard
 errors, confidence intervals, test hypotheses, etc: pca varnames,
 vce(normal).

Other topics

- Another example: hearing loss (from Stata manual)
- Rotation
- PCA versus regression (more)
- PCA versus factor analysis