TEAMCENTER

Deployment Center — Usage

Teamcenter 2312



Unpublished work. © 2023 Siemens

This Documentation contains trade secrets or otherwise confidential information owned by Siemens Industry Software Inc. or its affiliates (collectively, "Siemens"), or its licensors. Access to and use of this Documentation is strictly limited as set forth in Customer's applicable agreement(s) with Siemens. This Documentation may not be copied, distributed, or otherwise disclosed by Customer without the express written permission of Siemens, and may not be used in any way not expressly authorized by Siemens.

This Documentation is for information and instruction purposes. Siemens reserves the right to make changes in specifications and other information contained in this Documentation without prior notice, and the reader should, in all cases, consult Siemens to determine whether any changes have been made.

No representation or other affirmation of fact contained in this Documentation shall be deemed to be a warranty or give rise to any liability of Siemens whatsoever.

If you have a signed license agreement with Siemens for the product with which this Documentation will be used, your use of this Documentation is subject to the scope of license and the software protection and security provisions of that agreement. If you do not have such a signed license agreement, your use is subject to the Siemens Universal Customer Agreement, which may be viewed at https://www.sw.siemens.com/en-US/sw-terms/base/uca/, as supplemented by the product specific terms which may be viewed at https://www.sw.siemens.com/en-US/sw-terms/supplements/.

SIEMENS MAKES NO WARRANTY OF ANY KIND WITH REGARD TO THIS DOCUMENTATION INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND NON-INFRINGEMENT OF INTELLECTUAL PROPERTY. SIEMENS SHALL NOT BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, CONSEQUENTIAL OR PUNITIVE DAMAGES, LOST DATA OR PROFITS, EVEN IF SUCH DAMAGES WERE FORESEEABLE, ARISING OUT OF OR RELATED TO THIS DOCUMENTATION OR THE INFORMATION CONTAINED IN IT, EVEN IF SIEMENS HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

TRADEMARKS: The trademarks, logos, and service marks (collectively, "Marks") used herein are the property of Siemens or other parties. No one is permitted to use these Marks without the prior written consent of Siemens or the owner of the Marks, as applicable. The use herein of third party Marks is not an attempt to indicate Siemens as a source of a product, but is intended to indicate a product from, or associated with, a particular third party. A list of Siemens' Marks may be viewed at: www.plm.automation.siemens.com/global/en/legal/trademarks.html. The registered trademark Linux® is used pursuant to a sublicense from LMI, the exclusive licensee of Linus Torvalds, owner of the mark on a world-wide basis.

About Siemens Digital Industries Software

Siemens Digital Industries Software is a global leader in the growing field of product lifecycle management (PLM), manufacturing operations management (MOM), and electronic design automation (EDA) software, hardware, and services. Siemens works with more than 100,000 customers, leading the digitalization of their planning and manufacturing processes. At Siemens Digital Industries Software, we blur the boundaries between industry domains by integrating the virtual and physical, hardware and software, design and manufacturing worlds. With the rapid pace of innovation, digitalization is no longer tomorrow's idea. We take what the future promises tomorrow and make it real for our customers today. Where today meets tomorrow. Our culture encourages creativity, welcomes fresh thinking and focuses on growth, so our people, our business, and our customers can achieve their full potential.

Support Center: support.sw.siemens.com

Send Feedback on Documentation: support.sw.siemens.com/doc_feedback_form

Contents


Introduction to Deployment Center	
Getting started with Deployment Center	
Deployment considerations	
Deployment process	
Password encryption	
HTTPS communication	
Deployment Center architecture	
Installing and using Deployment Center	
Prepare to install Deployment Center	
Install Deployment Center	
Upgrade Deployment Center	
Deployment Center maintenance	
Participate in the Product Excellence Program	
Uninstalling Deployment Center	
Troubleshoot Deployment Center installation or upgrade	
Start Deployment Center	
Log on to Deployment Center	
Troubleshoot Deployment Center operations	
Backup and recovery procedures	
Managing repositories Manage repositories Maintaining repositories	
Troubleshoot the repository service	
Managing Teamcenter environments	
Manage environments	
Verify software, applications, and components	
Edit environment properties	
Create environments	
Register environments	
Copy environments	
Remove components	
itemore components	
Troubleshoot registering environments	
View registered machines	
Deploying software using Deployment Center	
Installation, upgrade, and maintenance strategy	

Application deployment procedure	5-2
Maintain your environment	5-4
Update or patch your environment	5-6
Server and client deployment scripts	5-8
Software task	5-10
Options task	 5-11
Applications task	 5-12
Components task	5-13
Deploy task	5-16
Run the deployment scripts	5-18
Troubleshoot the deployment script	5-22
Quick deployment	
Understanding quick deployment	6-1
Quick deployment procedure	6-2
Using the dc quick deploy utility	6-4
Creating an XML configuration file	6-6
Sharing components across environments using Quick Deploy	6-8
Troubleshoot quick deployment	6-10
How to deploy the Business Modeler IDE templates on Tean	ncenter
Deploy Business Modeler IDE packages	7-1

1. Introduction to Deployment Center

Getting started with Deployment Center

Deployment Center is a centralized web application for deploying software to Teamcenter environments. Deployment Center gives you access to multiple environments from a single, centralized location. It simplifies the process of installing and updating software and automates deployment. You can manage a variety of Teamcenter environments more efficiently.



Download software packages to a central location, set up your installation or update in Deployment Center, and generate deployment scripts. Run the scripts on target machines that access and install the software.

Benefits

- Deploy, manage, and maintain multiple versions of software in multiple Teamcenter environments from a single web application with authenticated user access.
- Reduce the costs of managing Teamcenter environments by reducing the number of people, steps, and time involved in software deployment.
- Provide a centralized location to create and view Teamcenter environments and view deployment information.

- Ensure consistency and accuracy by reviewing and adjusting deployment configuration before rollout to Teamcenter environments.
- When setting up your environment, take advantage of entering parameters for one component and having those values shared with related components. For example, when you enter a machine name or port number for a component, that information is shared with other components that require the same information.

Flexible administration of software deployment

The software deployment process is accomplished in two phases.

- Select the software and configure the deployment in the Deployment Center web application. You
 can manage responsibility for software deployment using a single administrator or share it among
 the site's deployment experts. For example:
 - A business analyst can make decisions about choosing the applications. Business analysts can choose the software versions and the applications needed by business units.
 - An administrator can make decisions about the machines, ports, URLs, user names, passwords, and component settings for the target machines in an environment. Administrators can make deployment selections based on knowledge of hardware infrastructure, number of users, and which applications are used by business units.
- 2. After reviewing the deployment configuration, generate the deployment scripts and deploy the software on the target machines.

Manage software deployment for Teamcenter environments

You can deploy a variety of applications and components among your Teamcenter environments. A **typical deployment process** specifies software configuration and generates deployment scripts that install or update the software on target servers using software kits from a common repository.

Manage software deployment using Deployment Center utilities

You can deploy Teamcenter environments by following a quick deployment process that uses a Deployment Center utility to manage application and component configurations and generate deployment scripts.

Finding information

This Deployment Center documentation describes how to create, deploy, and manage your Teamcenter environments using the Deployment Center application and its utilities. To learn how to deploy your specific software, application, or server component, refer to the product or feature documentation for the version that you plan to install or update.

The Deployment Center video gallery on Support Center provide information and sample files as part of recent releases of Deployment Center documentation. These videos and samples demonstrate the capabilities of Deployment Center. More information about the video gallery is available from the **GETTING STARTED** tile on the Deployment Center home page.

Deployment considerations

System requirements and compatibility

Download support documents from Support Center to find system software certified for Deployment Center and supported upgrade paths for Deployment Center and Teamcenter.

Limitations

- See the Teamcenter Interoperability Matrix (**Teamcenter Interoperability Matrix** date.xlsx) for information about versions of Deployment Center that can be upgraded directly to Deployment Center 2312.
- To perform deployment actions that are not yet available in Deployment Center, run Teamcenter Environment Manager (TEM) on the target machines to complete your environment updates and configuration.

For additional information specific to this release, see the Deployment Center README document available with the Deployment Center 2312 product download.

Deployment process

Using Deployment Center, you can create and configure Teamcenter environments, with the flexibility to change applications, components, and parameter settings before you deploy Teamcenter software to the target machines in your network. The deployment process allow you to:

- Import environments created using Teamcenter Environment Manager (TEM) into Deployment Center.
- Register imported environments and further modify them in Deployment Center.
- Add Teamcenter software kits from updates, patches, and asynchronous product releases.
- Review selected applications, components, and parameter settings before you generate deployment scripts.
- Validate deployment scripts before deploying.

In the deployment process, you will perform the following common Deployment Center procedures:

Start Deployment Center

Start and log on to Deployment Center. You can display information about all existing, registered Teamcenter environments, including deployed software, applications, server components, and environment properties.

Set up the software repository

Plan where to store Teamcenter and related software kits for deployment.

Software storage considerations

- Keep the software in a single local repository on the Deployment Center web server. Use this option if you don't have spare server space located near target servers.
- Put software in multiple locations that may be shared with your target environment. Plan for enough disk space to hold the entire set of software for an environment. If you have existing software kits in a *software* directory, you can map a UNC path to that location. Be sure the server is accessible to Deployment Center. Use this option to make access easier during deployment.
- Copy the software from the repository to each target server, ensuring each server gets the complete set of software. Specify this path in the -softwareLocation argument when you deploy. Plan for additional disk space on each target server. Use this option to install software more quickly.

Manage the repositories

- Specify the software **repository locations** when you install or upgrade Deployment Center. If you already have software on another server, you can include it.
- Deployment Center scans repository locations regularly for unzipped software. The scanned software appears on the **Software Repositories** page which lists all available, valid software kits. If you have software dependencies, the repository notes missing software.
- Place the downloaded software kits in a repository *software* directory. Be sure they have been unzipped.

Manage environments

You can create and manage registered environments in Deployment Center. You can view the list of Teamcenter environments on the **Environments page**.

You can create a new environment, register an existing Teamcenter environment, or remove an environment.

Review registered servers

You can view all machines from your registered Teamcenter environments. On the **Machines** page, you can see all server machines used by the components in your registered environments.

Install or update software and applications

In Deployment Center, determine your approach for installing or updating an environment. Then deploy your software using the Deployment Center application.

You can deploy software in a multiple server environment or on a single machine. If your components are on multiple servers, verify the server configuration for each component.

Configure server components

In Deployment Center, you configure server components that are associated with your selected software and applications. Some components may be automatically selected, and some settings may already be configured. You can choose multiple servers for deployment.

Because selections and settings are saved as you go, you can review and verify them. If you are unsure of your setup or you need to make changes, return later to complete or change your settings before deployment.

When you enter user names and passwords for server components in Deployment Center, passwords are encrypted in the generated deployment scripts or you can provide an encrypted password.

Validate deployment scripts

After you verify your configuration information, generate the deployment scripts, and copy each script to its corresponding target server. Each script contains the designated target machine name, what to install or update on the target machine, and the software configurations you specified in Deployment Center.

Tip:

Validate the deployment scripts in a test run. As a best practice, run the deployment scripts in diagnostic mode on each target machine to validate the configuration. Check the log output for errors. No updates are made to the target machine during diagnostic validation. Make the corrections in Deployment Center, regenerate the deployment scripts, and run them in diagnostic mode until all errors are addressed.

Deploy the software

After validation is successful, run the deployment scripts on each target machine. The deployment script has a parameter to specify the location of the software directory. Be sure the software is available to the target machines.

Update or maintain your environments

You can **install or update additional applications and components** in Teamcenter environments managed from Deployment Center. You can also **perform maintenance on component configuration or parameter values** after installation from Deployment Center.

To perform additional deployment actions that are not yet available in Deployment Center, run Teamcenter Environment Manager (TEM) on the target servers to complete your environment updates and configuration.

Password encryption

You can provide an encrypted password for Deployment Center installation, as well as for command line utilities, by creating a secure encrypted password or password file. The **dc_encrypt.bat** utility (on Windows systems) and **dc_encrypt.sh** utility (on Linux systems) are located in the *deployment_center* directory of the software download kit.

When creating an encrypted password, the input password is specified either in text form or in an environment variable that contains the password.

Caution:

The password must not be empty nor contain any whitespace characters such as space, tab, newline, carriage return, form feed, or vertical tab.

In addition, the password must not contain any of the following characters:

-password

Specify the clear text password for the Deployment Center administrator user that you want to encrypt.

-env

Specify the environment variable containing the Deployment Center administrator password.

-file

Specify the file in which you want to save the encrypted password.

If the path contains spaces, enclose it in quotes.

-help

Displays the usage information for dc_encrypt.

Example:

To produce an encrypted password and save it to a file:

```
dc_encrypt -password=dc_password
-file=D:\pwd_files\dc_admin.pwf
```

To produce an encrypted password without saving to a file:

```
dc encrypt-password=dc password
```

To produce an encrypted password from a password contained in an environment variable:

```
dc encrypt -env=DC PWD ENVAR
```

Note:

If you generate an encrypted password without using the **-file** argument, you must prefix the encrypted password with **dc:** and save it to a text file before you can use the encrypted password with a Deployment Center utility. For example, save the following to a file named **dc_admin.pwf**:

dc:encrypted-PW

You can create an encrypted password or password file that can be used by these Deployment Center utilities:

deployment_center.bat -maintenance can also update an existing password later.

send configuration to dc

deploy

dc quick deploy can also generate encrypted passwords.

Use dc_encrypt to generate password files.

HTTPS communication

Deployment Center supports HTTPS and HTTP communication. HTTPS ensures encrypted, secure communication between the Deployment Center server and Deployment Center services and utilities. When you install or upgrade Deployment Center, you can enable HTTPS communication in the properties files.

Obtain SSL/TLS certificates for the Deployment Center server

Deployment Center supports an HTTPS encrypted connection using JKS and PKCS12 certificates. You may use the Deployment Center Vault as the certificate authority to generate certificates locally. Alternatively, you may purchase a certificate from a Certificate Authority (CA) or create a self-signed certificate.

If the KeyStore certificate is not signed by a trusted CA (such as when you create a self-signed certificate), you may provide an associated TrustStore and password.

Set the **Certificate Authority Settings** parameters for Deployment Center to configure how you will obtain certificates.

Enable HTTPS when installing or upgrading Deployment Center

To use HTTPS communication between the Deployment Center server and other machines, set the **useHttpsCommunication** parameter to **true**. To use this setting, you must configure **Certificate Authority Settings** parameters.

By default, **useHttpsCommunication** is set to **false**. Setting it to **true** enables HTTPS and *disables* HTTP communication with Deployment Center.

Deployment Center services and utilities must use HTTPS.

After you enable HTTPS, Deployment Center refuses all HTTP connections. If you receive unexplained web browser errors when accessing the Deployment Center server, determine whether the URL is using HTTP.

Manage secrets using the Deployment Center Vault

Set **Deployment secrets distribution setting** parameters to configure management of passwords and other Deployment Center secrets with the Deployment Center Vault.

The **onlineSecretsDistribution** parameter specifies whether to enable online access to secrets from the Deployment Center Vault. The supported values and modes for this setting are as follows:

true

(Online mode) With this setting, deploy scripts retrieve secrets from the Deployment Center Vault during deployment.

Caution:

If you set **onlineSecretsDistribution** to **true**, you *must* set the **useHttpsCommunication** parameter to **true** to ensure encrypted transmission of secrets from the Deployment Center server.

false

(Offline mode) With this setting, secrets are encrypted and distributed in the deployment packages generated by Deployment Center.

HTTPS support for Deployment Center utilities

After you configure HTTPS support, the following utilities use HTTPS:

send_configuration_to_dc

deploy

dc_quick_deploy

Deployment Center architecture

The basic architecture of Deployment Center is comprised of several main parts that communicate with each other.

Jetty web server and the Deployment Center web application A Jetty web server is automatically installed and configured for Deployment Center, and the installation automatically deploys and runs the Deployment Center web application. No additional installation or configuration is required for the Jetty web server or the Deployment Center web application. Access the web application from a web browser on any machine.

H2 database

The H2 database is also automatically installed and configured for Deployment Center. The database stores information about the Teamcenter environments registered with Deployment Center. No additional installation or configuration is required for the H2 database.

Repository and the repository service The repository stores the downloaded software kits. Deployment Center uses the repository subdirectories when it registers Teamcenter environments and displays choices for installing and updating software and applications.

You provide the repository directory location during installation of Deployment Center. Be sure that repository location has adequate disk space available to store all the software kits needed for your deployments.

The repository subdirectories are automatically created:

• dc contributions

Contains the Deployment Center files for versions of Teamcenter, Active Workspace, Business Modeler IDE, and other supported software.

Caution:

Do not make changes to this directory.

· deploy scripts

Contains a directory for each environment managed by Deployment Center. Generated deployment scripts and related files are placed in the appropriate environment subdirectory in a timestamped folder. The Deployment Center populates this directory structure for installing software.

Caution:

Do not make changes to this directory.

software

Contains the software you want to install or update using Deployment Center. Download Teamcenter software from the **Downloads** page, unzip the archives, and then copy the unzipped folders into the *software* directory.

Deployment Center automatically scans this directory and displays the list of selections on the **Software Repositories** page.

You may add other software repository locations when you configure Deployment Center.

system

Stores Deployment Center software files.

Caution:

Do not make changes to this directory.

The repository service is automatically installed when you install Deployment Center. The repository service runs automatically and monitors the repository. The repository service reports the software kits to Deployment Center and populates the list of available software selections.

Staging area

The staging directory is where Deployment Center stores the generated deployment script ZIP files that are created when you finish the deployment tasks. Copy the deployment scripts to each of the target machines. If you have configured components that run on multiple machines in the environment, there is one generated deployment script ZIP file for each machine.

2. Installing and using Deployment Center

Prepare to install Deployment Center

Verify system software requirements and Teamcenter compatibility

- Log on to Support Center and open the Support White Papers Certifications page:
 - a. Open **Products → Teamcenter → Downloads**.
 - b. Under Select a Version, choose Support White Papers → Support White Papers Certifications, and then click the Support White Papers Certifications tile.
- 2. Download the following support documents:

Software Certifications Matrix (Tc2312PlatformMatrix-date.xlsx)

Contains information about system software certified for Deployment Center and Teamcenter, such as operating systems and Java runtime environments (JREs).

Make sure the required system software is installed on your machine before you install Deployment Center. Also, make sure the **JAVA_HOME** system environment variable is set to the location of a certified JRE.

Teamcenter Interoperability Matrix (Teamcenter Interoperability Matrix date.xlsx)

Lists which versions of Teamcenter are compatible with Deployment Center 2312. It also lists which versions of Deployment Center can be upgraded to Deployment Center 2312.

Make sure the version of Teamcenter you plan to install is compatible with Deployment Center 2312.

Verify system storage space

Siemens Digital Industries Software recommends the following storage space be available on your Deployment Center machine:

- Deployment Center server software: Minimum 215 MB.
- Deployment Center software repository: Minimum 1 GB, plus about 40 MB for each generated deployment package.

The software repository also requires space for downloaded software kits and additional space for any custom software packages. You can store software downloads on the Deployment Center server or you can configure repository locations on separate file systems.

Download the Deployment Center software kit

You can install Deployment Center using the software included in the Teamcenter software kit.

1. Log on to Support Center and open the Teamcenter Downloads page:

Products → **Teamcenter** → **Downloads**

- 2. Under Select a Version, choose Teamcenter 2312, and then click the Teamcenter 2312 tile.
- 3. Download the Teamcenter 2312 software kit for your platform (**Tc2312_***platform.***zip**). Extract its contents to a local directory.
- 4. Change to the **install\DeploymentCenter** directory (on Windows systems) or the **install/ DeploymentCenter** directory (on Linux systems).
- 5. Copy the Deployment Center software kit (**deployment_center.zip**) to a directory on your Deployment Center machine.
- 6. Extract the contents of the Deployment Center software kit on your Deployment Center machine.

Install Deployment Center

Configure Deployment Center properties, then run the Deployment Center installation script.

Configure Deployment Center installation properties

- 1. In the directory where you expanded the Deployment Center software kit, change to the **deployment_center** directory. Locate the installation properties file, *install_config.properties*, which specifies parameters for the Deployment Center installation.
- 2. Create a copy of the installation properties file, for example, **DC_install_config.properties**.
 - Open your installation properties file in a text editor to begin setting installation parameters.
- 3. Set values for the required parameters or accept the default values provided.
 - Parameters that are optional are commented out. You may uncomment and set these parameters if you want, but do *not* remove optional parameters from your installation properties file.
 - When you are finished setting parameters, save your installation properties file.

Table 2-1. Deployment Center Installation Configuration Parameters

Parameter Group	Parameter	Description
Product Excellence Program Settings	enable Software Analytics	Specifies whether to participate in the Product Excellence Program. Set to Yes to participate or No to opt out.
		If you do not specify a value, the Deployment Center installation script prompts you to enter a value.
		For more information, see <i>Participate in the Product Excellence Program</i> or the Siemens Digital Industries Software Trust Center.
Deployment Center Server Settings	serverDir	Specifies the full path to the directory for the Deployment Center web server and the database.
		This directory path must have write access enabled.
	serverPort	Specifies the port where the Deployment Center web server listens for requests.
		This port must <i>not</i> be in use by another service.
	serviceName	Specifies the service name for the Deployment Center web server. The default value is DC_Service .
		Make sure this name does <i>not</i> match any existing service name. A duplicate service name causes installation to fail.
	serviceDName	Specifies the display name for the Deployment Center service. The default value is Deployment Center Service . This parameter applies to Windows systems only.
Deployment Center Repository Settings	repoDir	Specifies the full path to the directory for the primary Deployment Center software repository. The Deployment Center installation script creates a software subdirectory in this path.
		The path must be a local path. UNC paths and mapped drives are not supported for the primary repository directory.
	repoPort	Specifies the port where the Deployment Center repository listens for requests from the Deployment Center server.
		This port must <i>not</i> be in use by another service.
	repoServiceName	Specifies the name for the Deployment Center repository service. The default value is DC_RepoService .
		Make sure this name does <i>not</i> match any existing service name. A duplicate service name causes installation to fail.
	repoServiceDName	Specifies the display name for the Deployment Center repository service. The default value is Deployment Center Repository Service . This parameter applies to Windows systems only.
	repoServicePublisherDName	Specifies the display name for the Deployment Center repository publisher service. The default value is Deployment Center Repository Publisher Service . This parameter applies to Windows systems only.
	repoPublisherPort	Specifies the port used by the repository publisher. Do <i>not</i> change this value unless it conflicts with a port already in use.
	repoSubscriberPort	Specifies the port used by the repository subscriber. Do <i>not</i> change this value unless it conflicts with a port already in use.

Parameter Group	Parameter	Description
Deployment Center User Settings	user	Specifies the user name for logging on to Deployment Center. The user views environments, sets up installations, and generates deployment scripts. This user account must have administrative privileges on the
		Deployment Center machine. The default value is dcadmin .
	password	Specifies the password for the Deployment Center user. By default, the password is unencrypted.
		To use an encrypted password for Deployment Center:
		a. Create an encrypted password using the dc_encrypt utility.
		b. Set the useEncryptedPassword parameter to true .
		c. Enter the encrypted password in the password parameter or save the encrypted password to a file and specify its location in the dcpasswordFile parameter.
	dcpasswordFile (Optional)	Specifies the path to the file that contains the password for the Deployment Center user. If the file contains an encrypted password, be sure to set the useEncryptedPassword parameter to true .
Extra Software Directory Settings	extraSoftwareDir (Optional)	Specifies a comma-separated list of paths to additional software repository directories.
		You may specify local directory paths or UNC paths. Mapped drives are <i>not</i> supported.
		If you use UNC paths, you must specify values for osUserNameRepoService and osUserPasswordRepoService.
	os User Name Repo Service (Optional)	Specifies the OS user name for the Deployment Center Repository Service on the current machine. The OS user must exist on the current machine and have access to the UNC paths specified in extraSoftwareDir.
		This parameter is required if you use UNC paths.
	osUserPasswordRepoService (Optional)	Specifies the OS user password for the user specified in osUserNameRepoService.
		This parameter is required if you use UNC paths.
Encrypted Password Settings	use Encrypted Password	Specifies whether to use encrypted passwords for Deployment Center installation. This setting applies to all password parameters in the installation properties file.
		This parameter is set to false by default. Set to true to enter encrypted passwords for <i>all</i> password parameters.
Script Generation Directory Settings	osUserNameDCService (Optional)	Specifies the OS user name to use when generating deployment scripts to UNC paths. This parameter applies only to Windows systems.
		This parameter is required if you specify any UNC paths in the scriptsDirn parameters.
	os User Password DCS ervice (Optional)	Specifies the OS user password for the user specified in osUserNameDCService.

Parameter Group	Parameter	Description
		This parameter is required if you specify any UNC paths in the scriptsDir <i>n</i> parameters.
	scriptsDirn (Optional)	Specifies one or more directories where you want to generate deployment scripts for the dc_quick_deploy utility . If no scriptsDir is specified, the default location is the primary Deployment Center repository.
		Append a positive integer to the scriptsDir argument for each specification. Then specify the path to the directory. For example, scriptsDir123 = <i>scripts_path</i> .
		You may specify local drives or UNC paths. To use UNC paths, you must run Deployment Center as a Windows service and specify values for osUserNameDCService and osUserPasswordDCService.
HTTPS Communication Settings	useHttpsCommunication	Specifies whether to use HTTPS protocol for all communication with Deployment Center. You must have a supported SSL/TLS certificate, an associated KeyStore, and optionally a TrustStore. The default value is false . Setting to true disables support for HTTP communication. Deployment Center services and utilities must use HTTPS.
Certificate Authority Settings	useVaultAsDefaultCA	Specifies whether to use the Deployment Center Vault as the certificate authority (CA) to generate certificates for HTTPS communication with Deployment Center. This parameter is set to true by default. If you use a different CA, set this parameter to false and enter values for the remaining parameters in this section.
	certificateStoreType	Specifies the certificate type you use, either JKS or PKCS12.
	(Optional)	This parameter is required if you use HTTPS and do not use the Deployment Center Vault as your CA.
	keyStorePath (Optional)	Specifies the path to the KeyStore for your certificate.
	(Орионат)	This parameter is required if you use HTTPS and do not use the Deployment Center Vault as your CA.
	keyStorePassword (Optional)	Specifies the password to the KeyStore specified in keyStorePath .
	trustStorePath (Optional)	Specifies the path to the TrustStore for your KeyStore if your certificate is not signed by a known and trusted CA.
		The TrustStore file is bundled with the Deployment Center utilities to support the KeyStore.
		This parameter is required if you use a self-signed KeyStore.
	trustStorePassword (Optional)	Specifies the password to the TrustStore specified in trustStorePath.
Deployment Center Vault Settings	onlineSecretsDistribution	Specifies whether to enable online access to secrets from the Deployment Center Vault. If set to false (offline mode), secrets are encrypted and distributed with the deployment packages generated by Deployment Center. If set to true (online mode), deploy scripts retrieve secrets from the Deployment Center Vault during deployment.
	vaultServicePort	Specifies the port used by the Deployment Center Vault service.

Parameter Group	Parameter	Description
vaul	vaultServiceClusterPort	Specifies the port used by the Deployment Center Vault service for cluster server requests. Make sure this port is <i>not</i> in use by another service.
	vaultServiceName	Specifies the name used by the Deployment Center Vault service. Make sure this name does <i>not</i> match any existing service name. A duplicate service name causes the installation to fail.
	vaultServiceDName	Specifies the display name for the Deployment Center Vault service. The default value is DC_Vault_Service . This parameter applies to Windows systems only.
	osUserNameVaultService (Optional)	Specifies the OS user name to use to access the Deployment Center Vault service in online mode. (That is, if onlineSecretsDistribution is set to true.) This setting applies to Windows systems only.
	osUserPasswordVaultService (Optional)	Specifies the OS password for the user specified in osUserNameVaultService.

Launch the Deployment Center installation script

- 1. Open an administrator command prompt and change to the directory where you expanded the Deployment Center software kit. Then, change to the **deployment_center** directory within this directory.
- 2. Run the Deployment Center installation script, **deployment_center.bat** (on Windows systems) or **deployment_center.sh** (on Linux systems), specifying your updated installation properties file using the **-inputFile** argument. Example:
 - Windows systems:

```
deployment_center.bat -install
-inputFile=DC_install_config.properties
```

• Linux systems:

```
deployment_center.sh -install
-inputFile=DC_install_config.properties
```

3. After the installation is complete, the script displays the URL to access Deployment Center:

https://machine:port/deploymentcenter

Open this URL and enter the user and password you specified in the Deployment Center installation properties file.

4. On Linux systems, Deployment Center creates a post-installation tasks script that installs daemon processes for the Deployment Center server, repository service, publisher service, and vault service. After the installation is complete, run the post-installation tasks script:

a. As a user with **root** privileges, change to the following directory:

DC-server-dir/rootscripts

Replace *DC-server-dir* with the Deployment Center server directory you specified in the **serverDir** parameter in your installation parameters file.

b. Run the following script:

```
root_servicessetup.sh
```

This script registers daemons and performs other installation actions that require root privileges.

If the installation fails or the installation script displays errors, see the Deployment Center installation log file:

• Windows systems:

DC-root\deployment_center\webserver\logs\

• Linux systems:

DC-root/deployment_center/webserver/logs/

Replace *DC-root* with the Deployment Center installation path you specified in the **serverDir** parameter.

The Deployment Center installation log file also includes the URL to Deployment Center.

Note:

If you did not install Deployment Center as a service (on Windows systems) or a daemon (on Linux systems) by specifying the **serviceName** parameter in the Deployment Center installation properties, you must **start the Deployment Center web server manually**. You may need to **set the locale** when you do this.

Upgrade Deployment Center

When you upgrade Deployment Center, all its data is preserved, including locations of software repositories and deployed-environment information. Be sure to check supported upgrade paths for Deployment Center before you proceed.

During upgrade, you may also:

Migrate to using the HTTPS protocol for communication with the Deployment Center server.

- Add repository locations.
- Update where you want to generate deployment scripts.
- Update your decision to participate in the **Product Excellence Program**.

Configure Deployment Center upgrade properties, and then run the Deployment Center upgrade script.

Configure Deployment Center upgrade properties

- 1. Stop the Deployment Center web server, and stop the Deployment Center service if it is running.
- 2. **Verify system software requirements** on your Deployment Center machine.
- 3. Download the Deployment Center software kit.
- 4. In the directory where you expanded the Deployment Center software kit, change to the **deployment_center** directory. Locate the upgrade properties file, named upgrade config.properties, which specifies parameters for the Deployment Center upgrade.
- 5. Create a copy of the installation properties file, for example, **DC_upgrade_config.properties**.
 - Open your installation properties file in a text editor to begin setting installation parameters.
- 6. Set values for the required parameters, or accept the default values provided.

Parameters that are optional are commented out. You may uncomment and set these parameters if you want, but do *not* remove optional parameters from your upgrade properties file.

When you are finished setting parameters, save your upgrade properties file.

Table 2-2. Deployment Center Upgrade Configuration Parameters

Parameter Group	Parameter	Description
Deployment Center Server Settings	serverDir	Specifies the full path to the directory for the Deployment Center web server and the database. This directory path must have write access enabled.
D. J C	P. LEster Bred	
Deployment Center repoPt Repository Settings	repoPublisherPort	Specifies the port used by the repository publisher. Do <i>not</i> change this value unless it conflicts with a port already in use.
	repoSubscriberPort	Specifies the port used by the repository subscriber. Do <i>not</i> change this value unless it conflicts with a port already in use.
Deployment Center User Settings	user	Specifies the user name for logging on to Deployment Center. The user views environments, sets up installations, and generates deployment scripts.
		This user account must have administrative privileges on the Deployment Center machine.

Parameter Group	Parameter	Description
	password	Specifies the password for the Deployment Center user. By default, the password is unencrypted.
		To use an encrypted password for Deployment Center:
		a. Create an encrypted password using the dc_encrypt utility.
		b. Set the useEncryptedPassword parameter to true .
		c. Enter the encrypted password in the password parameter, or save the encrypted password to a file and specify its location in the dcpasswordFile parameter.
	serviceDName	Specifies the display name for the Deployment Center service. The default value is Deployment Center Service . This parameter applies to Windows systems only.
	repoServiceDName	Specifies the display name for the Deployment Center repository service. The default value is Deployment Center Repository Service . This parameter applies to Windows systems only.
	repoServicePublisherDName	Specifies the display name for the Deployment Center repository publisher service. The default value is Deployment Center Repository Publisher Service . This parameter applies to Windows systems only.
Extra Software Directory Settings	extraSoftwareDir (Optional)	Specifies a comma-separated list of paths to additional software repository directories.
		You may specify local directory paths or UNC paths. Mapped drives are <i>not</i> supported.
		If you use UNC paths, you must specify values for osUserNameRepoService and osUserPasswordRepoService.
	osUserNameRepoService (Optional)	Specifies the OS user name for the Deployment Center Repository Service on the current machine. The OS user must exist on the current machine and have access to the UNC paths specified in extraSoftwareDir.
		This parameter is required if you use UNC paths.
	osUserPasswordRepoService (Optional)	Specifies the operating system user password for the user specified in osUserNameRepoService.
		This parameter is required if you use UNC paths.
Encrypted Password Settings	useEncryptedPassword	Specifies whether to use encrypted passwords for Deployment Center installation. This setting applies to all password parameters in the installation properties file.
		This parameter is set to false by default. Set to true to enter encrypted passwords for <i>all</i> password parameters.
Script Generation Directory Settings	osUserNameDCService (Optional)	Specifies the OS user name to use when generating deployment scripts to UNC paths. This parameter applies only to Windows systems.
		This parameter is required if you specify any UNC paths in the scriptsDirn parameters.

Parameter Group	Parameter	Description
	osUserPasswordDCService (Optional)	Specifies the OS user password for the user specified in osUserNameDCService.
		This parameter is required if you specify any UNC paths in the scriptsDirn parameters.
	scriptsDirn (Optional)	Specifies one or more directories where you want to generate deployment scripts for the dc_quick_deploy utility. If no scriptsDir is specified, the default location is the primary Deployment Center repository.
		Append a positive integer to the scriptsDir argument for each specification. Then specify the path to the directory, for example, scriptsDir123 =scripts_path.
		You may specify local drives or UNC paths. To use UNC paths, you must run Deployment Center as a Windows service and specify values for osUserNameDCService and osUserPasswordDCService.
HTTPS Communication Settings	useHttpsCommunication	Specifies whether to use HTTPS protocol for all communication with the Deployment Center. You must have a supported SSL/TLS certificate, an associated KeyStore, and optionally a TrustStore. Setting this parameter to true disables support for HTTP communication. Deployment Center services and utilities must use HTTPS.
Certificate Authority Settings	use Vault As Default CA	Specifies whether to use the Deployment Center Vault as the certificate authority (CA) to generate certificates for HTTPS communication with Deployment Center. This parameter is set to true by default. If you use a different CA, set this parameter to false and enter values for the remaining parameters in this section.
	certificateStoreType (Optional)	Specifies the certificate type you use, either JKS or PKCS12. This parameter is required if you use HTTPS and do not use the Deployment Center Vault as your CA.
	keyStorePath	Specifies the path to the KeyStore for your certificate.
	(Optional)	This parameter is required if you use HTTPS and do not use the Deployment Center Vault as your CA.
	keyStorePassword (Optional)	Specifies the password to the KeyStore specified in keyStorePath .
	trustStorePath (Optional)	Specifies the path to the TrustStore for your KeyStore if your certificate is not signed by a known and trusted CA.
		The TrustStore file is bundled with the Deployment Center utilities to support the KeyStore.
		This parameter is required if you use a self-signed KeyStore.
	trustStorePassword (Optional)	Specifies the password to the TrustStore specified in trustStorePath.
Deployment Center Vault Settings	onlineSecretsDistribution	Specifies whether to enable online access to secrets from the Deployment Center Vault. If set to false (offline mode), secrets are encrypted and distributed with the deployment packages generated by Deployment Center. If set to true (online mode), deploy scripts retrieve secrets from the Deployment Center Vault during deployment.

Parameter Group	Parameter	Description
	vaultServicePort	Specifies the port used by the Deployment Center Vault service.
	vaultServiceClusterPort	Specifies the port used by the Deployment Center Vault service for cluster server requests. Make sure this port is <i>not</i> in use by another service.
	vaultServiceName	Specifies the name used by the Deployment Center Vault service. Make sure this name does <i>not</i> match any existing service name. A duplicate service name causes installation to fail.
	vaultServiceDName	Specifies the display name for the Deployment Center Vault service. The default value is DC_Vault_Service . This parameter applies to Windows systems only.
	osUserNameVaultService (Optional)	Specifies the OS user name to use to access the Deployment Center Vault service in online mode (that is, if onlineSecretsDistribution is set to true). This setting applies to Windows systems only.
	osUserPasswordVaultService (Optional)	Specifies the OS password for the user specified in osUserNameVaultService.

Caution:

Do not remove the repository subscriber port (repoSubscriberPort) or repository publisher port (repoPublisherPort) parameters. These parameters are for internal use by the repository. If the port specification conflicts with a port already in use, you may change the port to an unused port.

Launch the Deployment Center upgrade script

- Open an administrator command prompt and change to the directory where you expanded the Deployment Center software kit. Then, change to the deployment center directory within this directory.
- Run the Deployment Center installation script, deployment_center.bat (on Windows systems) or deployment_center.sh (on Linux systems), specifying your updated upgrade properties file using the -inputFile argument. Example:
 - Windows systems:

```
deployment_center.bat -upgrade
-inputFile=DC_upgrade_config.properties
```

Linux systems:

```
deployment_center.sh -upgrade
-inputFile=DC_upgrade_config.properties
```

After the upgrade is complete, the script displays the URL to access Deployment Center:

https://machine:port/deploymentcenter

Open this URL and enter the user and password you specified in the Deployment Center upgrade properties file.

If the installation fails or the installation script displays errors, see the Deployment Center log file:

• Windows systems:

DC-root\deployment center\webserver\logs\

• Linux systems:

DC-root/deployment_center/webserver/logs/

Replace *DC-root* with the Deployment Center installation path you specified in the **serverDir** parameter.

The Deployment Center installation log file also includes the URL to Deployment Center.

Note:

If you did not install Deployment Center as a service (on Windows systems) or a daemon (on Linux systems) by specifying the **serviceName** parameter in the Deployment Center installation properties, you must **start Deployment Center manually**.

You may need to set the locale on the Deployment Center URL.

If you want to change the Deployment Center administrator password, use the **deployment_center.bat**-maintenance command.

If you encounter problems during Deployment Center upgrade, see **Troubleshoot Deployment Center installation or upgrade**.

Deployment Center maintenance

You can perform a few maintenance actions in Deployment Center:

- Update the password for the Deployment Center administrator.
- Add and remove repository software directories.
- Add and remove deployment script directories.

Caution:

When you add or remove directories, be sure that no one is using the Deployment Center for any activity during maintenance. Deployment Center services are stopped and restarted during the update.

If you run Deployment Center on Windows, you must be logged on using an account with administrator privileges. On Windows systems, you may specify local drives or UNC paths. When you specify a path, use double backslashes (\text{\tilde{\text{\texi{\text{\text{\text{\tex

- 1. Stop the Deployment Center web server, and stop the Deployment Center Windows service if it is running.
- 2. Open a command prompt. Run Deployment Center in maintenance mode:

Windows systems: deployment_center.bat -maintenance

Linux systems: deployment_center.sh -maintenance

Add the following required arguments to the command:

-serverDir (required)

Specify the full path to the existing directory for the Deployment Center installation.

-user (required)

Specify the user name for the Deployment Center administrator to validate the change.

-password (required)

Specify the password for the Deployment Center user to validate the change.

If **useEncryptedPassword** was set to **True** when the password was entered previously, enter the encrypted password.

- 3. To change the password for the Deployment Center server user, specify these parameters:
 - · -changePassword

Specify this parameter if you are changing the password.

-newPassword

Provide the updated password. You may specify a clear text password or an encrypted password. The current password will be authenticated to make the change.

-useEncryptedPassword

Set to **true** if you are providing an encrypted password.

4. If you are adding or removing repository directories, specify these parameters:

-addSoftwareDir (optional)

Specify additional paths to **software** directories for the repository. These paths must be separated by commas (,).

You may specify local file system paths or UNC paths. Mapped drives are not supported.

For network locations, specify the user name and password.

-osUserNameRepoService

Specify the OS user name for the Deployment Center Repository Service on the current machine. The OS user must exist on the current machine and should have access to the UNC paths specified in the additional software directories.

-osUserPasswordRepoService

Specify the OS user password for the Deployment Center Repository Service on the current machine.

To reiterate, this OS user must exist on the current machine and should have access to the UNC paths specified in the additional software directories.

-removeSoftwareDir (optional)

Specify existing paths to **software** directories that are scanned by the repository. Paths are separated by commas (,).

This action does not delete **software** directories, and it does not remove scanned software from the repository display. However, the repository no longer scans the directory for additional software. Software in the directory is not removed from the system.

Do not remove a directory specified as the primary repository, specified by **-repoDir during installation**.

5. If you are adding or removing deployment script directories, use these parameters:

-addScriptsDir

Specify one or more directories where you want to generate deployment scripts for the dc_quick_deploy utility. Append a positive integer to each scriptsDirn argument followed by a colon: and the associated path, for example, scriptsDir123:scripts_path. Separate multiple specifications with a comma (,).

You may specify local drives or UNC paths. For network locations, specify the user name and password.

For UNC paths, Deployment Center must be running as a Windows service.

If you specify an existing **scriptsDirn**, the previous value will be overwritten by the new value.

-osUserNameDCService (required)

Specify the user name for the UNC or mapped drive.

-osUserPasswordDCService (required)

Specify the user password for the UNC or mapped drive.

-removeScriptsDir

Specify one or more locations you want to remove from deployment script generation. Specify the **scriptsDirn** argument that defines the location, for example, **scriptsDir123**. Separate multiple specifications with a comma (,).

6. Start Deployment Center.

Example:

Add and remove directories for the repository list and the generated scripts list:

```
deployment_center.bat -maintenance -serverDir=D:\dc\win\4
   -user=dcadmin1 -password=dcadmin1X05bw
-addSoftwareDir=D:\Foundation_software,D:\AW_software
   -removeSoftwareDir=X:\Foundation_software,X:\AW_software
   -addScriptsDir=scriptsDir10:D:\abc1,scriptsDir11:D:\abc2
   -removeScriptsDir=scriptsDir3,scriptsDir4
```

Participate in the Product Excellence Program

During the installation of Deployment Center, you have the opportunity to participate in the Siemens Digital Industries Software Product Excellence Program. This program anonymously shares information with Siemens Digital Industries Software about how you deploy Deployment Center software. This

information assists us in improving future releases of Deployment Center. Data collection occurs in the background as software is used and does not affect performance or functionality.

During the installation, you can opt in or out of the program by setting the **enableSoftwareAnalytics** parameter in the Deployment Center installation configuration parameters.

After installation, you can change your participation choice using the Deployment Center maintenance utility from a command line on the Deployment Center machine:

Join the program

Windows:

```
deployment_center.bat -maintenance -
enableSoftwareAnalytics=yes
```

Linux:

```
deployment_center.sh -maintenance -
enableSoftwareAnalytics=yes
```

Opt out of the program

Windows:

```
deployment_center.bat -maintenance -
enableSoftwareAnalytics=no
```

Linux:

```
deployment_center.sh -maintenance -
enableSoftwareAnalytics=no
```

Deployment Center notifies you if the change was successful.

After you change this setting, log out of Deployment Center and log on again for the change to take effect.

What is the Product Excellence Program?

Siemens Digital Industries Software collects information about the use of our products by customers through the Product Excellence Program. This program is designed to protect the privacy of users and the intellectual property created through the use of Siemens Digital Industries Software offerings.

The information we collect helps us improve our product features and functionality to meet our customers' needs better.

Privacy statement

The Product Excellence Program helps Siemens Digital Industries Software understand how customers use our products and assists us in improving our products. The program is anonymous and participation is voluntary.

The Product Excellence Program is designed to protect the privacy of the user and the intellectual property created through the use of Siemens Digital Industries Software products.

How does it work?

The Product Excellence Program is used to collect data about your installation, the features you use and how you use them. The data is sent to Siemens Digital Industries Software for analysis. By examining usage patterns from a large number of people, we gain insight into how the products are used and how to improve the software in future releases. Data collection occurs in the background as you use the software and does not affect performance or functionality.

What data is sent?

The data collected can vary by product and by release as we gain more insight or add new capabilities. The Product Excellence Program may collect information on the functions utilized, the operating environment (for example, OS, RAM, and graphics), product version, or other indications of user interactions. This data is solely used by Siemens Digital Industries Software to improve our products and is never shared with any third party.

There is no contact information in the data and Siemens Digital Industries Software will not contact you by phone or email as a result of the data collected. Absolutely no information about the data you create or manage is collected.

Participation is optional.

You can review and control your participation at any time.

You can opt out of the Product Excellence Program during installation or after installation. Change your decision to join or opt out at any time.

What does this mean for Deployment Center?

The following table provides examples of the type of usage data that is collected by Siemens Digital Industries Software and, equally as important, clarifies what data is *not* collected by Siemens Digital Industries Software.

What we collect	What we do not collect
The data collected contains information about how Deployment Center is deployed and used, for example:	The data collected <i>does not</i> contain user information or intellectual property, including:
Deployment Center version	Contact information

What we collect	What we do not collect
Client browser type and localeParticipation count	 Information about data created or managed in Deployment Center IT infrastructure identifiable information, including server IP addresses and host names

For more information about the Product Excellence Program, see the Siemens Digital Industries Software Trust Center.

Uninstalling Deployment Center

To remove Deployment Center from your system, perform the following steps to uninstall Deployment Center.

Remove Deployment Center services, the software repository, and Deployment Center files.

- 1. Open an administrator command prompt on the server where Deployment Center is installed.
- 2. Stop all Deployment Center services.

On Windows systems, use the **net stop** command:

net stop *service-name*

Enter this command for all Deployment Center services you installed as Windows services:

Displayed name	Service name
Deployment Center Repository Publisher Service	DC_RepoService_Publisher
Deployment Center Repository Service	DC_RepoService
Deployment Center Service	DC_Service
Deployment Center Vault Service	DC_Vault_Service

Example:

```
net stop DC_RepoService_Publisher
net stop DC_RepoService
net stop DC_Service
net stop DC_Vault_Service
```

This example uses default service names. If you changed any of these service names in the installation parameters when you installed Deployment Center, use the service names you specified to stop the services.

To find a service's service name using the Windows **Services** panel, right-click its displayed name and choose **Properties**.

3. Delete Deployment Center services.

On Windows systems, use the **sc delete** command:

sc delete service-name

Example:

```
sc delete DC_RepoService_Publisher
sc delete DC_RepoService
sc delete DC_Service
sc delete DC_Vault_Service
```

If you used non-default service names when you **installed Deployment Center**, use the service names you specified to delete the services.

- 4. Close the command prompt.
- 5. Delete the software repository directory. You specified this location in the **repoDir** parameter when you **installed Deployment Center**.

If you specified additional software directories in the **extraSoftwareDir** parameter, delete those directories also.

6. Delete the entire directory where you installed Deployment Center.

Troubleshoot Deployment Center installation or upgrade

If you encounter problems installing or upgrading Deployment Center, access the log files from the location where you extracted the Deployment Center installation ZIP file. The logs are in webserver\logs.

Running the installation script

Make sure you run the Deployment Center installation script from a location with no spaces or quotation marks in the path. For example, this path contains a space:

D:\DC Kits\deployment center\deployment center

The space in the path (DC Kits) may cause the following error:

```
Could not find or load main class Kits\deployment_center \deployment_center\jar\com.dc.jrechecker.jar
```

'JAVA_HOME' is set to an unsupported version of Java. Remove the space in the path.

Remove the space in the path.

Repository service name

ff the default **RepositoryService** service name or a service name specified by **repoServiceName** matches an existing service name, the installation returns an error. Check the service names on the server for conflicts. You can either change a conflicting service name or specify a different repository service name using **repoServiceName**.

Service names differ between new and upgraded installations

On Windows systems, if you upgraded an installation of Deployment Center and also performed a new installation of Deployment Center 2312, you may notice the displayed names of the Deployment Center services differ between the new and upgraded installations. This does not cause problems and the services will operate normally.

Service	Displayed name prior to version 14.1	Displayed name in versions 14.1 and later
Deployment Center Service	DC_Service	Deployment Center Service
Deployment Center Repository Service	DC_RepoService	Deployment Center Repository Service

Locale support for the Deployment Center URL

You may need to set the browser locale for Deployment Center as it does not read the web browser locale language. Set the locale by appending the locale code to the end of the Deployment Center URL.

Example:

http://dc_server:8080/deploymentcenter/?locale=de_DE

Supported language codes:

cs_CZ, de_DE, en_US, es_ES, fr_FR, it_IT, ja_JP, ko_KR, pl_PL, pt_BR, ru_RU, zh_CN, zh_TW

Start Deployment Center

Before you access the Deployment Center web application from a web browser, start the Deployment Center web server. You can choose either of the following ways:

Automatically start the server as a service or daemon

On Windows systems, if you specified the **serviceName** parameter during installation, the Deployment Center web server is installed as a service and starts automatically.

On Linux systems, the **root_servicessetup.sh** script installs the Deployment Center service as a daemon.

Start the server manually

If you did not specify the service arguments, start the Deployment Center service from its startup script. Navigate to the server directory specified by the **serverDir** parameter when you installed Deployment Center and run the **startdc.bat** script.

If you experience a problem starting Deployment Center, see <u>Troubleshoot Deployment Centeroperations</u>.

Log on to Deployment Center

1. Enter the Deployment Center URL in the web browser. The form of the URL is:

http://host:serverPort/deploymentcenter

host is the server where Deployment Center is installed.

serverPort is the port number specified by the **serverPort** parameter for the **Deployment Center installation script**.

Tip:


The URL is displayed in the command window after Deployment Center installation is complete.

The URL is also specified in the installation log file.

2. Enter the user name and password as specified in the **user** and **password** parameters for the Deployment Center installation script.

The Deployment Center home page appears.

Deployment Center



If you experience a problem in logging on to Deployment Center, see <u>Troubleshoot Deployment Center operations</u>.

Troubleshoot Deployment Center operations

You can refer to the log files if you have difficulty with the Deployment Center server operations. The log files are located in *webserver**logs* and may contain information about:

- Inability to log on to Deployment Center.
- Inability to add software, applications, or components to a Deployment Center environment.
- Failure to create a deployment script.
- Deployment Center operation failures such as internal server error, display problems, or missing configuration files.

If you configure HTTPS for Deployment Center, it refuses all HTTP connections. If you get an unexplained web browser error when accessing the Deployment Center server, check whether the URL is using HTTP instead of HTTPS.

If you have a problem with the browser locale for Deployment Center as it does not read the browser locale language, you can append the locale code to the end of the Deployment Center URL.

Backup and recovery procedures

You can back up key Deployment Center software files for recovery in case of a failure. You can recover files from a configuration error that cannot be otherwise changed in the system. You can also recover data from a database corruption.

You need to be familiar with the **Deployment Center installation process** as the procedures refer to Deployment Center installation paths and parameters. In the procedures, *DC-install-dir* is the installation path to the Deployment Center.

Back up the Deployment Center system

Note:

As a good practice, a backup must be performed when you add software to Deployment Center.

- 1. Stop the Deployment Center server.
- 2. If you set up a repository service, stop the service. To locate the service, look for the service name or display name which you specified in the **serviceName** and **serviceDName** parameters when you installed Deployment Center.
- 3. Copy these database files to a safe location:

DC-install-dir\serverDir\db\deploy center.h2.db

DC-install-dir\serverDir\db\deploy center.trace.db

4. Record the list of software packages you downloaded to the repository. The repository directory is set to the location specified by **repoDir** during Deployment Center installation, for example:

DC-install-dir\repository\software

Note:

If you already recorded the list of software packages and there have been no changes to the repository since the last backup, you can skip this step.

5. Restart the repository service and start Deployment Center.

If you encounter a problem, stop Deployment Center and the repository service and replace the database files from your backup. If that does not fix the problem when you restart Deployment Center, download and replace the software packages in the repository.

Reinstall Deployment Center

If your recovery is not successful, you may need to reinstall Deployment Center.

- 1. Stop Deployment Center, and delete the repository service.
- 2. Either move or rename the Deployment Center installation, in case you need to access the software directories to repopulate the repository.
- 3. Reinstall Deployment Center in the same location, using the same paths and ports as the original installation. To restore the database files, the repository path specified by **repoDir** must be identical to the previous installation.
- 4. Update the repository with the same software packages that you retrieved from the previous backup. If the repository software packages are available from the installation that you moved or renamed, copy those files.

Wait for Deployment Center to update and recognize the software.

- 5. Stop the Deployment Center server.
- 6. If you set up a repository service, stop the service.
- 7. Copy the backup database files to your current Deployment Center installation:

DC-install-dir\serverDir\db\deploy center.h2.db

DC-install-dir\serverDir\db\deploy center.trace.db

8. Restart the repository service and start Deployment Center.

Deployment Center is restored to the state it was in from the last backup.

3. Managing repositories

Manage repositories

Deployment Center stores the software kits for your Teamcenter environment in a repository. The repository helps you determine whether you have everything you need for an installation or update. To access the repositories, log on to Deployment Center and click **SOFTWARE REPOSITORIES**.

Specifying repository locations

Each Deployment Center repository contains a *software* directory that stores your unzipped software kits. The primary repository is specified by the **repoDir parameter** during Deployment Center installation.

You may have Teamcenter software in more than one location. You can add these locations using the **extraSoftwareDir** parameter. Specify the paths for Deployment Center during **installation**, **upgrade**, or **maintenance**. Each specified path presumes there is a *software* subdirectory where unzipped software kits are stored.

The primary repository location (**repoDir**) must be a local directory path. UNC paths and mapped drives are not supported.

Additional repository locations (extraSoftwareDir) can be local file system paths or UNC paths. Mapped drives are not supported.

Manage software kits

Deployment Center scans for software in unzipped subdirectories of these registered repository *software* directories. Deployment Center reads directories nested one level under *software*. These subdirectories must contain unzipped, valid software directories.

Deployment Center does not scan further than the first level subdirectories under *software*. Software nested under another software folder is not found. Software that is placed in another location on the server is not scanned.

Review repository contents

The **Active Media** tab displays information about each software kit in the **Software Media** table. Deployment Center refers to the base Teamcenter software as Foundation software.

Software kit information includes the name, version, release type, repository folder location, and when it was last scanned. You can see whether it's in use by a Teamcenter environment and whether it has a dependency.

Dependent software must be present to successfully choose software to install or update. If you are missing dependent software, Deployment Center displays a message explaining what you need.

If the repository scanner detects an invalid file, the repository displays the file with a message. Invalid files can be a Word or Excel document, a directory containing software not supported by Deployment Center, or a software ZIP file that is not unzipped.

The repository service scanner updates the repository list periodically, but the refresh rate may be affected by factors such as server location and network performance.

Add or remove repository locations

You can add and remove software locations in the repository at any time using deployment center.bat in maintenance mode.

Review software configuration reports

You can review configuration information for any software listed in the repository. The report contains product, application, and component information you may need to set up a Teamcenter environment using the quick deploy process.

Choose a software kit from the Active Media tab and click Generate Software Configuration **Report** □. The HTML results provide comprehensive information about software dependencies and IDs, application internal names and dependencies, and component and property internal names and configuration values. This information can help you create or update the guick deploy XML configuration file.

Add software kits into the repository

- Download the software kits for the software versions that you want to deploy in your Teamcenter environment. Be sure to get the current full release any updates you want to apply to your Teamcenter environment.
- Unzip the software kits and copy the unzipped directories to the software subdirectory in one of your registered repository locations.
- Log on to Deployment Center, and click **SOFTWARE REPOSITORIES**. 3.
 - The Software Repositories page opens the Active Media tab of the repository and displays the Software Media table.
- Check the list of software to verify that it is correct and complete for your planned deployment. Check whether missing dependencies are noted. If so, retrieve the missing software and check again. The list may take a little while to update.

If you experience a problem in adding software to the Deployment Center repository, you can try to troubleshoot the repository service.

Remove obsolete software kits from the repository

When a software kit is no longer being used in a registered Teamcenter environment, you can remove it from the **Active Media** list.

- 1. Open the **Active Media** tab to display all the registered software kits. Click the software kit you want to remove.
- 2. Click **Remove** \bigcirc on the command bar and confirm the deletion.

If the software is used by an environment, an error message explains that it can't be removed and which environments are using it.

If the software is not used and is free to be removed, the selected software is moved to the **Obsolete Media** tab. Deployment Center deletes the software and the software directory from the file system.

To complete the software kit removal from Deployment Center, click the **Obsolete Media** tab, select the software to remove, and then click **Remove** on the command bar.

The repository scanner removes the software kit registration and removes the software from Deployment Center database. The selected software no longer appears in the **Obsolete Media** tab.

Update repository properties

The **Overview** tab provides helpful information about the server where the primary repository is located. The system information includes disk space, which you can monitor when you put software kits in the repository. The available and used disk space values are updated when you add or change software kits in the primary repository.

You can edit some of the repository properties.

- 1. Click Start Edit ⊘.
- 2. You can change the following information:
 - Repository Name

Enter or update a name for the repository.

Location

Enter or update a location for the repository server. You can use any convention you wish, such as geographical location, the name of a facility, or another value that helps you define the location.

Comments

Enter or update information that might be helpful to an administrator.

3. Click **Save Edits**

To cancel your changes, click Cancel Edits.

Maintaining repositories

Use the maintenance procedure for deployment_center.bat to add, remove, or update the repository software locations being used by Deployment Center.

Troubleshoot the repository service

If you have difficulty with software not appearing on the **Software Repositories** page, you may have repository scanning issues or software file problems. The repository log files are located on the Deployment Center server in *webserver\repotool\logs*.

4. Managing Teamcenter environments

Manage environments

The **Environments** page lists all environments being tracked by Deployment Center. You can view, **create**, and **delete** environments. To access the list of environments, log on to Deployment Center and click **ENVIRONMENTS**.

Deploy software in an environment

The **Deploy Software** tab displays the selected software used by registered environments. You choose the software necessary to proceed with deploying updates. If an environment is new, the selected software list may be empty. This is where you begin the **software deployment process**.

View an environment's properties

The **Overview** tab displays the environment's properties, such as the architecture, site, software version, applications, and components installed in the environment. Click an environment to learn more about it.

• Review the **Properties** for the environment.

If an environment is new, the **Overview** displays the information used to create it.

You can edit some environment properties.

• Review the **Software**, **Applications Installed**, and **Components** for an existing environment. You can click a selection to display more information in the right pane.

If an environment is new, **Software**, **Applications Installed**, and **Components** may not be populated, so no Teamcenter environment information may be displayed.

Exporting environments

You can use an existing environment as a starting point to create a new environment. You can export an XML configuration file that contains the selected environment's configuration. Edit this configuration file and then reuse it as the input XML file for the dc_quick_deploy utility.

On the **Environments** page, choose an environment from the list, and run **Export Environment** \rightarrow . Select whether you want the output XML file to contain all component configuration properties or just the required component properties.

Information about the software is available from the **Software Configuration Report**. The report may be helpful in making updates to the XML configuration file.

Verify software, applications, and components

On the **Environments** page, you can review the software, applications, and components for each environment.

Software

You can verify the status of software for the selected environment. The list includes installed and pending software. You can select the software package to see additional software details.

Applications Installed

You can verify the status of applications for the selected environment. The list includes installed and pending applications. You can select an application package to see additional application details.

Applications are associated with their installed software, such as Search for Active Workspace.

Components You can verify the status of components for the selected environment. The list includes installed and pending components. You can select the component package to see additional information about component settings. Components are associated with their applications, such as Indexing Engine and Indexer for Search.

> The component information in the right pane offers two views of the information. In the upper right corner, you can choose the view:

0

Show all parameters

Required parameters view displays only required parameter information. Click to expand the view to display both required and optional parameters.



Show only required parameters

All parameters view displays both required and optional parameter information. Click to collapse the view to required parameters.

Edit environment properties

On the **Environments** page, you can edit some environment properties. Click the **Overview** tab to display the properties of the selected environment.

- 1. Click **Start Edit** ∅ to display the editable fields.
- You can change the following information: 2.
 - Environment Name

Displays the name provided during setup for the environment. You can update the name for the environment.

Environment Type

Displays the type of the environment. The available types are Integration, Development, **Production**, **Test**, and **Training**. The type is set to **Production** by default when the environment is registered, but you can select another type.

Location

Displays the location of the environment. You can enter or update the geographical location for the environment, such as a city, the name of a facility, or another value that helps you define the location of the environment.

Comments

Displays additional information entered by the administrator. You can enter or update information about the environment.

Click **Save Edits** , or click **Cancel Edits** to discard your changes. 3.

Create environments

You can create an environment for your planned deployment. When you are ready to add software to your new environment, Deployment Center displays only the versions of Available Software that are supported in a new environment.

Create an environment

Log on to Deployment Center, and click **ENVIRONMENTS**.

The **Environments** page lists currently planned and registered environments.

- 2. On the far right below the command bar, click **Add Environment** \oplus .
- The new environment appears highlighted in the list. Choose **Overview** to display its information. 3.
- 4. You can edit some of the properties, such as **Name** and **Type**. On the command bar:

Click **Start Edit** ∅ to edit properties. To save your changes, click **Save Edits** 🖺.

To cancel your changes, click **Cancel Edits** \mathcal{A} .

You can also choose to export the configuration of an existing environment. You can reuse its configuration to create another environment using the guick deployment procedure.

Register environments

Register your environments in Deployment Center by running the **send_configuration_to_dc** utility on the corporate server that hosts each Teamcenter environment. If the environment is distributed across multiple servers, you must run the script on each machine that is part of the specific Teamcenter environment. The script sends configuration information about the applications and components that are currently installed to Deployment Center.

After the environment is registered, you can view its configuration information and verify the content. Deployment Center stores information about server machines deployed in your environments.

- View the machines used in deployed Teamcenter environments from the MACHINES tile on the Deployment Center home page.
- Select a machine from a list of servers when configuring components.

Caution:

Before updating an existing registered Teamcenter environment, be sure that you run the **send_configuration_to_dc** script to update the environment information. Configuration changes performed locally on Teamcenter servers since the last time the **send_configuration_to_dc** script ran could be overwritten.

- 1. On the machine hosting the Teamcenter environment, install the supported version of the JRE and set **JAVA_HOME** to the location.
- 2. If it's not already set, open a command prompt window, and set the **TC_ROOT** environment variable to the Teamcenter installation directory
- From the location where you installed Deployment Center, navigate to
 additional_tools\send_configuration_to_dc directory and find send_configuration_to_dc.zip.
 Copy and then unzip the file. Place the extracted directory on the machine hosting the Teamcenter environment.
- 4. In the command prompt window on the Teamcenter server, navigate to the send_configuration_to_dc directory. Run send_configuration_to_dc.bat (Windows) or send_configuration_to_dc.sh (Linux) using the following arguments.

-dcurl (required)

Specify the URL for the Deployment Center server you want to use.

-dcusername (required)

Specify the user name for the Deployment Center administrator as defined when installing Deployment Center.

-dcpassword OR -dcpasswordfile (required)

Specify the password for the Deployment Center administrator. You can specify the password as text or use an encrypted password or password file. If the password file path contains spaces, enclose it in quotes.

-environment (required)

Specify a name to identify the environment being scanned. Because an environment is ordinarily identified by its site ID, this argument allows you to create a readable label that makes it easier to identify the Teamcenter environment.

-config (optional)

Specify the ID value for the configuration used when installing the Teamcenter environment. Specify this argument if multiple configurations are installed in a single **TC_ROOT** location.

Example:

```
send_configuration_to_dc.bat -dcusername=dcadmin
  -dcpasswordfile="E:\admin passwords\dcadmin.pwf"
  -dcurl=http://dc_host:9000/deploymentcenter
  -environment=Sandbox
```

After the scan completes, the script returns the message:

```
All operations completed successfully.
```

You can then review the environment in Deployment Center.

Java EE web tier component configuration

Because Web Application Manager (insweb) is a separate tool from Teamcenter Environment Manager, **send_configuration_to_dc** is unable to scan Web Application Manager files. As a result, the Teamcenter Java EE web tier component configuration is not returned with the environment scan. After the scan is complete, you need to add the Java EE web tier component to the environment.

- 1. Log on to Deployment Center and go to the **Environments** page. Select the environment you scanned from the list.
- 2. On the **Deploy Software** tab, navigate to **the Components task**. Look for the **Teamcenter Web Tier (Java EE)**. Add it to the **Selected Components** if it's not already present.
- 3. In the **Selected Components** list, choose **Teamcenter Web Tier (Java EE)** and enter the configuration settings for the web tier from the original environment. If you are unsure about these settings, you can find them using either of these methods:

- In the Web Application Manager, select your web application and click **Modify**. Then review the web application information in **Modify Web Application**.
- Review the .dat files in the staging location for your web application. For example, find WEB ROOT\staging1 on the machine where you run the Web Application Manager.
- 4. Save your settings. Review the remaining **Selected Components** to make sure they are all 100% complete.

If you experience other problems in registering environments with Deployment Center, see **Troubleshoot registering environments**.

Copy environments

You can create an copy of an existing environment from your **Environments** list in Deployment Center for various development or training purposes. Copying an environment duplicates the software, applications, components, and configuration parameters of the selected source environment, changing the machine names to avoid impact to the source environment.

Caution:

The **Copy Environment** function is not intended for copying an environment and deploy scripts to the *same* machines to redeploy the *same* environment. It should be used only to create a *new* environment from a source environment and deploy it on a *different* set of machines. Deploying a copied environment to the same machines as the source environment may result in ambiguous deployment status and the environment could become unrecoverable.

1. Log on to Deployment Center, and then click **ENVIRONMENTS**.

The **Environments** page lists currently planned and registered environments.

- 2. In the environments list, select the environment you want to copy.
- 3. In the command bar on the far right, click **Copy Environment** .
- 4. In the Copy source environment dialog box, define values for the copied environment:
 - a. In the **Environment Name** box, type a name for the copied environment.
 - b. In the **Environment Type** box, choose the type of environment you want to create:

Developmen A workspace where developers can perform experimental configuration and customization of software.

Integration An environment in which multiple developers can integrate their code

changes to validate the work of a team and ensure interoperability before

committing changes to a test or production environment.

Production A working environment with live users and data.

Test A simulation of the production environment with the operating system

infrastructure, software modules, custom code, and settings you intend to

include in your production environment.

Training An environment created for educational use that contains software modules,

settings, and sample data for use in presenting or learning how to use the software. A training environment does not have to mimic a production environment, but can be a simplified environment that contains only

selected components or applications.

Deployment Center performs no special configuration according to environment type. The **Environment Type** parameter is merely a tag to denote the purpose of the copied environment.

5. Click **Copy** to create a copy of your selected environment, or click **Cancel** to cancel the copy.

Deployment Center adds the copied environment to the **Environments** list. You can continue configuring the copied environment at this time or return to it in a later session.

- 6. To continue configuring your copied environment, proceed to the **Applications** task to add applications to, or remove applications from, your copied environment.
- 7. Proceed to the **Components** task. Note any components whose **MACHINE** name is prefixed with **REPLACEME** and update those machine names as needed.

Deployment Center inserts these machine names to prevent changes to the source environment.

- 8. Continue updating configuration parameters as needed on all components in the **Selected Components** list until the values in the **COMPLETE** column are all **100**%.
- 9. Proceed to the **Deploy** task. Generate install scripts and deploy them on affected machines.

Remove environments

You can remove an environment from the **Environments** list in Deployment Center.

1. Log on to Deployment Center, and click **ENVIRONMENTS**.

The **Environments** page lists all environments.

2. Select the environment you want to remove.

3. Click **Delete** \otimes on the command bar and confirm the deletion.

The environment is only removed from Deployment Center tracking. The Teamcenter system remains intact.


Remove components

You can remove components from an environment in the **Components** task in Deployment Center.


Some components cannot be removed because they are required or because other components depend on them. Deployment Center identifies components that can be removed.

- 1. Log on to Deployment Center.
- 2. In the **Environments** list, select the environment you want to modify.
- 3. Proceed to the **Components** task.
- 4. In the **Selected Components** list, select the components you want to remove from your environment.

The check box by each component name indicates whether the component can be removed:



Hover over any disabled check box to view the reason the component cannot be removed. For example:



- 5. After you select components to remove, click **Remove Selected Components**, then confirm the deletion.
- 6. If any components do not have a configuration status of **100**%, update configuration parameters until all components show a configuration status of **100**%.

7. Proceed to the **Deploy** task. Click **Generate Install Scripts** to generate deployment scripts to update affected machines.

When script generation is complete, note any special instructions in the **Deploy Instructions** panel.

8. Locate deployment scripts, copy each script to its target machine, and run each script on its target machine.

For more information about running deployment scripts, see *Deployment Center — Usage*.

Troubleshoot registering environments

You can consult log files if you have difficulty with sending an environment configuration to Deployment Center (using the send configuration to dc script), such as:

- Sending configuration to Deployment Center fails.
- Inability to communicate with a Deployment Center server.
- Invalid credentials passed when sending environment configuration.

The registration configuration log files are located on the Teamcenter environment server in send configuration to dc dir\logs:

• tem config scanner error timestamp.log

Provides a description of environment scanning operation failures.

tem_config_rest_service_timestamp.log

Provides the communications information between the Deployment Center server and the send_configuration_to_dc utility.

If the Teamcenter Java EE web tier component configuration is not returned with the environment scan, you may need to complete the configuration after the environment is registered.

View registered machines

View the machines used in deployed Teamcenter environments. Select a machine name from the list to view its properties, such as operating system, disk capacity, and free disk space.

 Log on to Deployment Center, and click MACHINES. The Machines page lists all servers used by components in deployed environments. When you select a machine, the Overview provides information about the server where one or more software components are installed.

4. Managing Teamcenter environments

2. Verify that the properties for the server machine are what you expect.

Properties for a machine from a deployed environment include:

• Machine Name and IP Address

Identifies the machine by the server name and IP address.

• OS and OS version

Displays the operating system type and version installed on the machine.

Local Time

Displays the current date, time, and time zone at the machine's location.

• Disk Capacity and Disk Free

Displays the total disk space and the free space available. The pie chart to the right displays the same information visually.

• Last Update

Displays the last time information about this server was refreshed. The information is obtained and sent by the **send_configuration_to_dc utility**.

5. Deploying software using Deployment Center

Installation, upgrade, and maintenance strategy

You can use Deployment Center to install, upgrade, or update a Teamcenter environment. You can also perform maintenance on Deployment Center. You can choose the scenario that meets your needs.

Install a new Teamcenter environment

You can install software into a new environment. To prepare for a new installation:

- Define a Teamcenter environment in Deployment Center by one of the following methods:
 - Create a new environment if you are starting with a new Teamcenter installation.
 - Register an existing environment if you are installing new software in an existing environment.

 This may be the case if you are installing Active Workspace in an existing Teamcenter environment.
- Put your unzipped installation software kits in a repository directory. If you have an existing environment, put the software you used to install it into the repository.

Begin the installation by following the deployment procedure.

Upgrade or patch an existing Teamcenter environment

You can upgrade or patch software in an existing environment. Software dependencies are noted in the Deployment Center repository and in the **Software** deployment task. Deployment Center displays messages explaining issues with upgrade software or dependencies.

To prepare for a software upgrade or patch in an existing environment:

- Be sure you have a registered existing environment in Deployment Center before you start an upgrade.
- Be sure to **send existing configuration information** from the environment to Deployment Center using the **send_configuration_to_dc** script.
- Put your unzipped installation software kits in the repository and check for messages about dependencies.

Maintain an existing registered Teamcenter environment

You can update some software or components in an existing registered environment. Maintaining an existing registered Teamcenter environment means updating software or components for your current version, as permitted by Deployment Center. Be sure you send existing environment configuration information to Deployment Center. You must have the source software for your environment in the repository.

Update Deployment Center configuration

You can run deployment_center.bat -maintenance to change the administrator password, add and remove repository directories, and add and remove deployment script directories.

Application deployment procedure

The Deployment Center deployment process walks you through a set of tasks that creates a Teamcenter environment and the deployment scripts containing software, application, and component information. This method shows you software and application choices, displays configuration information and parameters, and allows you to leave the user interface and return while you are entering your configuration information.

The Deployment Center user interface **Deploy Software** page displays each step in the deployment task bar. In each task, Deployment Center prompts you to make selections and provide information. At any time in the process, you can save your work and exit. The settings are stored in Deployment Center, and you can return to the deployment process at your convenience.



Dark blue means the task is available and currently selected.

Medium blue means the task is available.

Gray means the task is not available yet. These tasks become available as steps within the previous tasks are completed.

Click a chevron to go to that task. You can revisit any task you previously completed to make changes. For example, if you completed the **Components** task, you can still return to the **Applications** task and make changes.

Caution:

Before proceeding to update an existing registered Teamcenter environment, be sure that you run the **send_configuration_to_dc script** from server components to provide current environment information in Deployment Center. Configuration changes performed locally on Teamcenter servers since the last time the **send_configuration_to_dc** script ran could be overwritten.

A Teamcenter environment doesn't track mass client software installations, so this action is not necessary for clients that have been deployed in this manner for the environment.

How to deploy software

1. Open the **Environments page** and choose the environment where you want to install or update software. The **Deploy Software** page provides access to the deployment tasks.

2. Software

Choose the software to install or update. The software determines the list of available applications. For example, if you choose Active Workspace software, you can install the applications it provides.

- **Pending Install** software will be installed or updated during deployment.
- **Pending Update** software is already installed in your environment, but it needs an update to support other selected software.
- Installed software is already installed in your environment and needs no updates.

3. Options

Choose single server or multiple server deployment for **Environment Type**.

Choose the Java or Windows architecture for **Architecture Type**.

4. Applications

Choose the applications. The list of available applications depends on the software selected in the **Software** task. Some applications may be automatically selected for you by default.

Each software package can have one or more applications in its bundle. Applications provide business logic, data model, work processes, and administration data for specific business uses, industries, or integrations. In this step, you do not need to know details of your network or configuration of software or hosts.

5. Components

Choose and configure components. Components run on the specified servers in your environment. Some components are automatically selected for you as required by the applications selected in the **Application** task. You need to configure any component that is not listed as **100**% complete.

Component status:

• **Pending Install** components will be installed during deployment.

- **Pending Update** components are already installed in your environment, but they need updates to support your selected applications.
- **Installed** components are already installed in your environment, and they don't need any updates.

You need to know the server hosts on which components will be installed or updated, user names and passwords for the server component, and component URLs. Some components may have additional required or optional settings.

6. **Deploy**

Generate deployment scripts. This task is not available until the **Components** task is complete.

Deployment scripts contain the information you configured in Deployment Center for each of the servers in your environment. The scripts install the software, applications, and components onto each target machine in your environment.

7. Run the deployment scripts.

After the scripts and software ZIP files are generated, copy them to each target machine and run them.

If you are **installing both server and client deployments**, both types of scripts are generated. Always run server component deployment scripts before running client deployment scripts.

You can run the deployment script in diagnostic mode to determine whether your script has any errors before updating the target machine.

Maintain your environment

Deployment Center can maintain applications or components in a **registered Teamcenter environment**. Maintenance is making changes to your existing environment. You are not performing upgrades or applying patches. Before you perform maintenance, you must:

- Be sure you have a **registered existing environment** in Deployment Center before you perform maintenance on its components.
- Send existing configuration information about a registered environment to Deployment Center using the send_configuration_to_dc script.
- Put your current environment's software in the repository and check for dependencies.

Perform maintenance

The tasks for updating software or components are similar to installation:

1. Open the **Environments page** and choose the environment you want to maintain. Begin the **Deploy Software** tasks.

2. Software

Choose software from the **Available Software** list. The software selections determine the list of available applications that you can update. Applications that must be updated are automatically selected. The **Selected Software** list displays currently installed versions.

3. Options

Either single server or multiple server deployment is selected for **Environment Type**. If you previously had a **Single Box** environment, you can choose **Distributed**; however, you will need to update the server information for affected components.

If an environment is already deployed on multiple servers, **Single Box** is not available.

Architecture Type for your environment is automatically selected and can't be changed.

4. Applications

Applications that are already installed are automatically displayed. You can add applications from the list. Applications that display a **Pending Install** status are waiting for deployment. Applications that are installed but need updates to support your selected software display the **Pending Update** status.

5. Components

It's possible that a selection from the current update may cause a previously configured component to need more information, especially if you add applications or move from a **Single Box** environment to a **Distributed** environment.

Components that are not yet installed display the **Pending Install** status. Components that are installed but need updates to support your selected applications display the **Pending Update** status.

Components display the % configured. If it's less than **100**%, complete the required parameter values. Components that are not impacted can be ignored (showing **100**% configured).

6. **Deploy**

Generate deployment scripts for the update. This task is available when the other tasks are complete.

Deployment scripts contain the information you configured in Deployment Center for the selected environment.

7. Run the deployment scripts

After the scripts and software ZIP files are generated, copy them to each target machine and run them.

Update or patch your environment

Deployment Center software updates follow a process that is similar to installation. When you want to update or patch your environment, choose the target version of software you want to apply. Deployment Center determines what to update or patch based on what is required by the selected target release and selected applications.

You may not be required to put source release software kits in the repository. Deployment Center constructs source to target release mapping using the environment's current configuration files sent in the report from <code>send_configuration_to_dc</code>. Deployment Center analyzes the target release information to construct the mapping at the time you choose to update. Sometimes, Deployment Center may require the source software if the target release doesn't provide adequate mapping information. If there is missing software that is required, Deployment Center displays messages telling you about the dependency and how to proceed.

Before you perform an update, you must download, unzip, and put the software update or patch kits in the Deployment Center repository. Check the repository for software dependencies and messages about missing software.

Import a configuration from TEM

Deployment Center can update or patch software in a registered Teamcenter environment. If the environment you want to update originated in TEM, run the send_configuration_to_dc script on the target servers to send the latest environment configuration information to Deployment Center.

Perform updates or patches

The procedure for updating an environment is similar to creating an environment.

Open the Environments page and choose the environment where you want to update software.
 Begin the Deploy Software tasks.

2. Software

Choose the target update software from the **Available Software** list. The **Selected Software** list displays currently installed versions and latest pending versions for the environment. If the software you need is not available, check whether it was listed in the repository.

If missing software is required, Deployment Center tells you about the dependency and how to proceed.

3. Options

Either Single Box or Distributed is selected for **Environment Type**. If you previously had a **Single Box** environment, you can choose **Distributed**; however, you will need to update the server information for components.

If an environment is already deployed on multiple servers, **Single Box** is not available.

The **Architecture Type** for your environment is automatically selected and can't be changed.

4. Applications

Applications that are already installed are automatically included for update. You can add other applications from the list. Applications that display a **Pending Install** status are waiting for deployment. Applications that are installed but need updates display the **Pending Update** status.

See Application names changed in Deployment Center for additional information about application names.

5. Components

Components that are not yet installed display the **Pending Install** status. Components that are installed but need updates to support your selected applications display the **Pending Update** status.

It is possible that a selection from the current update may cause a previously configured component to need more information.

Components display the % configured. If it's less than **100**%, complete the required parameter values. Components that are not impacted can be ignored (showing **100**% configured).

6. **Deploy**

Generate deployment scripts for the update. This task is available when the **Components** task is complete.

Deployment scripts contain the information you configured in Deployment Center for the selected environment.

7. Run the deployment scripts

After the scripts and software ZIP files are generated, copy them to each target machine and run them.

Server and client deployment scripts

In Deployment Center, you install or update server software by configuring their components. You can also configure client software components for mass client software installation. You generate both server deployment scripts and client deployment scripts using the Deploy task.

Server deployment scripts

Select applications and configure the server components needed for your environment. After you run deployment scripts on the target servers, information about the target environment is sent to Deployment Center.

Server scripts must be run prior to running mass install client scripts for individual user machines. After the environment is updated, then run mass client install scripts on user machines.

If you are configuring client software as a component, such as a single installation of rich client on a specific server, this is considered a server deployment script because the deployment is for a specific server machine.

Mass client deployment scripts

Install and configure client software for users to run locally on individual machines. Client deployment scripts can only be created in a distributed environment. Mass client software is not machine-specific, so one client deployment script can run on any number of machines. Client scripts do not send any information back to the Deployment Center, so the environment is not aware of which clients are installed or using it.

Multiple types of clients may be installed together with one script. Configure each type of client component and specify the same **Instance Name** for all of them. For every specified instance name, Deployment Center groups the installation scripts together and generates a single client install deployment script.

Caution:

Server component scripts must run prior to running any mass client installation scripts for an environment.

Tip:

If a user's machine already has a client installation and the deploy script can detect the installation path, the deploy script runs the update on the user's current client installation. If the deploy script has multiple clients but doesn't detect all the installation paths, it performs an installation if it doesn't find an installation path or an update if it finds the current installation.

Process for deploying mass client software

1. Client software deployment is performed as part of a **Distributed Teamcenter environment**. You may create mass client deployment scripts as part of configuring a Teamcenter environment.

- Choose the client you want to deploy in the Components task. If a client supports mass user 2. installations, the configuration panel displays a check box to enable it.
- Enable mass client deployment and specify the required parameters. Machine Name is replaced by 3. **Instance Name** for a client script. Enter a name for the current client deployment.
- 4. Save the client component configuration and complete any remaining required component parameters.

The client component displays (Mass Client) in the Selected Components list as the type of client deployment. Client components configured for mass deployment display a status of n/a because they are not tracked as part of a server component.

- Generate the deployment scripts. The Deploy Instructions displays the path to the output zip 5. files. A client deployment file is named deploy mass client instance-name.zip.
- 6. Optionally, you can reduce the size of the client deployment scripts by running the generateMiniSoftware utility.
- 7. Run the client deployment script after running any server component scripts that were generated for the Teamcenter environment.

Client software may be installed as part of a server component where supported.

Generating mini-kits for mass client installations

You can reduce the size of your mass client deployment files by generating a mini software kit. Running the generateMiniSoftware utility extracts only the necessary software from the full software kits and builds a smaller, more portable software kit for the specific client deployment.

To generate a mini software kit, perform the following steps:

- Locate the minisoftwaregenerator.zip file in the additional tools directory in your Deployment Center installation. Expand this zip file to find the generateMiniSoftware utilities for Windows and Linux.
- 2. To generate a mini software kit, type the following command in a single line:

```
generateMiniSoftware.bat -deployScriptDir=deploy-script-dir
-softwareLocation=software-dir
-outDir=output-dir -includeAllConfiguredApps
```

Supply the following values in the command:

deploy-script-dir: Path to the mass client deployment scripts directory. Be sure the scripts are in .zip file format.

software-dir: Path to the directory or software repository from which the utility can gather files for the mini software kit. This can be a single path, or multiple paths separated by commas. Type the value the **default** to gather files from software kits in repositories registered with Deployment Center.

output-dir: The location in which to generate the mini software kit.

The optional **includeAllConfiguredApps** argument creates a mini kit that can be used to install a rich client *or* update an existing rich client. To create a mini kit for updating only, omit this argument. Omitting this argument creates a smaller but limited-use mini-kit.

For example:

```
generateMiniSoftware.bat -deployScriptDir=D:\DC_deploy_scripts
    -softwareLocation=E:\DC_software -outDir=D:\mini_deploy_scripts
    -includeAllConfiguredApps
```

After you run the utility, its output log file contains information about which components and applications are included in the mini-kit as well as information about the size of the mini kit compared to the original software kits.

For more information about the *generateMiniSoftware* utility, see the *Teamcenter Utilities* in the Teamcenter documentation.

Software task



In this task, select the software to install from the list of installable applications. The software you select determines the list of applications available in the **Applications** task. The **Selected Software** list displays both current and pending installations for the environment.

If a software kit you select depends on another kit, Deployment Center automatically selects the additional required kit.

1. In the **Software** task, click **Edit Selected Software** \oplus to add software.

This **Available Software** panel displays the software choices.

2. The **Available Software** panel lists software from the repository. The software status displays information about the software kit. After making your selections, click **Update Selected Software** to add them to **Selected Software**.

If the software you need is not listed, you must add it to the repository. Add software as needed, but you may have to choose applications and configure components before deployment.

3. When your **Selected Software** list is complete, go to the **Options** task.

Options task



In this task, choose the deployment options for your environment.

- 1. Choose the **Environment Type**.
 - Choose **Single box** to install all components on a single machine using the same installation path.

After you define **Machine Name**, **OS**, and **Teamcenter Installation Path** for one of the components, those values are adopted by the other components.

If an environment is already deployed on multiple servers, this type will not be available.

• Choose **Distributed** to install components on separate servers in an environment. This type may be selected automatically if your environment is already set up as a distributed environment.

Key configuration values (Machine Name, OS, and Teamcenter Installation Path) are shared only with components that are required to be on the same server.

If you install all components on the same host, but in *different installation paths*, choose the **Distributed** environment type.

You can change the value from **Distributed** to **Single box** if an install or an update is not in progress. For configured components that are not yet installed, **Machine Name**, **OS**, and **Teamcenter Installation Path** are changed to the values specified for the corporate server component.

- 2. Choose **Architecture Type**.
 - Choose **Java EE** to filter component choices to the Java EE architecture.
 - Choose .NET to filter component choices to the Windows .NET architecture.

If your environment already has deployed one of the architectures, the type is selected and can't be changed.

3. Choose **Infrastructure Type**.

- Choose **Local** if your environment is to contain standard connected components or component configurations shared from a Global infrastructure environment. This is the default selection in a new environment.
- Choose **Global** if your environment is to contain components configured for sharing to multiple Teamcenter Local environments.

A Global infrastructure is used to define mass client information that can be shared to multiple environments managed in Deployment Center.

Only certain components are supported for sharing to other environments, such as the four-tier rich client, TCCS, and Security Services Session Agent.

4. When your selections are complete, click **Save Environment Options** to go to the **Applications** task.

Applications task



In this task, choose applications for the software you selected. The list of available applications is determined by the **Selected Software** packages. Each software package includes one or more applications as a part of its bundle. The applications contain components, which you select later in the **Components** task.

Some applications are automatically selected based on your **Selected Software**. For example, if you choose Active Workspace, the **Selected Applications** list displays the applications that are configured as required for installation.

Applications that have a **Pending Install** status are waiting for installation deployment to complete. Applications that have a **Pending Update** status are already installed but need an update to support other selections,

1. In the **Applications** task, click **Edit Selected Applications** ⊕ to add applications.

The **Available Applications** panel displays the application choices.

- 2. In Available Applications, choose the applications to install. If you choose an application that has one or more required applications associated with it, the associated applications are automatically selected. Click **Update Selected Applications** to add them to the **Selected Applications** list.
- 3. You can add or remove applications as long as they are not already installed. Selected applications show the **Pending Install** status. When your **Selected Applications** list is complete, go to the Components task.

Components task



In this task, configure components for installation. Components provide the functionality for your environment. The Selected Components list displays required components that are automatically added from the Selected Applications list. Selected Components also displays optional components that were either already installed or previously selected. You can add more optional components from the Available Components panel.

Components that have a **Pending Install** status are waiting for installation deployment to complete. Components that have a **Pending Update** status are already installed but need an update to support other selections.

Some administrative tasks require that you have server names, user names, passwords, URLs, and other information available for the deployment. The following conditions may apply during component configuration:

- If a server machine was previously deployed in another environment or is specified in the current deployment for a different component, you can select it from the Machine Name list.
- If a component has a dependency on another component that is already defined, those values are shared with dependent components. This means that the component displays some percentage of completion.
- If you have not configured a component, the state may be either **Start** or some percentage complete if it has a shared dependency.
- When you are defining parameter values, some fields may not be editable. For example, if the component is already deployed in an environment, some parameters can't be changed (such as Machine Name and OS).
- If you selected the **Single Box** environment type in the **Options task**:

- Specifying a **Machine Name**, **OS**, and **Teamcenter Installation Path** for one component shares those values with the remaining components. If you change these values on one of the components, the changes are propagated to the other components when you save.
- If a component is already selected or installed, it is only listed as an available component if multiple instances of that component are supported.

Add a component

1. In the **Components** task, click **Add component to your environment** \oplus to add components.


The **Available Components** panel displays the optional component choices.

- 2. In **Available Components**, select the components to install. Then click **Update Selected Components** to add them to the **Selected Components** list.
- 3. In **Selected Components**, the **COMPLETE** column displays the state of completion for required component settings.
- 4. Click a component in the list to display its parameters in the right panel. This panel initially displays only required parameters. You must enter values for settings that appear in required parameters view. You can toggle the view between required parameters and all parameters.
 - Show all parameters

Required parameters view displays only required parameter information. Click to expand the view to display both required and optional parameters.

Show only required parameters

All parameters view displays both required and optional parameter information. Click to collapse the view to required parameters.



5. Completing all of the required settings pushes the state to **100**% complete. If you don't have all the information you need, you can save your settings at any time and return to finish them.

For example, if you are installing the corporate server, required parameters include machine name, platform, Teamcenter installation path, and administrative user information. If you expand to **Show all parameters**, the corporate server displays additional optional settings.

- 6. When you are finished entering settings, click **Save Component Settings**.
- 7. The next component that is not complete appears in the right-side panel. When all **Selected Components** are **100**% configured, go to the **Deploy** task. The **Deploy** task is not available until the **Selected Components** are all complete.

Remove a component

You can remove a component from the list, provided that the component:

- Is optional.
- Has a status of **Pending Install**.

Dependent components that were added to the environment with the main component are also removed for the same server. Other components of the same type are not removed. For example, if you have two server pools, removing one server pool removes its dependents but the other server pool remains.

- 1. In **Selected Components**, click the component you want to remove.
- 2. From the command bar, click **Remove** \bigcirc .

You are prompted to confirm removing the component from the list.

Deploy task



In this task, generate deployment scripts for the components you want to install. Deployment scripts contain the information you configured in Deployment Center for the selected environment. These scripts install the software, applications, and components on to each target machine in your environment.

When the scripts are finished, the **Deploy Instructions** panel displays information about the deployment and instructions for proceeding with the deployment. You must copy the scripts to each target machine and run them to complete the installation.

1. To generate deployment scripts, click **Generate Install Scripts**.

Deployment Center generates installation scripts, and reports information about the scripts in the right panel.



- 2. In the **Deploy Instructions** panel, you can view the report about the deployment, including the location of the deployment scripts and the instructions for continuing the deployment.
- 3. After you confirm that the scripts you need are in the directory, you can proceed with the deployment.

Description of the Deploy Instructions

- Script Generation Date displays the time stamp for the local date and time of script generation.
- **Deployment Overview** describes the deployment covered by the scripts.
- **Software To Be Installed** lists the software required to deploy the components.
- **Software Needed For Install** lists software that is already installed on the machine but is still needed for this process to deploy other components.
- **Deploy Script Directory** displays the path to the location of the ZIP files containing the generated scripts. Go to the ZIP file directory and check for one or more ZIP files corresponding to the machines

in your Teamcenter environment. Look for the *Deploy_Instructions.html* file, which contains the same information and instructions that you reviewed in the report.

• **Deploy Scripts** displays the ZIP files that were generated for each server along with the associated component names. Each ZIP file contains the installation scripts for a single server.

If all components are to be installed on the same machine, there is only one ZIP file. The ZIP file name ends with the target machine name where you run the script. For example, if the ZIP file is named 20180511_202452EDT__Sandbox_LM6W006.zip, it runs on the LM6W006 machine. Run an installation script only on its designated machine.

Run the deployment scripts

The *deploy_scripts* staging area contains directories for each deployment environment. There is a subdirectory for each set of generated deployment scripts for the Teamcenter environment. Each server or mass client instance has its own deployment ZIP file.

The deployment files are generated to a location that was specified by the **-scriptsDir** configuration during **install** or **upgrade**, or **maintenance**.

The dc_quick_deploy utility may specify either a -scriptsDir value or a -scriptDirectoryName for the location of deployment scripts,

Deploy_Instructions.html

Provides information about the deployment and instructions for running your deployment scripts.

• Software ZIP files for the installation or update that contain the software required to complete your server or mass client deployment.

Caution:

When you deploy server components on an existing Teamcenter environment using the Deployment Center application, be sure that you run the send_configuration_to_dc utility to update the configuration information in Deployment Center before making changes. Configuration changes performed locally on Teamcenter servers since the last time the send_configuration_to_dc script ran could be overwritten.

The **Deploy Instructions** in the **Deploy task** display the path in the **Deploy Script Directory** section.

Be sure you logged in as a user with administrative privileges before running deployment scripts.

1. Navigate to the *deploy_scripts* directory. There may be one or more directories under the *deploy_scripts* directory that identify the environment with a timestamp subdirectory.

2. Determine which subdirectory you need, and find the ZIP files and the *Deploy_Instructions.html* that you generated.

The server ZIP files have the naming convention:

```
deploy_host name.zip
```

The client ZIP files have the naming convention:

```
deploy_mass_client_instance name.zip
```

3. Before you run the deployment scripts, make them available to the designated machines. For server deployments in your Teamcenter environment, copy the ZIP files to a directory that is accessible to the servers in your environment using one of these methods:

Copy the ZIP files directly to each server and unzip them

Select this method if you want to run the deployment locally on the machine. You must copy the correct ZIP file that matches each server. Be sure the server host name matches the host name in the ZIP file name.

Copy the ZIP files to a shared location, unzip them, and map a drive on each server

Select this method if you want to run the deployment from a common location accessible to all the servers in the Teamcenter environment. You must share the deployment location by mapping a drive to that location on each server.

If you unzip on a Linux system, be aware that path and file names are in mixed case. Avoid converting path and file names to lowercase, as paths are case sensitive. See the documentation for your ZIP utility for information.

Caution:

Be sure to run server deployment scripts before running client deployment scripts for an environment.

- 4. Set **JRE64_HOME** to a Java JRE 64-bit location.
- 5. If you are installing the Active Workspace Client Builder, **JAVA_HOME** must be set to the Java JDK location.
- 6. If a Teamcenter server manager is running, stop it.
- 7. Open a command prompt window and navigate to the location where you unzipped the files.
- 8. Run the deploy.bat (Windows) or deploy.sh (Linux) script with the necessary arguments:

Argument	Description
-dcusername	Specifies the user name of the Deployment Center administrator.
	You defined this user when you installed Deployment Center.
-dcpassword OR -dcpasswordfile	Specifies the password for the Deployment Center administrator.
	Use -dcpassword to specify the password as text, or use -dcpasswordfile to specify an encrypted password or password file. If the password file path contains spaces, enclose it in quotes.
-softwareLocation	Specifies the software location or locations.
	Set to default to find software in the registered repository directories, or specify one or more software paths separated by commas. For example:
	-softwareLocation=D:\deploy_software,X:\Foundation_s oftware
	The software directories specified must include <i>software</i> subdirectories.
-dcurl (optional)	Specifies the URL to the Deployment Center server, if it differs from the URL specified in the deploy script.
	When you run a deployment script on a server that is on a different network than the Deployment Center server, you can specify an alternate URL for Deployment Center. You may specify a fully qualified domain name, an alias, or a reverse proxy for the server in the URL.
	The specified URL replaces the Deployment Center URL in the deploy script configuration for authentication and communication with the Deployment Center server.
-diagnosticChecks (optional)	Specifies diagnostic mode.
	This option runs a diagnostic validation test of the deployment. Diagnostic mode checks whether the deployment tasks in the deploy script can be completed successfully on the target machine. Diagnostic mode does not perform any updates during validation.
	Run the deploy script in diagnostic mode to validate properties like operating system and database credentials, ports, installation paths, FSC unique IDs, and so on. The log output provides success and failure information.
	For client mass installation scripts, there is no server host validation as they are machine neutral.
	Make any necessary corrections in Deployment Center, regenerate your deployment scripts, and run them again in diagnostic mode. Repeat until all the errors are addressed.
-ignoreDiagnostics (optional)	Skips diagnostic validation tests of the deployment.
	You may want to ignore diagnostic validation if you determine that an issue reported by -diagnosticChecks does not need to be addressed.

Argument	Description
	Specify this argument if you've received a diagnostic report that meets your requirements for acceptable deployment.
-startServices	Starts the services of all required components in an installed environment. Run the deploy script in this mode to start all the necessary services. Running the deployment with this option <i>only</i> performs the service start operation and skips executing the remainder of the deployment tasks.
-stopServices	Stops the services of all required components in an installed environment. Run the deploy script in this mode to stop all the necessary services. Running the deployment with this option <i>only</i> performs the service stop operation and skips executing the remainder of the deployment tasks.
-getServiceStatus	Retrieves the status of the services of all required components in an installed environment. Run the deploy script in this mode to retrieve the status of all the necessary services. Running the deployment with this option <i>only</i> performs the service status operation and skips executing the remainder of the deployment tasks.

On Linux systems, make sure you run the script in Korn Shell (ksh) to avoid errors. For example:

```
./deploy.sh -softwareLocation=/kits/software
```

When the installation or update is complete, the command prompt returns a success message with the location of the log files.

If you experience a problem in running the deploy script, see Troubleshoot the deployment script.

If you have multiple Teamcenter servers in your environment, you can run deployment scripts on them in parallel. To do this, run the deployment script on the primary business logic server (the corporate server) first. Deployment Center uploads a dataset to the volume that contains key items from the TC_DATA directory, which provides the necessary information for deploying on the remaining servers. You can then subsequently run the install or update deployment script on the remaining servers concurrently. Running deployment scripts in parallel can significantly reduce deployment time.

How to deploy using a software mini-kit

If you generated a software mini-kit, you can run the mass client deploy script using the mini-kit by performing the following steps:

Copy the mini-kit zip file to a directory accessible to the target machine on which you will run the mass client deploy script.

The mini-kit file is named env-name mass-client-instance OS.zip, for example, Env001 TcMassClient wntx64.zip.

⁻dcusername=dcadmin -dcpasswordfile=/opt/passwords/dcadmin.pwf

⁻dcurl=http://dcserver.mysite.com:8008/deploymentcenter

- 2. Expand (unzip) the mini-kit in the location to which you copied it.
- 3. Copy the mass client deploy script (*deploy.bat* on Windows or *deploy.sh* on Linux) to the target machine.
- 4. Run the mass client deploy script as for a typical installation, except in the **softwareLocation** argument, specify the location of the mini-kit you expanded in step 2.

Troubleshoot the deployment script

There are two types of deployment scripts, server deployment and client deployment. Log files provide information on how to address an issue.

When generating deployment scripts, you can check for log files in the **logs** directory under the **ScriptDir** directory.

As a best practice, run deployment scripts in diagnostic mode on the target machines to validate the configuration entered in Deployment Center. Running each deployment script in diagnostic mode tests the deployment configuration without making changes to the target machine during diagnostic validation.

Troubleshooting server component deployment scripts

Review the log files for the *deploy.bat* or *deploy.sh* scripts and check for errors. If you have errors, make the corrections using the method you used to create the deployment script. Regenerate the deployment scripts and run them again in diagnostic mode. Repeat the cycle until all errors are addressed.

The log files are located in the **logs** directory under the *deployment_script_dir* directory on the Teamcenter machine where you are running *deploy.bat* or *deploy.sh*:

Some of the more common errors you may see:

- Inability to locate the software required by the script as specified by -softwareLocation.
- Inability to communicate with a Deployment Center server.
- A deployment failure.

When the deployment script runs on a Teamcenter server, it may encounter errors that are outside the scope of Deployment Center. If an error occurs when you run *deploy.bat* or *deploy.sh*, check the log file *deployer timestamp.log*:

- 1. Look for a section titled **Diagnostic Checks Details**, which provides validation information.
- 2. Look for the point of failure and check whether the error notification is followed by a path to another log file on the Teamcenter server. For example, a Business Modeler IDE error can generate

its own log file, which is saved on the Teamcenter server. The path to other log files is provided in the deployer_timestamp.log.

3. If the script reports an error without an explanation, check Teamcenter server error logs, which are located in either the *logs* directory under *TC_ROOT* or the server's temporary directory (for example, *TEMP* or *TMP*).

In the Teamcenter error logs, look for an error that has a timestamp for approximately the same time as the error logged in *deployer_timestamp.log*.

Tip:

Be sure that your environment is not running when you deploy.

5. Deploying software using Deployment Center

6. Quick deployment

Understanding quick deployment

An alternative to using the Deployment Center application is to deploy software using a utility. The utility uses an XML configuration file to provide the software, application, and component information for your target environment. You can install a new Teamcenter environment or update an existing one.

Quick deployment considerations

Consider using quick deployment if:

- You want to deploy a simple environment quickly.
- You want to make regular scripted updates to an environment.
- You want to generate test or development environments frequently.
- You want to generate new environments from existing environments.
- You want to schedule or automate environment updates using continuous development tools.

The quick deployment approach

The principles for setting up an environment and choosing software in the Deployment Center application also apply to the quick deployment process. You must have experience setting up and configuring applications and components for Teamcenter environments to effectively use this approach.

The quick deployment procedure explains how to:

Create the XML configuration file that contains application and component configuration for your
environment. You can export an XML configuration file from an existing environment to use as a
starting point. Update the file with the configuration required to install or update your Teamcenter
environment. XML configuration files can be generated from the Deployment Center application
Environments page or the dc_quick_deploy utility.

You may want to use an existing environment that was created using Teamcenter Environment Manager (TEM) as your starting point. Register the environment using the send_configuration_to_dc utility to send the configuration information to Deployment Center. Then you can generate an XML configuration file from the environment for editing.

• Create deployment scripts for the target environment by running the dc_quick_deploy utility. The input is your XML file containing your software, application, and component configuration. The utility generates the deployment scripts in the directory specified by the -scriptsDir parameter. Configure the locations for the -scriptsDir parameter during install, upgrade, or maintenance.

• Run the deployment scripts generated by dc_quick_deploy on the target component servers, as you normally would, to complete the installation or update.

Quick deployment procedure

The quick deployment process creates or updates a Teamcenter environment using deployment scripts generated by the dc_quick_deploy utility. The process uses an XML configuration file to provide application and component information rather than obtaining it directly from the Deployment Center application.

This type of deployment requires that software, application, and component configuration information are defined in a structured XML configuration file. The dc_quick_deploy utility processes the XML file, and then generates deployment scripts and instructions.

If you are also deploying mass client installations or updates, the **dc_quick_deploy** utility generates **two types of deploy scripts**, one for server software and one for client software.

Define your deployment

Before you begin, define the components for your software and applications. Gather and evaluate the associated server information as needed for each component. You must have experience setting up and configuring applications and components for Teamcenter environments to successfully use the quick deploy approach.

Ensure the repository has the software required for your installation or update. Identify and include any software dependencies. Determine whether you are using a single or distributed server environment. Define the list of applications and their dependencies.

You may need to know server names, locations, operating systems, port numbers, user names, passwords, installation paths, connection URLs, or other required or optional settings for your components.

You can obtain software configuration information in a couple of ways:

- You can review software configuration information from the **Repositories** page for each software kit. From the **Active Media** tab, click **Generate Software Configuration Report**. The HTML report provides comprehensive information about software dependencies and IDs, application internal names and dependencies, and component and property internal names and configuration values.
- You can create a quick deploy XML configuration file from an existing Teamcenter environment and edit it for reuse in another environment.

Information from the Software Configuration Report may be helpful in making updates to the XML configuration file.

- 1. Assemble the information required to successfully deploy the target Teamcenter environment, including software, application, server, and configuration settings.
- 2. Create an XML configuration file to work from. You can evaluate the best method to create or obtain an XML configuration file.

You may prefer to start from an existing Teamcenter environment configuration:

- If the environment is registered in Deployment Center, select it from the **Environments** page and choose **Export Environment** \rightarrow .
- Run the dc_quick_deploy utility in export mode to generate an XML configuration file from a specified environment.
- For an environment that was configured using TEM, register the environment with Deployment Center using the send_configuration_to_dc utility. Then you can export an XML configuration file.
- 3. Edit the XML configuration file, ensuring it contains all the configuration information for your desired environment.
 - You will need to provide passwords for target servers in the configuration file. The **dc_quick_deploy** utility can generate **encrypted passwords** for you if needed. The encrypted password can then be entered in the XML configuration for the specific component.
- 4. After you complete the XML configuration file, run the **dc_quick_deploy** utility in **import mode** to generate deployment scripts. The import mode requires the XML configuration file you created as input.

The output includes generated deployment scripts for each of the servers in your environment and a Deploy Instructions HTML file.

If dc_quick_deploy encounters an error, the returned error message includes information about how to resolve the problem.

If you are generating both client and server scripts, the output provides:

- One or more server scripts, where the zip file name follows the pattern **deploy** server-name.zip.
- One script for each set of client installs, where the zip file name follows the pattern deploy_mass_client.zip.
- 5. After the script files and instructions are generated, copy them to each target machine and run them as you usually would. Run the deployment script in diagnostic mode on the target machine to determine whether you have errors. After making your corrections, run the deployment script.

Using the dc_quick_deploy utility

The dc_quick_deploy utility provides the same functionality as the Deployment Center application for creating or updating a Teamcenter environment. This command line approach provides the configuration information for your environment's software, applications, and components in an XML configuration file. Then the dc_quick_deploy utility processes the configuration information to generate deployment scripts for the target component servers. The quick deployment procedure guides you through producing the XML configuration file and generating the deployment scripts.

Find dc quick deploy.zip in the Deployment Center installation under the \additional tools directory.

Unzip the file to use dc_quick_deploy.bat (Windows) or dc_quick_deploy.sh (Linux).

The dc_quick_deploy utility has two explicit modes, export and import. You can also use dc_quick_deploy to encrypt passwords for your XML configuration files. In a command window, you can enter dc_quick_deploy-help to return usage details.

Export mode

The **export** mode exports the configuration information for an existing environment in Deployment Center. Use this mode to generate a valid XML configuration file that you can use as a starting point for a new or updated environment. The following arguments are *required* when you run the **dc_quick_deploy** utility in export mode:

Argument	Description
-mode (required)	Specifies export to generate the environment's configuration.
-environment (required)	Specifies the name of the Teamcenter environment being exported.
-exportfile (required)	Specifies the full path and name of the file, including the .xml extension, where the configuration file will be exported.
-exportType (required)	Specifies whether the exported file contains Full (all component properties) or Lean (only required properties) configuration information.
-dcURL (required)	Specifies the URL to access Deployment Center.
-dcusername (required)	Specifies the user name for Deployment Center as defined when installing Deployment Center.
-dcpassword or -dcpasswordfile (one is required)	Specifies the password text <i>or</i> the encrypted password or file .
-preserveDeploymentStatus (optional)	Specifies you want to export the environment preserving the deployment status of software, applications, and components.

Example:

```
dc_quick_deploy.bat -dcurl=http://abc34xyz:8080/deploymentcenter
   -mode=export -environment=test_env -exportType=Full
   -exportfile=D:\export_files\quick_deploy.xml
   -dcusername=dcadmin -dcpassword=14pXjKcFG8CIrbjdy1teV5JWJY
```

Import mode

The **import** mode imports a configuration file containing the configuration for the specified environment. Use this mode to import a valid XML configuration file for a new or updated environment. The following arguments are available when you when you run the **dc_quick_deploy** utility in import mode:

Argument	Description
-mode (optional)	Specified by default, import imports the specified XML configuration file.
-environment (required)	Specifies the name of the Teamcenter environment being created or updated.
-inputFile (required)	Specifies the path and file name for a valid environment XML configuration file.
-dcURL (required)	Specifies the URL to access Deployment Center.
-dcusername (required)	Specifies the user name for Deployment Center as defined when installing Deployment Center.
-dcpassword or -dcpasswordfile	Specifies the password text or the encrypted password or file.
-machine (optional)	Specifies the name of the machine where the deployment scripts will be generated, which defaults to the current user's machine if not specified.
-platform (optional)	Specifies the operating system for the machine where the deployment scripts will be generated, which defaults to the current user's platform if not specified. For example, use wntx64 for Windows and Inx64 for Linux.
-scriptDirectoryName or -scriptsDir (optional)	 Specifies the path to where deployment scripts will be generated. -scriptDirectoryName specifies a directory name using letters, numbers, and underscores. No special characters or spaces are supported. -scriptsDir specifies the parameter that represents the path where you want to generate deployment scripts. The parameter was defined during Deployment Center installation, upgrade, or maintenance. For example, -scriptsDir=scriptsDir123 resolves to the file path that was configured for scriptsDir123.

Argument	Description
	If -scriptsDir resolves to a UNC path, Deployment Center must be running as a Windows service.

Example:

```
dc_quick_deploy.bat -dcurl=http://localhost:8080/deploymentcenter
  -environment=test_env -platform=wntx64 -machine=abc236wxyz
  -inputFile=D:\import_files\quick_deploy_input.xml
  -dcusername=dcadmin -dcpasswordfile=C:\dc_pwds\deploymentcenter.pwf
```

Encrypt passwords for your server components

You can use **dc_quick_deploy** to quickly generate encrypted passwords that you can use to specify passwords in the XML configuration file.

```
dc_quick_deploy -encrypt=clear_text_password
```

Enter the resulting encrypted password in the property specification for a component, as in this example:

```
cproperty id="fnd0_tcAdminPassword" value="'IE6tFf61dcrRZHuMzJ34Sx2a"
encrypted="true"/>
```

Creating an XML configuration file

The **dc_quick_deploy** utility requires an XML file containing the configuration information to create deployment scripts for the desired environment. The XML configuration file contains an environment's settings for software, applications, and components.

The easiest way to create an XML configuration file is to export the current configuration of an existing environment that most closely resembles the one you wish to produce. You can then edit the exported XML file to add or update the configuration information for your desired environment. After you complete your edits, run **dc_quick_deploy** again, and import the XML configuration file as the input file. This action generates the scripts you deploy on the target servers.

You can find examples of XML configurations files to assist you.

Choose an export method

There are a couple of ways to export an environment's XML configuration file:

• On the **Environments** page, choose an environment from the list, and click **Export Environment** \Rightarrow .

Select whether you want the output XML file to contain all component configuration properties or just the required component properties.

 Use the export mode of the dc_quick_deploy utility to generate an XML configuration file for a specified environment.

Choose whether you want to generate a full (all configuration properties) or lean (only required configuration properties) XML file.

Choose either Full or Lean configuration

As part of a strategy for creating Teamcenter environments, evaluate what the XML configuration file requires. When specifying the **exportType**, you can choose **Full** or **Lean**.

Full

Includes all the application and component parameters for the environment.

Lean

For applications:

• Includes only top level applications that display in the Deployment Center application.

Does not include applications associated by default with a software selection, such as Teamcenter Foundation and Active Workspace.

Does not include applications that are either automatically selected as dependent applications or hidden in Deployment Center.

For components:

Includes only required properties for components, including properties that have a value different from the default value.

Import the XML configuration file

After you update the XML configuration for your desired environment, use the the import mode of the dc quick deploy utility to generate the scripts to create the environment from the input XML configuration file.

Find examples of quick deploy XML configuration files

The Teamcenter Deployment Reference Architecture contains sample Quick Deploy and configuration files that you can review to learn more about the XML file structure.

Download the Teamcenter Deployment Reference Architecture from the Support White Papers Teamcenter Deployment Reference Architecture page on Support Center:

Log on to Support Center and open **Products**→**Teamcenter**→**Downloads**. 1.

- Under Select a Version, choose Support White Papers → Support White Papers Teamcenter
 Deployment Reference Architecture, and then click the Support White Papers Teamcenter
 Deployment Reference Architecture tile.
- Download the latest version of the Teamcenter_Deployment_Reference_Architecture_version.zip file.

Also, the **Software Configuration Report** contains information that may be helpful in making updates to the XML configuration file.

Sharing components across environments using Quick Deploy

Using Deployment Center, you can create an environment that contains client components that can be shared across multiple Teamcenter environments. By setting the **Infrastructure Type** option in Deployment Center to **Global**, you create an environment whose components can be imported into environments whose **Infrastructure Type** is set to **Local**.

The following client components are supported for sharing from a Global infrastructure environment:

- Rich client four-tier
- Teamcenter client communication system
- Teamcenter Security Service Session Agent

You can create a Global or Local environment using Quick Deploy.

The following example defines a Global infrastructure environment. The **infraTypeName** tag designates the environment as **Global**. The **infrastructureType** properties indicate a component belongs to a Global environment and is therefore sharable.

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<quickDeployConfig configName="Env_006" version="1.0">
    <archType types="J2EE"/>
    <infraType infraTypeName="GlobalEnvironment"/>
    <quickDeploySoftware>
        <software id="Foundation" version="2312.20231030.00"/>
    </quickDeploySoftware>
    <quickDeployApplications/>
    <quickDeployClients>
        <client id="fnd0_4tierrichclient" machineName="testingl"</pre>
massDeploy="false" platform="wntx64
            cproperty id="fnd0_compressWebResponse" value="true"/>
            cproperty id="fnd0_4tierrichclient.massDeployCheck"
value="false"/>
            cproperty id="fnd0_4tierrichclientInstallationPath"
value="C:\Program Files\Siemens\Teamcenter\
                teamcenter root"/>
            cproperty id="fnd0_4tierrichclient.appSupportedList"
```

After configuring the Quick Deploy script for your Global infrastructure environment, you can deploy it using the dc_quick_deploy utility.

You can similarly define a Local infrastructure environment in a Quick Deploy script like the following example. Note the **infrastructureType** property that denotes the environment as a Local infrastructure. **imported** properties denote components imported from a Global infrastructure environment.

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<quickDeployConfiq confiqName="Env 001" version="1.0">
   <archType types=J2EE"/>
   <quickDeploySoftware>
      <software id="Foundation" version="2312.20231030.00"/>
   </quickDeploySoftware>
   <quickDeployApplications/>
   <quickDeployClients>
      <cli>d="fnd0_4tierrichclient" globalEnvName="GlobalEnvTestl5"
globalMachineName="testingl"
  globalInstallationPath="C:\Program Files\Siemens\Teamcenter\teamcenter_root">
          cproperty id="fnd0_4tierrichclient.imported" value="true"/>
          <package id="fnd0 foundation"/>
      </client>
      <client id="fnd0_tccs" machineName="testing1" massDeploy="false"</pre>
platform="wntx64">
          cproperty id="fnd0_tccsMergeFromFMSHorae" value=""/>
          cproperty id="fnd0_tccsEnableClientCommunicationConfig"
value=""/>
          operty id="fnd0_tccs.massDeployCheck." value="false"/>
          Files\Siemens\Teamcenter\teamcenter_root"/>
          cproperty id="fnd0_tccslocal" value="false"/>
          cproperty id="fnd0_reverseProxyCriteriaList" value=""/>
```

cproperty id="fnd0 tccsinfrastructureType" value="Local"/>

```
</client>
    <quickDeployComponents>
        <component id="fnd0_corporateserver" machineName="testing1"</pre>
platform="wntx64
        <component id="fnd0_licensingserver" machineName="testingl"</pre>
platform="wntx64">
        <component id="fnd0_fsc" machineName="testingl"</pre>
platform="wntx64">
        <component id="fnd0_fsc keys" machineName="fsc"</pre>
platform="wntx64">
        <component id="fnd0_fsc group" machineName="fsc"</pre>
platform="wntx64">
        <component id="fnd0_tcdbserver" machineName="testingl"</pre>
platform="wntx64">
        <component id="fnd0_serverManager" machineName="testing1"</pre>
platform="wntx64">
        <component id="fnd0_j2ee tcwebtier" machineName="testing1"</pre>
platform="wntx64">
        <component id="fnd0_serverpool DBConfig" machineName="testingl"</pre>
platform="wntx64">
    </quickDeployComponents>
    <quickDeployProperties>
         cproperty id="InstallDirectory" value="C:\Program
Files\Siemens\Teamcenter\teamcenter root"/>
    </quickDeployProperties>
</quickDeployConfig>
```

Again, you can deploy your Local infrastructure environment using the dc_quick_deploy utility.

Troubleshoot quick deployment

Review the logs generated by the dc_quick_deploy utility on the Deployment Center server in deployment_center_server_dir logs.

7. How to deploy the Business Modeler IDE templates on Teamcenter

Deploy Business Modeler IDE packages

Users can generate a Business Modeler IDE template package in Teamcenter 11.3 or later that can be deployed to Teamcenter environments using either Deployment Center or Teamcenter Environment Manager (TEM). This consolidated output directory contains templates, libraries, and deployment configuration files.

To deploy a Business Modeler IDE template package, obtain the directory of the template package output generated by the Business Modeler IDE. Place the Business Modeler IDE output directory in the *software* subdirectory of the Deployment Center repository.

To ensure you have a supported template package, check:

• Directory naming convention

template-internal-name_OS_template-version_build-version_YYYY_MM_DD_HH-MM-SS

An optional template version may be assigned by the Business Modeler IDE user to track the versions of a template package. If the Business Modeler IDE user assigns a build number, the template is in development. The build version tracks iterative testing before the template is ready for production. Template versions and build versions are expressed as integers separated by periods, up to four places.

· artifacts subdirectory

Contains the template software ZIP files for deployment.

• dc contributions subdirectory

Contains the template bundle information (called packages) for deployment by Deployment Center. If you use TEM, this directory is ignored.

tem contributions subdirectory

Contains the template bundle information for deployment by TEM. If you use Deployment Center, this directory is ignored.

media_teamcenter_template-package-name.xml file

Provides the application names to both TEM and Deployment Center for deployment.

7. How to deploy the Business Modeler IDE templates on Teamcenter

The Deployment Center repository displays **Dependencies** as specified within Business Modeler IDE packages using package IDs.

For information on creating and updating Business Modeler IDE packages, refer to the Business Modeler IDE documentation included with Teamcenter.