◆ PREVIOUS NEXT ▶

# 3.1 Introduction

This chapter begins the description of the sockets API. We begin with socket address structures, which will be found in almost every example in the text. These structures can be passed in two directions: from the process to the kernel, and from the kernel to the process. The latter case is an example of a value-result argument, and we will encounter other examples of these arguments throughout the text.

The address conversion functions convert between a text representation of an address and the binary value that goes into a socket address structure. Most existing IPv4 code uses inet\_addr and inet\_ntoa, but two new functions, inet\_pton and inet\_ntop, handle both IPv4 and IPv6.

One problem with these address conversion functions is that they are dependent on the type of address being converted: IPv4 or IPv6. We will develop a set of functions whose names begin with sock\_ that work with socket address structures in a protocol-independent fashion. We will use these throughout the text to make our code protocol-independent.

[ Team LiB ]

◆ PREVIOUS NEXT ▶

1 of 1 10-12-2022, 12:18

4 PREVIOUS NEXT ▶

## 3.2 Socket Address Structures

Most socket functions require a pointer to a socket address structure as an argument. Each supported protocol suite defines its own socket address structure. The names of these structures begin with <code>sockaddr\_</code> and end with a unique suffix for each protocol suite.

### **IPv4 Socket Address Structure**

An IPv4 socket address structure, commonly called an "Internet socket address structure," is named <code>sockaddr\_in</code> and is defined by including the <code><netinet/in.h></code> header. Figure 3.1 shows the POSIX definition.

### Figure 3.1 The Internet (IPv4) socket address structure: sockaddr\_in.

```
struct in addr {
                              /* 32-bit IPv4 address */
 in addr t s addr;
                              /* network byte ordered */
struct sockaddr_in {
                              /* length of structure (16) */
 uint8_t sin_len;
                             /* AF INET */
  sa family t
                sin family;
               sin_port;
                             /* 16-bit TCP or UDP port number */
 in_port_t
                              /* network byte ordered */
                             /* 32-bit IPv4 address */
 struct in_addr sin_addr;
                              /* network byte ordered */
                 sin_zero[8]; /* unused */
```

There are several points we need to make about socket address structures in general using this example:

• The length member, sin\_len, was added with 4.3BSD-Reno, when support for the OSI protocols was added (Figure 1.15). Before this release, the first member was sin\_family, which was historically an unsigned short. Not all vendors support a length field for socket address structures and the POSIX specification does not require this member. The datatype that we show, uint8\_t, is typical, and POSIX-compliant systems provide datatypes of this form (Figure 3.2).

Figure 3.2. Datatypes required by the POSIX specification.

Datatype	Description	Header
int8_t	Signed 8-bit integer	<sys types.h=""></sys>
uint8_t	Unsigned 8-bit integer	<sys types.h=""></sys>
int16_t	Signed 16-bit integer	<sys types.h=""></sys>
uint16_t	Unsigned 16-bit integer	<sys types.h=""></sys>
int32_t	Signed 32-bit integer	<sys types.h=""></sys>
uint32_t	Unsigned 32-bit integer	<sys types.h=""></sys>
sa_family_t	Address family of socket address structure	<sys socket.h=""></sys>
socklen_t	Length of socket address structure, normally uint32_t	<sys socket.h=""></sys>
in_addr_t	IPv4 address, normally uint32_t	<netinet in.h=""></netinet>
in_port_t	TCP or UDP port, normally uint16_t	<netinet in.h=""></netinet>

Having a length field simplifies the handling of variable-length socket address structures.

Even if the length field is present, we need never set it and need never examine it, unless we are dealing with routing sockets
 (<u>Chapter 18</u>). It is used within the kernel by the routines that deal with socket address structures from various protocol families (e.g., the routing table code).

The four socket functions that pass a socket address structure from the process to the kernel, bind, connect, sendto, and sendmsg, all go through the sockargs function in a Berkeley-derived implementation (p. 452 of TCPv2). This function copies the socket address structure from the process and explicitly sets its  $\sin_l$ en member to the size of the structure that was passed as an argument to these four functions. The five socket functions that pass a socket address structure from the kernel to the process, accept, recvfrom, recvmsg, getpeername, and getsockname, all set the  $\sin_l$ en member before returning to the process.

Unfortunately, there is normally no simple compile-time test to determine whether an implementation defines a length field for its socket address structures. In our code, we test our own HAVE SOCKADDR SA LEN constant (Figure

<u>D.2</u>), but whether to define this constant or not requires trying to compile a simple test program that uses this optional structure member and seeing if the compilation succeeds or not. We will see in <u>Figure 3.4</u> that IPv6 implementations are required to define <u>SIN6\_LEN</u> if socket address structures have a length field. Some IPv4 implementations provide the length field of the socket address structure to the application based on a compile-time option (e.g., \_SOCKADDR\_LEN). This feature provides compatibility for older programs.

- The POSIX specification requires only three members in the structure: sin\_family, sin\_addr, and sin\_port. It is acceptable for a POSIX-compliant implementation to define additional structure members, and this is normal for an Internet socket address structure. Almost all implementations add the sin\_zero member so that all socket address structures are at least 16 bytes in size.
- We show the POSIX datatypes for the s\_addr, sin\_family, and sin\_port members. The in\_addr\_t datatype must be an unsigned integer type of at least 32 bits, in\_port\_t must be an unsigned integer type of at least 16 bits, and sa\_family\_t can be any unsigned integer type. The latter is normally an 8-bit unsigned integer if the implementation supports the length field, or an unsigned 16-bit integer if the length field is not supported. Figure 3.2 lists these three POSIX-defined datatypes, along with some other POSIX datatypes that we will encounter.
- You will also encounter the datatypes u\_char, u\_short, u\_int, and u\_long, which are all unsigned. The POSIX specification defines these with a note that they are obsolete. They are provided for backward compatibility.
- Both the IPv4 address and the TCP or UDP port number are always stored in the structure in network byte order. We must be cognizant of this when using these members. We will say more about the difference between host byte order and network byte order in Section 3.4.
- The 32-bit IPv4 address can be accessed in two different ways. For example, if serv is defined as an Internet socket address structure, then serv.sin\_addr references the 32-bit IPv4 address as an in\_addr structure, while serv.sin\_addr.s\_addr references the same 32-bit IPv4 address as an in\_addr\_t (typically an unsigned 32-bit integer). We must be certain that we are referencing the IPv4 address correctly, especially when it is used as an argument to a function, because compilers often pass structures differently from integers.

The reason the  $sin\_addr$  member is a structure, and not just an  $in\_addr\_t$ , is historical. Earlier releases (4.2BSD) defined the  $in\_addr$  structure as a union of various structures, to allow access to each of the 4 bytes and to both of the 16-bit values contained within the 32-bit IPv4 address. This was used with class A, B, and C addresses to fetch the appropriate bytes of the address. But with the advent of subnetting and then the disappearance of the various address classes with classless addressing (Section A.4), the need for the union disappeared. Most systems today have done away with the union and just define in addr as a structure with a single in addr t member.

• The sin\_zero member is unused, but we *always* set it to 0 when filling in one of these structures. By convention, we always set the entire structure to 0 before filling it in, not just the sin zero member.

Although most uses of the structure do not require that this member be 0, when binding a non-wildcard IPv4 address, this member must be 0 (pp. 731–732 of TCPv2).

• Socket address structures are used only on a given host: The structure itself is not communicated between different hosts, although certain fields (e.g., the IP address and port) are used for communication.

## **Generic Socket Address Structure**

A socket address structures is *always* passed by reference when passed as an argument to any socket functions. But any socket function that takes one of these pointers as an argument must deal with socket address structures from *any* of the supported protocol families.

A problem arises in how to declare the type of pointer that is passed. With ANSI C, the solution is simple: void \* is the generic pointer type. But, the socket functions predate ANSI C and the solution chosen in 1982 was to define a *generic* socket address structure in the <sys/socket.h> header, which we show in Figure 3.3.

#### Figure 3.3 The generic socket address structure: sockaddr.

The socket functions are then defined as taking a pointer to the generic socket address structure, as shown here in the ANSI C function prototype for the bind function:

```
int bind(int, struct sockaddr *, socklen t);
```

This requires that any calls to these functions must cast the pointer to the protocol-specific socket address structure to be a pointer to a generic socket address structure. For example,

If we omit the cast "(struct sockaddr \*)," the C compiler generates a warning of the form "warning: passing arg 2 of 'bind' from incompatible pointer type," assuming the system's headers have an ANSI C prototype for the bind function.

From an application programmer's point of view, the *only* use of these generic socket address structures is to cast pointers to protocol-specific structures.

Recall in <u>Section 1.2</u> that in our unp.h header, we define SA to be the string "struct sockaddr" just to shorten the code that we must write to cast these pointers.

From the kernel's perspective, another reason for using pointers to generic socket address structures as arguments is that the kernel must take the caller's pointer, cast it to a struct sockaddr \*, and then look at the value of sa\_family to determine the type of the structure. But from an application programmer's perspective, it would be simpler if the pointer type was void \*, omitting the need for the explicit cast.

## **IPv6 Socket Address Structure**

The IPv6 socket address is defined by including the <netinet/in.h> header, and we show it in Figure 3.4.

#### Figure 3.4 IPv6 socket address structure: sockaddr in6.

The extensions to the sockets API for IPv6 are defined in RFC 3493 [Gilligan et al. 2003].

Note the following points about <u>Figure 3.4</u>:

- The SIN6 LEN constant must be defined if the system supports the length member for socket address structures.
- The IPv6 family is AF INET6, whereas the IPv4 family is AF INET.
- The members in this structure are ordered so that if the <code>sockaddr\_in6</code> structure is 64-bit aligned, so is the 128-bit <code>sin6\_addr</code> member. On some 64-bit processors, data accesses of 64-bit values are optimized if stored on a 64-bit boundary.
- The sin6 flowinfo member is divided into two fields:
  - O The low-order 20 bits are the flow label
  - O The high-order 12 bits are reserved

The flow label field is described with Figure A.2. The use of the flow label field is still a research topic.

The sin6\_scope\_id identifies the scope zone in which a scoped address is meaningful, most commonly an interface index for a link-local address (Section A.5).

#### **New Generic Socket Address Structure**

A new generic socket address structure was defined as part of the IPv6 sockets API, to overcome some of the shortcomings of the existing struct sockaddr. Unlike the struct sockaddr, the new struct sockaddr\_storage is large enough to hold any socket address type supported by the system. The sockaddr storage structure is defined by including the <netinet/in.h> header, which we show in Figure 3.5.

## Figure 3.5 The storage socket address structure: sockaddr\_storage.

The sockaddr storage type provides a generic socket address structure that is different from struct sockaddr in two ways:

- **a.** If any socket address structures that the system supports have alignment requirements, the <code>sockaddr\_storage</code> provides the strictest alignment requirement.
- **b.** The sockaddr storage is large enough to contain any socket address structure that the system supports.

Note that the fields of the <code>sockaddr\_storage</code> structure are opaque to the user, except for <code>ss\_family</code> and <code>ss\_len</code> (if present). The <code>sockaddr\_storage</code> must be cast or copied to the appropriate socket address structure for the address given in <code>ss\_family</code> to access any other fields.

# **Comparison of Socket Address Structures**

Figure 3.6 shows a comparison of the five socket address structures that we will encounter in this text: IPv4, IPv6, Unix domain (Figure 15.1), datalink (Figure 18.1), and storage. In this figure, we assume that the socket address structures all contain a one-byte length field, that the family field also occupies one byte, and that any field that must be at least some number of bits is exactly that number of bits.




Figure 3.6. Comparison of various socket address structures.

Two of the socket address structures are fixed-length, while the Unix domain structure and the datalink structure are variable-length. To handle variable-length structures, whenever we pass a pointer to a socket address structure as an argument to one of the socket functions, we pass its length as another argument. We show the size in bytes (for the 4.4BSD implementation) of the fixed-length structures beneath each structure.

The sockaddr\_un structure itself is not variable-length (Figure 15.1), but the amount of information—the pathname within the structure—is variable-length. When passing pointers to these structures, we must be careful how we handle the length field, both the length field in the socket address structure itself (if supported by the implementation) and the length to and from the kernel.

This figure shows the style that we follow throughout the text: structure names are always shown in a bolder font, followed by braces, as in sockaddr\_in{}.

We noted earlier that the length field was added to all the socket address structures with the 4.3BSD Reno release. Had the length field been present with the original release of sockets, there would be no need for the length argument to all the socket functions: the third argument to bind and connect, for example. Instead, the size of the structure could be contained in the length field of the structure.

[ Team LiB ]

◆ PREVIOUS NEXT ▶

5 of 5 10-12-2022, 12:18



# 3.3 Value-Result Arguments


We mentioned that when a socket address structure is passed to any socket function, it is always passed by reference. That is, a pointer to the structure is passed. The length of the structure is also passed as an argument. But the way in which the length is passed depends on which direction the structure is being passed: from the process to the kernel, or vice versa.

1. Three functions, bind, connect, and sendto, pass a socket address structure from the process to the kernel. One argument to these three functions is the pointer to the socket address structure and another argument is the integer size of the structure, as in

```
struct sockaddr_in serv;
/* fill in serv{} */
connect (sockfd, (SA *) &serv, sizeof(serv));
```

Since the kernel is passed both the pointer and the size of what the pointer points to, it knows exactly how much data to copy from the process into the kernel. Figure 3.7 shows this scenario.

Figure 3.7. Socket address structure passed from process to kernel.



We will see in the next chapter that the datatype for the size of a socket address structure is actually <code>socklen\_t</code> and not <code>int</code>, but the POSIX specification recommends that <code>socklen\_t</code> be defined as <code>uint32 t</code>.

2. Four functions, accept, recvfrom, getsockname, and getpeername, pass a socket address structure from the kernel to the process, the reverse direction from the previous scenario. Two of the arguments to these four functions are the pointer to the socket address structure along with a pointer to an integer containing the size of the structure, as in

```
struct sockaddr_un cli;  /* Unix domain */
socklen_t len;
len = sizeof(cli);  /* len is a value */
getpeername(unixfd, (SA *) &cli, &len);
/* len may have changed */
```

The reason that the size changes from an integer to be a pointer to an integer is because the size is both a *value* when the function is called (it tells the kernel the size of the structure so that the kernel does not write past the end of the structure when filling it in) and a *result* when the function returns (it tells the process how much information the kernel actually stored in the structure). This type of argument is called a *value-result* argument. Figure 3.8 shows this scenario.

1 of 2 10-12-2022, 12:18

int \*
length
socket
address
structure

protocol
address
kernel

Figure 3.8. Socket address structure passed from kernel to process.

We will see an example of value-result arguments in  $\underline{\text{Figure 4.11}}$ .

We have been talking about socket address structures being passed between the process and the kernel. For an implementation such as 4.4BSD, where all the socket functions are system calls within the kernel, this is correct. But in some implementations, notably System V, socket functions are just library functions that execute as part of a normal user process. How these functions interface with the protocol stack in the kernel is an implementation detail that normally does not affect us. Nevertheless, for simplicity, we will continue to talk about these structures as being passed between the process and the kernel by functions such as bind and connect. (We will see in Section C.1 that System V implementations do indeed pass socket address structures between processes and the kernel, but as part of STREAMS messages.)

Two other functions pass socket address structures: recvmsg and sendmsg (Section 14.5). But, we will see that the length field is not a function argument but a structure member.

When using value-result arguments for the length of socket address structures, if the socket address structure is fixed-length (Figure 3.6), the value returned by the kernel will always be that fixed size: 16 for an IPv4 <code>sockaddr\_in</code> and 28 for an IPv6 <code>sockaddr\_in6</code>, for example. But with a variable-length socket address structure (e.g., a Unix domain <code>sockaddr\_un</code>), the value returned can be less than the maximum size of the structure (as we will see with Figure 15.2).

With network programming, the most common example of a value-result argument is the length of a returned socket address structure. But, we will encounter other value-result arguments in this text:

- The middle three arguments for the select function (Section 6.3)
- The length argument for the getsockopt function (Section 7.2)
- The msg\_namelen and msg\_controllen members of the msghdr structure, when used with recvmsg (Section 14.5)
- The ifc len member of the ifconf structure (Figure 17.2)
- The first of the two length arguments for the sysct1 function (Section 18.4)

[<u>Team LiB</u>]

4 PREVIOUS NEXT ▶


2 of 2 10-12-2022, 12:18

◆ PREVIOUS NEXT ▶

# 3.4 Byte Ordering Functions

Consider a 16-bit integer that is made up of 2 bytes. There are two ways to store the two bytes in memory: with the low-order byte at the starting address, known as *little-endian* byte order, or with the high-order byte at the starting address, known as *big-endian* byte order. We show these two formats in Figure 3.9.

Figure 3.9. Little-endian byte order and big-endian byte order for a 16-bit integer.



In this figure, we show increasing memory addresses going from right to left in the top, and from left to right in the bottom. We also show the most significant bit (MSB) as the leftmost bit of the 16-bit value and the least significant bit (LSB) as the rightmost bit.

The terms "little-endian" and "big-endian" indicate which end of the multibyte value, the little end or the big end, is stored at the starting address of the value.

Unfortunately, there is no standard between these two byte orderings and we encounter systems that use both formats. We refer to the byte ordering used by a given system as the *host byte order*. The program shown in <u>Figure 3.10</u> prints the host byte order.

Figure 3.10 Program to determine host byte order.

intro/byteorder.c

```
1 #include
                "unp.h"
3 main(int argc, char **argv)
4 {
5
       union {
 6
           short
                   s;
                   c[sizeof(short)];
8
       } un;
9
       un.s = 0x0102;
       printf("%s: ", CPU_VENDOR_OS);
10
       if (sizeof(short) == 2) {
           if (un.c[0] == 1 && un.c[1] == 2)
12
               printf("big-endian\n");
13
           else if (un.c[0] == 2 \&\& un.c[1] == 1)
               printf("little-endian\n");
17
               printf("unknown\n");
18
       } else
           printf("sizeof(short) = %d\n", sizeof(short));
```

1 of 3 10-12-2022, 12:18

```
20 exit(0);
```

We store the two-byte value  $0 \times 0102$  in the short integer and then look at the two consecutive bytes, c[0] (the address A in Figure 3.9), to determine the byte order.

The string <code>CPU\_VENDOR\_OS</code> is determined by the GNU <code>autoconf</code> program when the software in this book is configured, and it identifies the CPU type, vendor, and OS release. We show some examples here in the output from this program when run on the various systems in <a href="Figure">Figure</a> 1.16.

```
freebsd4 % byteorder
i386-unknown-freebsd4.8: little-endian
macosx % byteorder
powerpc-apple-darwin6.6: big-endian

freebsd5 % byteorder
sparc64-unknown-freebsd5.1: big-endian

aix % byteorder
powerpc-ibm-aix5.1.0.0: big-endian

hpux % byteorder
hppal.1-hp-hpux11.11: big-endian

linux % byteorder
i586-pc-linux-gnu: little-endian

solaris % byteorder
sparc-sun-solaris2.9: big-endian
```

We have talked about the byte ordering of a 16-bit integer; obviously, the same discussion applies to a 32-bit integer.

There are currently a variety of systems that can change between little-endian and big-endian byte ordering, sometimes at system reset, sometimes at run-time.

We must deal with these byte ordering differences as network programmers because networking protocols must specify a *network byte order*. For example, in a TCP segment, there is a 16-bit port number and a 32-bit IPv4 address. The sending protocol stack and the receiving protocol stack must agree on the order in which the bytes of these multibyte fields will be transmitted. The Internet protocols use big-endian byte ordering for these multibyte integers.

In theory, an implementation could store the fields in a socket address structure in host byte order and then convert to and from the network byte order when moving the fields to and from the protocol headers, saving us from having to worry about this detail. But, both history and the POSIX specification say that certain fields in the socket address structures must be maintained in network byte order. Our concern is therefore converting between host byte order and network byte order. We use the following four functions to convert between these two byte orders.

```
#include <netinet/in.h>
uint16_t htons(uint16_t host16bitvalue);
uint32_t htonl(uint32_t host32bitvalue);

Both return: value in network byte order
uint16_t ntohs(uint16_t net16bitvalue);
uint32_t ntohl(uint32_t net32bitvalue);

Both return: value in host byte order
```

In the names of these functions, h stands for host, n stands for network, s stands for short, and 1 stands for long. The terms "short" and "long" are historical artifacts from the Digital VAX implementation of 4.2BSD. We should instead think of s as a 16-bit value (such as a TCP or UDP port number) and 1 as a 32-bit value (such as an IPv4 address). Indeed, on the 64-bit Digital Alpha, a long integer occupies 64 bits, yet the hton1 and ntoh1 functions operate on 32-bit values.

When using these functions, we do not care about the actual values (big-endian or little-endian) for the host byte order and the network byte order. What we must do is call the appropriate function to convert a given value between the host and network byte order. On those systems that have the same byte ordering as the Internet protocols (big-endian), these four functions are usually defined as null macros.


We will talk more about the byte ordering problem, with respect to the data contained in a network packet as opposed to the fields in the protocol headers, in <u>Section 5.18</u> and <u>Exercise 5.8</u>.

We have not yet defined the term "byte." We use the term to mean an 8-bit quantity since almost all current computer systems use 8-bit bytes. Most Internet standards use the term *octet* instead of byte to mean an 8-bit quantity. This started in the early days of TCP/IP because much of the early work was done on systems such as the DEC-10, which did not use 8-bit bytes.

Another important convention in Internet standards is bit ordering. In many Internet standards, you will see "pictures" of packets that look

2 of 3 10-12-2022, 12:18

similar to the following (this is the first 32 bits of the IPv4 header from RFC 791):



This represents four bytes in the order in which they appear on the wire; the leftmost bit is the most significant. However, the numbering starts with zero assigned to the most significant bit. This is a notation that you should become familiar with to make it easier to read protocol definitions in RFCs.

A common network programming error in the 1980s was to develop code on Sun workstations (big-endian Motorola 68000s) and forget to call any of these four functions. The code worked fine on these workstations, but would not work when ported to little-endian machines (such as VAXes).

[Team LiB] ↑ PREVIOUS NEXT ►

3 of 3 10-12-2022, 12:18

◆ PREVIOUS NEXT ▶

# 3.5 Byte Manipulation Functions

There are two groups of functions that operate on multibyte fields, without interpreting the data, and without assuming that the data is a nullterminated C string. We need these types of functions when dealing with socket address structures because we need to manipulate fields such as IP addresses, which can contain bytes of 0, but are not C character strings. The functions beginning with str (for string), defined by including the <string.h> header, deal with null-terminated C character strings.

The first group of functions, whose names begin with b (for byte), are from 4.2BSD and are still provided by almost any system that supports the socket functions. The second group of functions, whose names begin with mem (for memory), are from the ANSI C standard and are provided with any system that supports an ANSI C library.

We first show the Berkeley-derived functions, although the only one we use in this text is bzero. (We use it because it has only two arguments and is easier to remember than the three-argument memset function, as explained on p. 8.) You may encounter the other two functions, bcopy and bcmp, in existing applications.

```
#include <strings.h>
void bzero(void *dest, size t nbytes);
void bcopy(const void *src, void *dest, size t nbytes);
int bcmp(const void *ptr1, const void *ptr2, size t nbytes);
                                                                                             Returns: 0 if equal, nonzero if unequal
```

This is our first encounter with the ANSI C const qualifier. In the three uses here, it indicates that what is pointed to by the pointer with this qualification, src, ptr1, and ptr2, is not modified by the function. Worded another way, the memory pointed to by the const pointer is read but not modified by the function.

bzero sets the specified number of bytes to 0 in the destination. We often use this function to initialize a socket address structure to 0. bcopy moves the specified number of bytes from the source to the destination. bemp compares two arbitrary byte strings. The return value is zero if the two byte strings are identical; otherwise, it is nonzero.

The following functions are the ANSI C functions:

```
#include <string.h>
void *memset(void *dest, int c, size t len);
void *memcpy(void *dest, const void *src, size t nbytes);
int memcmp(const void *ptr1, const void *ptr2, size t nbytes);
                                                                                  Returns: 0 if equal, <0 or >0 if unequal (see text)
```

memset sets the specified number of bytes to the value c in the destination. memcpy is similar to bcopy, but the order of the two pointer arguments is swapped. bcopy correctly handles overlapping fields, while the behavior of memopy is undefined if the source and destination overlap. The ANSI C memmove function must be used when the fields overlap.

One way to remember the order of the two pointers for memopy is to remember that they are written in the same left-toright order as an assignment statement in C:

```
dest = src;
```

One way to remember the order of the final two arguments to memset is to realize that all of the ANSI C memXXX functions require a length argument, and it is always the final argument.

memcmp compares two arbitrary byte strings and returns 0 if they are identical. If not identical, the return value is either greater than 0 or less than 0, depending on whether the first unequal byte pointed to by ptr1 is greater than or less than the corresponding byte pointed to by ptr2. The comparison is done assuming the two unequal bytes are unsigned chars.

[Team LiB]

◆ PREVIOUS NEXT ▶

1 of 1 10-12-2022, 12:18