


Drop Shot

Weight on the bottom, bait suspended above it, both under your control



What it does	Everything else puts the weight above the bait. This puts it below. The weight anchors on the bottom and the bait hovers a fixed distance above it, where you can shake it in place indefinitely without moving it.
Why it matters	Fish that will not chase will still eat something that hangs in front of them. This is the rig for a tough day in deep clear water.
Components	Cylinder or teardrop weight, size 1 or 1/0 drop-shot hook, small minnow-shaped plastic.
Tag length	12 in for bottom-hugging perch and smallmouth; 24-36 in for fish suspended off a drop.
Line	6-8 lb fluorocarbon on spinning tackle.
Catches	Smallmouth, walleye, perch, crappie, largemouth. On Pine Lake's east wall it is the most reliable summer rig there is.

Build it


1. Tie a **Palomar knot** with the hook, but leave a very long tag end — 2 to 3 ft.
2. Pass that tag end **back down through the hook eye**, from the top. This is the step everyone forgets, and it is what makes the hook stand out from the line at right angles with the point up.
3. Attach the **weight** to the bottom of the tag with a simple overhand loop, or crimp it into the weight's line clip so it pulls free on a snag instead of costing you the rig.
4. Nose-hook the plastic through the very tip so it hangs horizontally and free.

Fish it

Drop straight down	This is primarily a vertical rig. Get over the fish and lower it.
Feel the weight land	Once it is down, take up slack until the line is just tight to the weight, and then stop reeling.
Shake, do not lift	Shake the rod tip. The weight never moves; only the bait quivers. That is the entire presentation, and you can do it in one spot for a minute at a time.
The bite	Often just added weight, or the line moving sideways. Reel down and sweep — no snap, small hook.
Where	Pine spots 3 (the east wall) and 4 (down the sides of the bar), 25-40 ft. North spots 3 and 4 .

When to use it
August on Pine Lake, when the fish are deep, the sun is high and nothing is chasing. It is also the best rig in the guide for fishing a spot you can see on electronics: put it on their nose and leave it there.

Prove the rig



- Bench test

Pull the Palomar, then hold the line vertical: hook point must face up at a right angle; re-thread the tag if it does not.
- Water test

Lower beside the boat and shake slack line: bait quivers while the cylinder stays planted.
- Proof at depth

The line alternates tight/slack without the weight leaving bottom; mark the 12–24 in tag against a ruler.
- If it fails

Hook hangs point-down: tag was passed through the wrong side. Weight hops: add weight or reduce rod movement. Change one variable, repeat the same cast or drop, and keep the first setting that restores the expected proof.

Record the adjustment

Try	Depth / distance	Sink count	Observed action	Fish response	Next single change
1					
2					
3					

Questions before another cast

Did the rig reach the intended depth? What visible line, rod-tip, bottom, or lure response proves that? Did the connection and hook point survive the retrieve? Was a follow, bite, snag, or refusal observed rather than assumed? Name one variable to change and one to hold constant. If the observation cannot answer those questions, repeat the same short controlled cast before changing the setup.

☐ Sketch the cast: surface, cover, target depth, line angle, and where the response occurred

Evidence-based verdict

☐ repeat unchanged

☐ alter one variable

☐ retire or repair the rig

Reason and next prediction

Telos. Lake Country Fishing — Drop Shot. Revised 2026-07-25. Project-created text and diagrams are licensed CC BY 4.0. Incorporated public-domain artwork remains public domain and is credited on the plate it appears with. See LICENSE and CREDITS.md in the source. Nothing here is professional advice; verify current regulations and follow the stated safety procedure.