

Splunk4Admins - Forwarder Management

Cheat Sheet for Lab Commands

Task 1:

Follow the guide for connecting to the show instance via SSH.

Task 2:

cd /opt/splunk-ds/splunk/bin
./splunk status

Splunk version ./splunk version

Splunk Web port:

Splunk management (splunkd) port:

Splunk App Server ports:

Splunk KV store port:

Splunk server name:

./splunk show web-port

./splunk show splunkd-port

./splunk show appserver-ports

./splunk show kvstore-port

./splunk show servername

Default host name: ./splunk show default-hostname

Task 3:

/opt/splunk-ds/splunk/etc/system
ls README
ls default
ls local
more +39 README/server.conf.spec
ls /opt/splunk/etc/deployment-apps
more /opt/splunk/etc/deployment-apps/README

Task 4:

mkdir all_forwarder_outputs
cd all_forwarder_outputs
mkdir metadata
mkdir local
cd metadata
vi local.meta

```
access = read : [ * ], write : [ admin ]
export = system
cd ../local
vi outputs.conf
# BASE SETTINGS
[tcpout]
defaultGroup = primary_indexer
forceTimebasedAutoLB = true
forwardedindex.0.whitelist = (_audit|_introspection|_internal)
[tcpout:primary_indexer]
server = server one:9997
vi limits.conf
# By default a universal or light forwarder is limited to 256kB/s
# Either set a different limit in kB/s, or set the value to zero to
# have no limit.
# Note that a full speed UF can overwhelm a single indexer.
# [thruput]
# maxKBps = 0
```

Note: this file doesn't do anything as everything is commented out, but the notes in the file are valuable to expose to customers and get them thinking about throughput limits.

```
vi app.conf
```

```
[install]
state = enabled

[package]
check_for_updates = false

[ui]
is_visible = false
is_manageable = false
```

Task 5:

cd /opt/splunk-ds/splunk/etc/deployment-apps
mkdir all_deploymentclient
cd all_deploymentclient
mkdir metadata

```
mkdir local
cd metadata
vi local.meta
access = read : [ * ], write : [ admin ]
export = system
vi app.conf
[install]
state = enabled
[package]
check_for_updates = false
[ui]
is_visible = false
is_manageable = false
vi deploymentclient.conf
[deployment-client]
# Set the phoneHome
# 10 minutes
# phoneHomeIntervalInSecs = 600
[target-broker:deploymentServer]
# Change the targetUri
targetUri = https://ds-ip:8089
Task 6:
cd /opt/splunk-ds/splunk/etc/system/local
vi serverclass.conf
[serverClass:all forwarders]
restartSplunkd = true
whitelist.0 = UF1
whitelist.1 = HF1
[serverClass:all_forwarders:app:all_forwarder_outputs]
vi serverclass.conf
[serverClass:all_deployment_clients]
restartSplunkd = true
whitelist.0 = *
```

[serverClass:all_deployment_clients:app:all_deploymentclient]

/opt/splunk/bin/splunk btool serverclass list --debug

Task 7:

```
cd /opt/splunk-ds/splunk/etc/deployment-apps
scp -r -P 2222 all_deploymentclient/
splunk@{IPAddress}:/opt/splunkforwarder/etc/apps
scp -r -P 2222 all_deploymentclient/ splunk@{IPAddress}/opt/splunk/etc/apps
ssh username@{UF1IPAddress}
cd /opt/splunkforwarder/etc/apps/
ls -1
/opt/splunkforwarder/bin/splunk restart
ssh username@{HF1PAddress}
cd /opt/splunk/etc/apps/
ls -1
/opt/splunk/bin/splunk restart
```

Task 8:

```
ssh username@{UF1IPAddress}
cd /opt/splunkforwarder/bin
./splunk enable boot-start
./splunk stop
./splunk clone-prep-clear-config
cd /opt
tar -czvf splunkforwarder_image.tar SplunkForwarder
scp -P 2222 /opt/splunkforwarder_image.tar.gz username@{UF2IPAddress}:/tmp
/opt/splunkforwarder/bin/splunk start
ssh username@{UF2IPAddress}
cd /tmp
ls -1
tar -xzvf splunkforwarder_image.tar.gz -C /opt
ls -1 /opt
/opt/splunkforwarder/bin/splunk start
```

Task 9:

```
ssh username@deployment-server
cd /opt/splunk-ds/splunk/etc/deployment-apps
mkdir all_linux_inputs
```

```
cd all linux inputs
mkdir metadata
mkdir local
cd metadata
vi local.meta
access = read : [ * ], write : [ admin ]
export = system
vi app.conf
[install]
state = enabled
[package]
check_for_updates = false
[ui]
is visible = false
is_manageable = false
vi inputs.conf
[monitor:///var/log/messages]
disabled = false
index = linux
sourcetype = syslog
cd /opt/splunk-ds/splunk/etc/system/local
vi serverclass.conf
[serverClass:all linux]
restartSplunkd = true
whitelist.0 = *
machineTypesFilter=linux-i686, linux-x86_64
[serverClass:all_linux:app:all_linux_inputs]
/opt/splunk-ds/splunk/bin/splunk btool serverclass list --debug
/opt/splunk-ds/splunk/bin/splunk restart
```

Task 10:

cd /opt/splunk-ds/splunk/etc/deployment-apps

```
mkdir all_apache_inputs
cd all_apache_inputs
mkdir metadata
mkdir local
cd metadata
vi local.meta
access = read : [ * ], write : [ admin ]
export = system
cd ../local/
vi app.conf
[install]
state = enabled
[package]
check_for_updates = false
is_v<mark>isible = false</mark>
is_manageable = false
vi inputs.conf
[monitor:///var/log/apache2/access.log]
index = web
sourcetype = access_combined
_TCP_ROUTING = HF1
mkdir /opt/splunk-ds/splunk/etc/deployment-apps/modified_routing_outputs
cd /opt/splunk-ds/splunk/etc/deployment-apps/modified_routing_outputs
mkdir metadata
mkdir local
cd metadata
vi local.meta
access = read : [ * ], write : [ admin ]
export = system
cd ../local/
vi app.conf
[install]
state = enabled
```

```
[package]
check_for_updates = false
[ui]
is_visible = false
is_manageable = false
vi outputs.conf
[tcpout:HF1]
server = <HF_IP_ADDRESS>:9997
mkdir /opt/splunk-ds/splunk/etc/deployment-apps/all_hf_props
cd /opt/splunk-ds/splunk/etc/apps/all_hf_props
mkdir metadata
mkdir local
cd metadata
vi local.meta
access = read : [ * ], write : [ admin ]
export = system
cd ../local/
vi app.conf
[install]
state = enabled
[package]
check_for_updates = false
is visible = false
is_manageable = false
vi props.conf
[access_combined]
TRANSFORMS-set_error = set_apache_error
vi transforms.conf
[set_apache_error]
REGEX = ERROR
FORMAT = sourcetype::apache_error
DEST_KEY = MetaData:Sourcetype
```

cd /opt/splunk/splunk-ds/etc/system/local
vi serverclass.conf

```
[serverClass:all_apache]
restartSplunkd = true
whitelist.0 = UF*
blacklist.0 = HF*
```

```
[serverClass:all_apache:app:all_apache_inputs]
[serverClass:all_apache:app:modified_routing_outputs]
```

```
[serverClass:all_hf]
restartSplunkd = true
whitelist.0 = HF*
blacklist.0 = UF*
```

[serverClass:all_hf:app:all_hf_props]

/opt/splunk/bin/splunk btool serverclass list --debug
/opt/splunk/bin/splunk restart