How to boot Windows and Linux, using uefi net boot and iPXE.

At home, I have an Unraid server, a beast of a machine, with more cores than Indian have arrows. So I added some virtual machines to it, and later on Nvidia graphic card. This makes the VM as fast as a normal PC and allows me to play games on it. This opened the option to use Parsec for remote gaming.

My idea was to have a network bootable live client that would boot a Live CD of Linux and run Parsec client for me to connect to a VM. I also install/reinstall lots of Linux distros for work. But you could also create live LibreELEC for example and boot up TV box from network. There is lots of potential for network bootable installations or live OSes.

Right out of the bat, the Linux idea was not working with Parsec because it supports only old ass Ubuntu 18 which in turn had issues (not supported) build in Intel UHD600 on my "thin" client. So it would not work with h256 codec. On other hand installing win10 and running Parsec from there it works perfectly.

What we need?

What we need to get this work ? You might have heart of PXE server for network booting. And well this is what we are going to use. PXE server is nothing really special, it's not one software 'PXE' its more of a collection of services that work together.

- A server or VM I'm going to create a VM with Ubuntu server, version 20.04 LTS on Unraid. This will be our PXE server. (It does not matter if it's a VM, or server... it has to be connected to your network with fixed IP preferably)
- A DHCP server When we use PXE booting, the NW card will ask your DHCP server for IP and where the TFTP server is. Also, what "ROM" it should load from that TFTP server.
- TFTP server this is basically a crappy ftp server (no, you can't use FTP server) ancient as PXE itself. Think of it as FTP service, that has no user, and it's open to everybody on your network. This will server the first step of the network bod process, the PXE ROM.
- HTTP server We are going to use Apache 2, but you can use virtually anything that is capable to serve files over plain old HTTP. IPXE is cool in a way that it can reach out to a http server and load data from there, so you don't need to host everything over TFTP, which is painfully slow.

 SAMBA server This is for windows, the Windows boot environment don't know how to mount files over HTTP, so SAMBA is our next option.
- ISOs Images of Windows, Linux or what ever you are trying to boot up over a network

Drivers - This is related to Windows, the Windows PE (I will talk more about what it is in windows section) does not have many drivers in it. This can cause that it can't mount SAMBA share with install files because no network card recognized... (happened to me and my thin client, so that was not fun to figure out how to fix it. I will show you in windows section)

My exact setup


▲ Warning

Read this so there is no confusion later on.

Since I'm running this on Unraid, part of the guide will depend on SAMBA server. So I will use the SAMBA already running on Unraid. However, If you're following this guide without Unraid, I have included how to set SAMBA on your PXE boot server directly.

For not Unraid users: install SAMBA on PXE server directly and use its IP in the guide...

I also installed a fancy graph plugin to my McDocs so here is a high-level overview of my setup.



There will be also one Unraid share folder that is mounted inside the VM, but more about that in VM/Server setup.

Unraid VM

Important

Feel free to skipp this part if you install on other hypervisiors or bare metal. Just intsall Ubuntu 20.04 server if you wan't to follow allong command by command.

I do have one Unriad share called isos and in it there is folder pxe-boot. I will map this folder to the VM and everythig will be stored there.

I have created new VM on unraid, with 2CPU and 2G of RAM (you might get away with 1G). Also mapped the isos share to it like this:

Unraid Share: /mnt/user/isos/pxe-boot/ Unraid Mount tag: /pxe-boot

Provide Ubuntu ISO as well into: 0S Install ISO


Boot up and install the OS as usual, enable ssh server during install if you want to use ssh client later on

Network

I'm using VLANs in my netowork, and my VMs are on VLAN30 (IPs in range 10.0.30.x) and my Unriad is in VLAN0 (IPs in range 10.0.0x). They can 'talk' to each other cross VLANs but you should not worry about this much. I'm just explaining it, why there are different IPs ranges. For you just make sure that the IP that you give to your new PXE Ubuntu server is reachable by IPs assigned by your DHCP server.

I'm on purpose not going to install new DHCP server since most of you, and me already have one in network. Either standalone, or most likely part of your router. The configuration regarding PXE and your DHCP solution differs a bit between brands so Google is your friend.

For my Unifi USG 3P router its setup per Network so go to Settings -> Networks click on your network name. Then Advance and scroll down to DHCP Network Boot



- the ROM we will boot (In our case its uefi iPXE, we will add this file to place soon)
- DHCP TFTP Server IP of our PXE server

▲ Importor

I'm going to use UEFI network boot only, this is supported by most modern devices and UniFi in its infinite wisdom did not added option for legacy BIOS boots.

A Warning

Some cheap routers might not have option for PXE / Network boot. In that case you need to deploy your own DHCP server and disable the one on your router. This is way out of scope of this guide though. So ~ Google.com

Software services

Log in as root and update your installation with:

apt update apt upgrade

TFTP server

Our main service. This will server the before mentioned ROM file to the network bootable client

Install:

apt install -y tftpd-hpa

Edit /etc/default/tftpd-hpa to look like this:

TFTP_USERNAME="tftp"
TFTP_DIRECTORY="/pxe-boot"
TFTP_ADDRESS=":69"
TFTP_OPTIONS="--secure"

Regular Server/VM

Create our main folder /pxe-boot Make sure there is enough free space since this folder will house ISOs later on. Put it on separate disk, Ivol or what ever, it's up to you.

Unraid

For Unraid users, I'm going to mount Unriad share ISOs (which have pxe-boot folder in it) to this VM.

#Create directory where to mount the share
mkdir /pxe-boot

#Edit /etc/fstab and add
/pxe-boot /pxe-boot 9p trans=virtio,version=9p2888.L,_netdev,rw 8 8
#Mount the share
mount -a

HTTP server

Use what ever you prefer to server HTTP files from /pxe-boot. I'm going with apache2

Install

apt install -y apache2

Edit file /etc/apache2/sites-available/000-default.conf,remove everything and add this:

*VirtualHoat *:88>
 ServerAdmin some@mail.com
 DocumentRoat /pse-boot
 ErrorLog \${APACHE_LOG_DIB}/error.log
 CustomLog \${APACHE_LOG_DIB}/access.log combined
 /VirtualHoat

*Directory />
 Options *FollowSymLinks *Indexes
 Require all granted
 </Directory>>

Reload Apache and TFTP

systemctl restart tftpd-hpa systemctl restart apache2

Check

Now before we move on, check that the following works

Create test file in /pxe-boot

touch /pxe-boot/test.file

Make sure you can see this file when you go to IP of your PXE server via web browser.

Test TFTP server, ideally from other computer on the network, that you can connect on the PXE server IP and download the <code>test.file.id</code> this test from a Windows 10 machine running Ubuntu Linux subsystem. One thing to note at that is, Windows 10 frewall will block the TFTP, not the initial connection but the download as that happens on random port not the TFTP port: 69. So I disabled the firewall for a minute and did the following.

vladoportos@Odin:-\$ tftp 10.0.30.15
tftp- verbose
Verbose mode on.
tftp- get test.file getting from 10.0.30.15;test.file to test.file [netasci]
tftp- gut test.file
yladoportos@Odin:-\$ ls | grep test.file
tvladoportos@Odin:-\$ ls | grep test.file
vladoportos@Odin:-\$

Samb

We need samba only for windows network installation as far as I know. Because we can boot up to WindowsPE environment, but we need to give it content of the actual windows ISO for installation.

So far I have found the only working option to let the WinPE loader mount samba share as disk and install from that.

Unraid

In this case we export directly the iso share in Unriad. Just set the security in SAMBA for this share to Public so there is no password/user

Regular VM/Server

Install SAMBA

apt install -y samba

Edit /etc/samba/smb.conf and at the bottom add:

[pxe-boot]
comment = Samba on Ubuntu
path = /pxe-boot
read only = yes
browsable = yes

Reload

systemctl restart samba

✓ Note

Later on I will reference this SAMBA share, for Unriad it will be \\18.8.8.2\isos\pxe-boot\... and if you installed it directly on your PXE server than it will be \\<PXE server.IP>\pxe-boot\...

✓ Done

We are done with server setup and services, we can now move on to setting the iPXE ROM in next chapter.

All the services are up, take a break and drink

☑ Liked it ? Buy me a drink :)

Last update: May 26, 2022

Comments









Login
Sort by Best Favorite Favorite Start the discussion...

LOG IN WITH OR SIGN UP WITH DISQUS ?

Name