SoftICE Dynamic Notes

Live object layouts and paint traces

Window Classes (TB80RTM)

TBKMain, TBKClient, TBKChildWindow, TBKReserved_1, SchedulerWndTB80. A lesson click is delivered to TBKClient, not TBKChildWindow. BMSG does not see the 16-bit queue; BPX on the TBKClient proc does.

Polygon Painter Confirmation

TB80BAS segment 0x82 paints a polygon. GDI!POLYGON count is at object+0x30 (word), point array far pointer at object+0x32 (4 bytes each, stored twips). PaintPolygon = FUN_1408_0376. ScaleTwipsToScreen = FUN_1008_01dd (seg 2 offset 0x1DD). With DS:01A6/01A8 = 96, screen = stored/15. Breakpoint fires per polygon; leave it set while scrolling freezes SoftICE.

Arc and Rectangle

Arc painter: TB80BAS segment 0x7B, CALL GDI!ARC. Object far pointer at [BP+04]. Bounding box stored as twips at object+0x0F. Fill color at +0x18. Rectangle painter (seg 0x83) reads bounds at +0x0F and calls GDI!RECTANGLE. Chip bodies are the small rectangles.

Dump Caveats

Early /DUMP captures were SoftICE console logs, not target memory. With expert mode and careful addressing, real page and object dumps were obtained (ASYM_TpID, Page#, property blocks, live point arrays).