Reseller Panel


Complete Setup Guide — from zero to a fully operational reseller panel

This guide walks you through every step, from getting your credentials to onboarding your first reseller and going live. No prior experience needed — every step is explained as if to a 10-year-old.

Table of Contents

1. What This Does
2. Prerequisites
3. Get Your SellAuth Credentials
4. Set Up the Project
5. Configure the .env File
6. Start the Server
7. Access the Admin Panel
8. Add Your First Reseller
9. Onboard a Reseller (What They Get)
10. How Resellers Use the API
11. The Reseller Storefront
12. Referral System
13. Reseller Applications
14. Day-to-Day Operations
15. Security Features
16. Customizing Branding & Colors
17. Troubleshooting
18. Full API Reference

1. What This Does



What it does:

- Pulls your product catalog + stock from your SellAuth shop automatically.
- Each reseller gets a **unique API key**.
- Each reseller has a **custom discount percentage** you set.
- Resellers query your panel and see products at **their discounted prices**.
- Resellers NEVER see your SellAuth directly — they only talk to your panel.
- Resellers get a **storefront** (web dashboard) to browse, order, and track history.
- **Prepaid balance** system — resellers deposit funds, orders deduct automatically.
- **Referral system** — resellers refer others and earn a % commission.
- **Public application form** — new resellers apply, you approve/reject from the admin panel.
- **Security hardening** — hashed API keys, rate limiting, audit logs.

2. Prerequisites

Requirement	How to check	Minimum
Linux server	`uname -a`	Any modern distro (Debian/Ubuntu recommended)
Python	`python3 --version`	3.11 or higher
Docker + Compose	`docker --version`	Optional (for Docker deployment)
Free port		Port 8000 must be free

	`ss -tlnp | grep 8000`	

On your local machine you just need a web browser.

3. Get Your SellAuth Credentials

You need **two values** from your SellAuth dashboard.

3.1 — Get your API Key

1. Go to **https://dash.sellauth.com** and log in.
2. In the left sidebar, click **Account** → **Developers** (or **API**).
3. Copy your API key — it looks like `sa_live_xxxxxxxxxxxxxxx`.

> **Save this key immediately.** You may not be able to see it again. Never share it or put it in a client app — it stays server-side only.

3.2 — Get your Shop ID

1. Click **Shops** in the sidebar, then click your shop.
2. Look at the URL: `https://dash.sellauth.com/shops/12345` — the number is your Shop ID.

4. Set Up the Project

```
cd ~/projects/reseller-panel
python3 -m venv .venv
source .venv/bin/activate
pip install -r requirements.txt
```

Project layout

File / folder	Purpose
`main.py`	FastAPI app entry point
`config.py`	Reads your .env settings

`database.py`	SQLite storage (resellers, orders, balances, referrals)
`security.py`	Rate limiting, security headers, request size limits
`routers/storefront.py`	Reseller-facing web storefront
`routers/admin_ui.py`	Admin web dashboard
`routers/api_webhook.py`	Reseller API (query products/stock)
`routers/api_admin.py`	Admin REST API
`services/sellauth.py`	SellAuth API client
`templates/`	HTML templates (admin + storefront)
`discord_bot.py`	Optional Discord management bot

5. Configure the .env File

```
cp .env.example .env
nano .env
```

Fill in at minimum:

Key	What to put
`SELLAUTH_API_KEY`	Your key from step 3.1
`SELLAUTH_SHOP_ID`	Your shop ID from step 3.2
`ADMIN_PASSWORD`	A strong password (NOT "admin")
`BRAND_NAME`	Your brand, e.g. `DTF MARKET`

> **Do not** put quotes or spaces around the `=` sign.

6. Start the Server

Option A — Direct (testing)

```
source .venv/bin/activate
uvicorn main:app --host 0.0.0.0 --port 8000
```

Option B — Docker (production)

```
docker compose up -d
docker compose logs -f
```

7. Access the Admin Panel

Open `http://YOUR_SERVER_IP:8000` and log in with your `ADMIN_PASSWORD`.

The admin dashboard shows:

- **Active Resellers** — how many you have.
- **Total Products** — pulled from SellAuth.
- **Total Stock** — sum of all stock.

Top navigation: **Dashboard** / **Resellers** / **Stock** / **Orders** / **Applications**.

8. Add Your First Reseller

1. Click **Resellers** → **+ Add Reseller**.
2. Enter name and discount %.
3. Click **Create** — a popup shows the API key **once**.

> **Copy the API key now.** It is shown only once. You can regenerate it (invalidates the old one) but can never view it again — keys are stored hashed.

How discount works: product costs $40 retail, reseller discount 25% → reseller sees $30. The `original_price` is also shown so they know the retail.

9. Onboard a Reseller

Give a new reseller three things:

```
Storefront:  http://YOUR_SERVER_IP:8000/store/login
Your Key:    rs_xxxxxxxxxxxxxxx
Discount:    25% off all products
```

They can log into the storefront with their API key, OR use the raw API (below).

10. How Resellers Use the API

Resellers only need one URL. The API key goes in the path.

```
# Health check (verify the key works)
GET /api/webhook/{api_key}/health

# Get all products with their discounted prices
GET /api/webhook/{api_key}
```

Response includes `price` (discounted) and `original_price` (retail).

Query param	Example	Description
`page`	`?page=2`	Page number (default 1)
`per_page`	`?per_page=100`	Products per page (max 200)
`type`	`?type=service`	Filter by `service` or `file`

11. The Reseller Storefront

Resellers get a full web dashboard at `/store`. After logging in with their API key, they see:

- **Dashboard** — "Welcome back" summary: balance, discount, total orders, referral earnings, recent orders.
- **Products** — browse the catalog at their discounted prices, place orders.
- **Orders** — full order history.
- **Balance** — current balance + transaction history.

- **Referrals** — their referral code, link, and earnings.

Orders deduct from the reseller's prepaid balance. When a reseller places an order, the panel creates a SellAuth checkout link they can send to their customer — SellAuth auto-delivers after payment.

12. Referral System

Every reseller automatically gets a unique **referral code** (e.g. `XK4F9T2Q`).

- Resellers share their link: `http://YOUR_SERVER_IP:8000/store/apply?ref=XK4F9T2Q`
- When a new reseller applies with that code and is approved, they're linked.
- The referrer earns `REFERRAL_COMMISSION_PERCENT` (default 5%) of every order the referred reseller places.
- Commission is credited automatically to the referrer's balance.

13. Reseller Applications

The public form at `/store/apply` collects: email, Discord, website, Discord server, products, and optional referral code.

In the admin panel, **Applications** shows all pending applications:

- **Approve** → enter a name + discount % → creates the reseller automatically (and links any referral).
- **Reject** → marks it rejected.

> The default discount for approved applications is `DEFAULT_APPLICATION_DISCOUNT` (default 30%).

14. Day-to-Day Operations

- **Add balance to a reseller** — Resellers → Edit → "Add Funds".
- **Change a discount** — Resellers → Edit → Discount %.
- **Suspend a reseller** — Resellers → Edit → Status = Inactive.
- **Rotate a key** — Resellers → (old key stops working immediately).
- **View all orders** — Orders tab shows every reseller's orders.

- **Check stock** — Stock tab reflects live SellAuth inventory.

15. Security Features

Feature	What it does
Hashed API keys	Keys stored as SHA-256 hashes — a DB leak never reveals keys
Rate limiting	60 req/min global, 30/min webhook, 5/min login per IP
Brute-force lockout	Admin login locks after 5 failures / 15 min
Security headers	CSP, X-Frame-Options, nosniff, etc.
Request size limit	Rejects bodies over 64 KB
Audit log	Every admin action is logged with IP
Constant-time compare	Password/key checks use hmac.compare_digest

16. Customizing Branding & Colors

The UI ships with the **DTF Market** palette, defined as CSS variables in `templates/store_base.html` and `templates/base.html`.

Variable	Default	Use
`--bg`	`#0b1018`	Page background
`--bg-nav`	`#000000`	Navbar
`--bg-input`	`#0e141e`	Inputs / wells
`--bg-card`	`#121a26`	Cards and panels
`--bg-hover`	`#16202e`	Hover / raised
`--brand-gradient`	`linear-gradient(135deg, #4f7cff, #7c5cff)`	Buy buttons, active tabs
`--accent`	`#7c5cff`	

		Primary accent (purple)
`--accent-light`	`#a78bfa`	Links and details

Status colors: `#22c55e` Undetected · `#fbbf24` Updating · `#3b82f6` Testing · `#ef4444` Risky · `#f97316` Frozen.

Set `BRAND_NAME` in `.env` to change the name shown in the header and login page.

17. Troubleshooting

Problem	Fix
"No products loaded"	Check `SELLAUTH_API_KEY` / `SELLAUTH_SHOP_ID` in .env. Test with curl (step 3).
SellAuth returns 401	Your API key is stale/revoked — regenerate in dash.sellauth.com.
Can't log into admin	Too many attempts → wait 15 min. Or check `ADMIN_PASSWORD`.
Port 8000 in use	Change `PORT` in .env or remap in docker-compose.yml.
Reseller can't log into store	Verify they're using the full API key (starts with `rs_`).
Discord bot not connecting	`DISCORD_BOT_TOKEN` empty → bot disabled (expected). Add token to enable.

18. Full API Reference

Reseller endpoints (`/api/webhook/{api_key}`)

Method	Path	Purpose
GET	`/health`	Verify key + get discount info
GET	`/`	List products with discounted prices

Admin endpoints (`/api/admin/`)

Method	Path	Purpose
GET	`/api/admin/health`	Admin API health
GET	`/api/admin/resellers`	List resellers
POST	`/api/admin/resellers`	Create reseller
PUT	`/api/admin/resellers/{id}`	Update reseller
DELETE	`/api/admin/resellers/{id}`	Delete reseller

Done! Your reseller panel is fully operational.