TCS CORPORATE WEBSITE

Columns Container — Authoring Guide

Role / audience	Authoring — Content authors, content managers, AEM authoring leads
Version	1.0
Status	Draft for review
Owner	Content Lead / AEM Authoring Lead (proposed)
Last validated	2026-11-13
Documents	1
Classification	INTERNAL — classification to be confirmed

Generated from the Markdown sources of docs/handover (branch migrated-page-content-edam); do not edit this PDF.

Contents

Columns Container — Authoring Guide
- Where to see it
- For Content Authors
- Authorable Fields
- Screenshot-Based Authoring Steps
- Variations
- Complete Authoring Example
- Content and Asset Guidelines
- Troubleshooting
- Screenshots
- Known limitations
- Open items
- Change history

Columns Container — Authoring Guide

Attribute	Value
Document ID	AUT-C-columns-container
Audience	Content authors, content managers, AEM authoring leads
Purpose	How to add, fill in and check the Columns Container component
Scope	—
Prerequisites	—
Owner	Content Lead / AEM Authoring Lead (proposed)
Approver	Product Owner (to be confirmed)
Version	1.0
Status	Draft for review
Last updated	13 November 2026
Last validated	13 November 2026
Source files	blocks/columns-container/README.md, blocks/columns-container/_columns-container.json
Related documents	—
Related AEM paths	—

1. Where to see it

- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/columns-container
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/columns-container/alignment-gap-and-breakpoints
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/columns-container/columns-of-blocks
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/columns-container/columns-per-row

2. For Content Authors

1. On the page, choose Add (+) where sections are added and pick **Columns Container**.
2. Inside it, add a **Column Break**, then the components of that column after it; add the next **Column Break**, then its components, and so on. Columns sit side by side in rows of Columns per row (Automatic: up to 4); more Column Breaks start a new row.
3. Select the Columns Container to set its properties: in **Content** the Style, BG Color, Width Type, Background Image and Anchor name; in **Layout** the Columns per row, Gap, Vertical alignment and Side by side from; in **Additional** the block options.
4. Optionally name each Column Break (**Column name**, shown in the editor only) and use its Additional tab for the column's Anchor ID, Hide block and spacing.
5. To reorder columns, move a Column Break together with its components in the content tree.
6. Preview at desktop and mobile widths, publish, and check the published page at the breakpoint you chose.

Allowed in a column: Column Break, Text, Image, Button, Title, Hero, Teaser, Quote, Testimonial, Anchor List, Accordion, Tabs (block), Table, Table List, List, Separator, Embed, Video, Modal, Form Variations, Filter List, Conversation Canvas, Cards and Fragment; not Page Header, Footer and TCS Header.

Minimum required: a Column Break and a component after it (content before the first Column Break is a column of its own). **Recommended:** keep Style Columns Container selected; one Column Break per column; Padding when using a BG Color. **Optional:** everything else.

Tab	Field	Values	Default
Content	Style	Columns Container (keep it selected: it makes the section a Columns Container), Highlight (multiselect)	Columns Container
Content	BG Color	Default, Grey, Dark, Dark green (as the Teaser's): only the background colour of the columns (`bg-grey`, `bg-dark`, `bg-dark-green` on the block); text, links and buttons turn light on Dark and Dark green. Space around the columns: Padding in the Additional tab	Default
Content	Width Type	Full Width, Fixed Width	Full Width
Content	Background Image	An image behind the whole container (as on sections)	—
Content	Image alt text	The background image's alternative text; empty: decorative	—
Content	Anchor name	Section id, e.g. `our-offices` (link with `#our-offices`, Anchor List)	—
Layout	Columns per row	Automatic (as many as there are Column Breaks, at most 4), 1, 2, 3, 4; more Column Breaks start a new row (6 at 3 per row: 2 rows of 3); the columns are of equal width	Automatic
Layout	Gap	None, Small, Medium, Large	Medium
Layout	Vertical alignment	Top, Middle, Bottom, Stretch (equal heights)	Top
Layout	Side by side from	Tablet (600px), Desktop (900px), Large desktop (1200px); stacked below	Desktop
Additional	Anchor ID, Hide block, Animation Type, Motion Speed, Animation Trigger, Padding / Margin	As on blocks; Animation Type moves the columns in one after another	—

In Universal Editor edit mode each column is outlined and labelled with its name, so it can be selected; an empty column says what to add.

3. Authorable Fields

Columns Container (`columns-container`)

Model `columns-container`; template name "Columns Container" (the block class AEM renders); children: `column-break`, `text`, `image`, `button-block`, `title`, `hero`, `teaser`, `image-collage`, `quote`, `media-contacts`, `testimonial`, `anchor-list`, `accordion`, `tabs-block`, `table`, `table-list`, `list`, `separator`, `embed`, `video`, `modal`, `form-variations`, `filter-list`, `conversation-canvas`, `cards`, `fragment`.

Stored on a new component (definition template): `style` = `"columns-container-section"`, `columnsGap` = `"medium"`, `columnsAlign` = `"top"`, `columnsFrom` = `"desktop"`, `columnsPerRow` = `"auto"`.

Content tab — Columns Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Style	`style`	multiselect	No	`columns-container-section`	Columns Container (`columns-container-section`), Highlight (`highlight`)	Keep Columns Container selected: it makes the section a Columns Container. Add Highlight for the highlight background, as on sections.	columns-container-section
BG Color	`containerBgColor`	select	No	""	Default (""), Grey (`bg-grey`), Dark (`bg-dark`), Dark green (`bg-dark-green`), Navy (`bg-navy`)	The background colour of the columns, only the colour (text and buttons turn light on Dark and Dark green); set the space around them with the Padding fields of the Additional tab.	bg-dark-green
Width Type	`sectionWidth`	select	No	`full-width`	Full Width (`full-width`), Fixed Width (`fixed-width`)	—	—
Background Image	`backgroundImage`	reference	No	—	—	—	/content/dam/tcs-corp/dummy-pages/images/smart-home.jpg
Image alt text	`backgroundImageAlt`	text	No	—	—	Describe the image for screen readers. Leave empty if the image is decorative. Delivered with `backgroundImage` (field collapse).	—
Anchor name	`anchorName`	text	No	—	regExp: ^#?[a-z0-9][a-z0-9-]*$; customErrorMsg: Lower-case letters, digits and hyphens, e.g. our-offices.	Lets Anchor List links and #links jump to this section, e.g. our-offices (lowercase, no spaces).	our-offices

Layout tab — Columns Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Columns per row	`columnsPerRow`	select	No	`auto`	Automatic (`auto`), 1 (1), 2 (2), 3 (3), 4 (4)	How many columns sit side by side in a row, all of equal width; more Column Breaks start a new row (e.g. 6 Column Breaks at 3 per row: 2 rows of 3). Automatic: as many as there are Column Breaks, at most 4. Add a Column Break, then the components of the column after it.	2
Gap	`columnsGap`	select	No	`medium`	None (`none`), Small (`small`), Medium (`medium`), Large (`large`)	The space between the columns (and between them when stacked).	large
Vertical alignment	`columnsAlign`	select	No	`top`	Top (`top`), Middle (`middle`), Bottom (`bottom`), Stretch (equal heights) (`stretch`)	How columns of different heights line up side by side.	middle
Side by side from	`columnsFrom`	select	No	`desktop`	Tablet (600px) (`tablet`), Desktop (900px) (`desktop`), Large desktop (1200px) (`large`)	Below this width the columns are stacked, one under the other.	tablet

Additional tab — Columns Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	containerAnchor	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	A unique ID of the block on the page, starting with anchor-, e.g. anchor-our-services; link to it with #anchor-our-services.	—
Hide block	containerHide	boolean	No	false	on / off	Hides the whole block on the page until it is turned off (shown faded in the editor).	—
Animation Type	containerAnimation	select	No	""	None (""), Fade in (motion-fade-in), Fade up (motion-fade-up), Fade down (motion-fade-down), Fade left (motion-fade-left), Fade right (motion-fade-right), Slide up (motion-slide-up), Slide down (motion-slide-down), Slide left (motion-slide-left), Slide right (motion-slide-right), Scale in (motion-scale-in)	How the block's content appears; repeated items (cards, list items, accordion items, columns) appear one after another. None: shown as is. Not played in the editor or when the visitor prefers reduced motion.	motion-fade-up
Motion Speed	containerAnimationSpeed	select	No	""	Medium (""), Fast (motion-fast), Slow (motion-slow)	How fast the animation runs: 0.3, 0.6 or 0.9 seconds. Shown when containerAnimation is set and containerAnimation is not empty.	motion-slow
Animation Trigger	containerAnimationTrigger	select	No	""	On Scroll / Viewport Entry (""), On Page Load (motion-on-load)	When the block's animations run. On Scroll: when the block comes into view (at once if it is in view when the page opens). On Page Load: as soon as the block is ready, wherever it is on the page. Shown when containerAnimation is set and containerAnimation is not empty.	—
Padding left	containerPaddingLeft	select	No	""	Default (""), 0 (none) (pl-0), 0.25rem (space-100) (pl-100), 0.5rem (space-200) (pl-200), 0.75rem (space-300) (pl-300), 1rem (space-400) (pl-400), 1.25rem (space-500) (pl-500), 1.5rem (space-600) (pl-600), 2rem (space-800) (pl-800), 2.5rem (space-1000) (pl-1000), 3rem (space-1200) (pl-1200), 4rem (space-1600) (pl-1600), 5rem (space-2000) (pl-2000), 6rem (space-2400) (pl-2400), 7.5rem (space-3000) (pl-3000)	—	pl-1000
Padding right	containerPaddingRight	select	No	""	Default (""), 0 (none) (pr-0), 0.25rem (space-100) (pr-100), 0.5rem (space-200) (pr-200), 0.75rem (space-300) (pr-300), 1rem (space-400) (pr-400), 1.25rem (space-500) (pr-500), 1.5rem (space-600) (pr-600), 2rem (space-800) (pr-800), 2.5rem (space-1000) (pr-1000), 3rem (space-1200) (pr-1200), 4rem (space-1600) (pr-1600), 5rem (space-2000) (pr-2000), 6rem (space-2400) (pr-2400), 7.5rem (space-3000) (pr-3000)	—	pr-1000
Padding top	containerPaddingTop	select	No	""	Default (""), 0 (none) (pt-0), 0.25rem (space-100) (pt-100), 0.5rem (space-200) (pt-200), 0.75rem (space-300) (pt-300), 1rem (space-400) (pt-400), 1.25rem (space-500) (pt-500), 1.5rem (space-600) (pt-600), 2rem (space-800) (pt-800), 2.5rem (space-1000) (pt-1000), 3rem (space-1200) (pt-1200), 4rem (space-1600) (pt-1600), 5rem (space-2000) (pt-2000), 6rem (space-2400) (pt-2400), 7.5rem (space-3000) (pt-3000)	—	pt-1000

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Padding bottom	containerPaddingBottom	select	No	""	Default (""), 0 (none) (pb-0), 0.25rem (space-100) (pb-100), 0.5rem (space-200) (pb-200), 0.75rem (space-300) (pb-300), 1rem (space-400) (pb-400), 1.25rem (space-500) (pb-500), 1.5rem (space-600) (pb-600), 2rem (space-800) (pb-800), 2.5rem (space-1000) (pb-1000), 3rem (space-1200) (pb-1200), 4rem (space-1600) (pb-1600), 5rem (space-2000) (pb-2000), 6rem (space-2400) (pb-2400), 7.5rem (space-3000) (pb-3000)	—	pb-1000
Margin left	containerMarginLeft	select	No	""	Default (""), 0 (none) (ml-0), 0.25rem (space-100) (ml-100), 0.5rem (space-200) (ml-200), 0.75rem (space-300) (ml-300), 1rem (space-400) (ml-400), 1.25rem (space-500) (ml-500), 1.5rem (space-600) (ml-600), 2rem (space-800) (ml-800), 2.5rem (space-1000) (ml-1000), 3rem (space-1200) (ml-1200), 4rem (space-1600) (ml-1600), 5rem (space-2000) (ml-2000), 6rem (space-2400) (ml-2400), 7.5rem (space-3000) (ml-3000)	—	—
Margin right	containerMarginRight	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	—	—
Margin top	containerMarginTop	select	No	""	Default (""), 0 (none) (mt-0), 0.25rem (space-100) (mt-100), 0.5rem (space-200) (mt-200), 0.75rem (space-300) (mt-300), 1rem (space-400) (mt-400), 1.25rem (space-500) (mt-500), 1.5rem (space-600) (mt-600), 2rem (space-800) (mt-800), 2.5rem (space-1000) (mt-1000), 3rem (space-1200) (mt-1200), 4rem (space-1600) (mt-1600), 5rem (space-2000) (mt-2000), 6rem (space-2400) (mt-2400), 7.5rem (space-3000) (mt-3000)	—	—
Margin bottom	containerMarginBottom	select	No	""	Default (""), 0 (none) (mb-0), 0.25rem (space-100) (mb-100), 0.5rem (space-200) (mb-200), 0.75rem (space-300) (mb-300), 1rem (space-400) (mb-400), 1.25rem (space-500) (mb-500), 1.5rem (space-600) (mb-600), 2rem (space-800) (mb-800), 2.5rem (space-1000) (mb-1000), 3rem (space-1200) (mb-1200), 4rem (space-1600) (mb-1600), 5rem (space-2000) (mb-2000), 6rem (space-2400) (mb-2400), 7.5rem (space-3000) (mb-3000)	—	—

Notes on the fields:

- **Style** (`style`, multiselect): `columns-container-section` makes the section a Columns Container. A section that has the container's Layout values (`data-columnsperrow`, `data-columnsgap`, `data-columnsalign`, `data-columnsfrom`) stays one even if an author removes that Style. Highlight adds the section's grey highlight band (`main .section.highlight` in `styles/styles.css`); Sections no longer offer Highlight (handover 2.33), the Columns Container still does.
- **BG Color** (`containerBgColor`): a class on the block, only the background colour (no padding). On Dark and Dark green the theme contract of `styles/styles.css` turns text, links (underlined in running text), focus and buttons light (Primary white); a Teaser or Columns Container with BG Color Grey inside sets them back. Contrast is the tokens'.
- **Width Type, Background Image, Image alt text, Anchor name**: the Section's fields with the same names, applied by `decorateSectionsWithOptions` as on any section (the Image alt text is delivered

with the image, field collapse). A Background Image is behind the whole section; its alt text is read by screen readers unless empty (decorative).

- **Columns per row** (`columnsPerRow`): class `per-row-1` to `per-row-4`; Automatic (`per-row-auto`) means as many columns as Column Breaks, at most 4. The block gets `columns-container-{1-4}`.
- **Gap** (`columnsGap`): `gap-none` (0), `gap-small` (`--space-400`), Medium (the default, `--space-800`), `gap-large` (`--space-1600`); the same gap separates stacked columns.
- **Vertical alignment** (`columnsAlign`): `align-middle`, `align-bottom`, `align-stretch`; Top is the default.
- **Side by side from** (`columnsFrom`): `from-tablet` (600px), Desktop (900px, the default), `from-large` (1200px).
- **Legacy mapping:** the former **Column widths** option (`columnsLayout`) was removed; values authored before are ignored and the columns are of equal width. Column Breaks authored when the item was named "Column" (rendered as class `column`) are read as Column Breaks.
- **Additional tab:** see AGENTS.md "Additional tab". The container is a section, whose `classes_*` fields AEM doesn't deliver, so its fields are `container*` (`containerAnchor`, `containerHide`, `containerAnimation`, `containerAnimationSpeed`, `containerAnimationTrigger`, `containerPadding*`, `containerMargin*`), turned into classes of the synthetic block by `applySectionBlockOptions`. Hide block hides the whole section on the page. Animation Type animates the columns one after another (`decorators/motion-decorator.js`, target `.columns-container-column`, staggered).
- **Data layer:** the block is a component `tcs-corp/components/columns-container`; the blocks in its columns are its children (see below).

4. Screenshot-Based Authoring Steps

Authoring Step 1: Add the Columns Container

```
[Screenshot Placeholder]

File name:
columns-container-authoring-step-1.png

Purpose:
The page's Add (+) menu with Columns Container, and the empty container's hint in edit mode.

Annotations:
A = Add (+) on the page
B = Columns Container in the list
C = Empty hint "Add a Column Break, then the components of the column after it."
```

Values to Enter

Callout	Field	Value	Reason	Expected result
B	Add (+)	Columns Container	Added where sections are added	An empty container with the hint
—	Style	Columns Container	Keep it: it makes the section a container	Section class `columns-container-section`

Author action: add the container. Expected preview: the hint (edit mode only). Published: nothing until it has content. Business rule: it is a section; it can't be placed inside another section. Common mistake: adding a Section and expecting columns; resolution: use the Columns Container.

Authoring Step 2: Add the columns

```
[Screenshot Placeholder]

File name:
columns-container-authoring-step-2.png

Purpose:
```

```
The content tree with two Column Breaks, each followed by its components, and the two outlined columns
in the canvas.

Annotations:
A = First Column Break and its components
B = Second Column Break and its components
C = Column labels in the canvas
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Column name	Grey Teaser	Tells the columns apart in the editor	Label "Grey Teaser" (edit mode only)
A	Components after it	A Teaser	The first column's content	Teaser in column 1
B	Column name	Contact details	—	Label "Contact details"
B	Components after it	Title, Text	The second column's content	Shown in column 2

Author action: add Column Break, its components, the next Column Break, its components. Expected preview: two outlined columns. Published: two columns from 900px. Business rule: a component belongs to the Column Break above it; content before the first Column Break forms its own first column. Common mistake: components added before the first Column Break; resolution: move them after it.

Authoring Step 3: Set the layout

```
[Screenshot Placeholder]

File name:
columns-container-authoring-step-3.png

Purpose:
The Layout tab with Columns per row 2, Gap Large, Vertical alignment Middle, Side by side from Tablet
(600px).

Annotations:
A = Columns per row
B = Gap
C = Vertical alignment
D = Side by side from
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Columns per row	2	Two columns per row	`per-row-2`, `columns-container-2`
B	Gap	Large	More space between the columns	`gap-large` (`--space-1600`)
C	Vertical alignment	Middle	Centre columns of different heights	`align-middle`
D	Side by side from	Tablet (600px)	Side by side on tablets too	`from-tablet`

Author action: choose the layout. Expected preview: the layout at the editor's canvas width. Published: stacked below 600px, side by side from 600px. Common mistake: judging the breakpoint in a narrow editor canvas; resolution: preview at the target widths.

Authoring Step 4: Background colour and spacing

```
[Screenshot Placeholder]

File name:
```

```
columns-container-authoring-step-4.png

Purpose:
BG Color Dark green in the Content tab and Padding top / bottom / left / right 2.5rem (space-1000) in
the Additional tab.

Annotations:
A = BG Color
B = Padding fields
C = Result with light text
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	BG Color	Dark green	Brand band	`bg-dark-green`; light text and buttons
B	Padding top / bottom / left / right	2.5rem (space-1000)	BG Color adds no space	`pt-1000`, `pb-1000`, `pl-1000`, `pr-1000`
—	Animation Type / Motion Speed	Fade up / Slow	Columns appear one after another	Played on scroll on the page, not in the editor

Author action: choose the colour, then the padding. Expected preview: coloured columns with space inside. Published: the same; the animation plays when the block comes into view (not for reduced motion). Common mistake: expecting padding from BG Color; resolution: set the Padding fields.

5. Variations

Columns per row

Automatic (as many as Column Breaks, at most 4), or 1 to 4. More Column Breaks than per row start new rows of the same column width. **Rendering:** class `columns-container-{n}` sets `--columns-container-count`; the grid is `repeat(n, minmax(0, 1fr))` from the breakpoint. Below it, one column.

Gap

None, Small, Medium (default), Large: the `--columns-container-gap` variable, used between columns and between stacked columns.

Vertical alignment

Top (default), Middle, Bottom, Stretch (equal heights): `align-items` of the grid; visible only side by side.

Side by side from

Tablet (600px), Desktop (900px, default), Large desktop (1200px). Below the chosen width the columns are stacked in their order.

```
[Screenshot Placeholder]

File name:
columns-container-from-large-desktop.png

Purpose:
Side by side from Large desktop (1200px) at 1024px: still stacked.

Annotations:
A = Stacked columns at 1024px
```

BG Color

Default, Grey, Dark, Dark green: only the colour; on Dark and Dark green the theme contract applies (light text, links, focus, buttons). Use the Additional tab's Padding for space inside the colour.

Width Type and Background Image

The Section options: Fixed Width caps the section at the content width; a Background Image sits behind the whole section.

Columns in a Tabs Container tab

A section can't hold a section, so inside a Tabs Container a tab's own Column Breaks make the columns: add a Column Break after the Tab, then that column's components, then the next Column Break. The Tab's **Columns per row** (Automatic, 1-4) sets the columns per row; content before the first Column Break (e.g. a heading) stays above the columns. `blocks/tabs/tabs.js` (`columnsOf`) builds a Columns Container block in the tab's panel, so the layout, CSS and editor labels are the same; Gap, Vertical alignment and Side by side from keep their defaults (Medium, Top, Desktop) there.

Accessibility (all variations): the reading order is the content order (columns are not reordered). **Data layer:** unchanged by the variation. **Personalization / fallback:** none.

6. Complete Authoring Example

Scenario: an "Our offices" band on a contact page: a dark green background, a heading and address text on the left, a Teaser with a call to action on the right, side by side from tablet.

Field	Example value	Guidance
Style	Columns Container	Keep selected
BG Color	Dark green	Use the theme's light text
Anchor name	our-offices	Links `#our-offices` jump to the section
Columns per row	2	Two columns
Gap	Large	—
Vertical alignment	Middle	—
Side by side from	Tablet (600px)	—
Padding (all sides)	2.5rem (space-1000)	Space inside the colour
Animation Type / Motion Speed	Fade up / Slow	Optional
Column Break 1 / content	Contact details / Title "Our offices", Text with the address	—
Column Break 2 / content	Grey Teaser / a Teaser with BG Color Grey and a Button	The Grey Teaser gets dark text back

Steps: Authoring Steps 1 to 4. Expected output: two columns on dark green, stacked below 600px. Accessibility: headings in order; buttons and links readable on the dark background. Analytics: the container is a `columns-container` component, the Teaser its child; clicks are the Teaser's. Personalization fallback: none.

Pre-publish checklist: Style Columns Container kept; every column starts with a Column Break; padding set with a BG Color; images have alt text; checked at 390px, 768px and 1440px.

7. Content and Asset Guidelines

- **Columns:** up to four per row (at most 4 in Automatic; 1–4 when chosen); more Column Breaks make more rows. No verified limit on the number of rows was identified.

- **Column content:** start a column with a heading when it is a topic of its own; keep the columns' content of similar length if Vertical alignment Stretch isn't used.
- **Column names:** short editor labels (not shown on the page).
- **Background image:** an image from the DAM; alt text only if it carries meaning, else leave it empty (decorative). The section background is built as a responsive picture (2000px wide from 600px, 750px below).
- **Images in columns:** follow their component; blocks fill their column's width.
- **CTAs and links:** on Dark and Dark green, use the Button blocks; the theme inverts them.
- **Tags and metadata:** not used.
- **Missing content:** an empty column shows nothing on the page (a hint in edit mode); a container without content renders nothing.

8. Troubleshooting

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
Content shown as a plain section	Not a Columns Container (Style removed and no Layout values)	Inspect the section for `columns-container-section`	Re-select Style Columns Container	Columns appear
Everything in one column	No Column Breaks	Check the content tree	Add a Column Break per column	Columns appear
An unexpected first column	Content before the first Column Break	Check the tree order	Move it after a Column Break	Expected columns
Columns stacked on tablet	Side by side from Desktop (default)	Check the Layout tab; inspect for `from-*`	Choose Tablet (600px)	Side by side at 600px
No space inside the colour	BG Color adds no padding	Check the Additional tab	Set Padding	Space inside
Padding / Hide / Animation without effect	Fields not delivered (content authored before the `container*` fields)	Inspect the section's `data-container*` attributes	Re-enter the values in the Additional tab	Classes on the block
Column Break option change not visible in the editor	Applied when the section is rendered again (R-C-7)	Reload	Reload	Applied

Evidence to collect (no secrets): page URL, viewport width, the section's classes and `data-*` attributes, the block's classes, console errors.

9. Screenshots




Figure: Columns Container as published (block library) — desktop 1440 × 900 (/design-block-master/en/block-library/columns-container/alignment-gap-and-breakpoints, captured 2026-11-08).




Figure: Columns Container as published (block library) — mobile 375 × 812 (/design-block-master/en/block-library/columns-container/alignment-gap-and-breakpoints, captured 2026-11-08).

> **Screenshot required**

> - Required screen: Columns Container dialog in Universal Editor (every tab, including Additional)
> - Required role/access: AEM Sites author with Universal Editor (content author)
> - Required navigation steps: AEM Sites console > /content/tcs-corp/language-masters/en > open a page in Universal Editor
> - Reason unavailable: No AEM author access in the documentation program (access blocker AB-01)
> - Owner: Content Lead / AEM Authoring Lead (proposed)
> - Target completion date: To be confirmed

10. Known limitations

- Universal Editor screenshots are placeholders: no author access in this program.

11. Open items

- None.

12. Change history

Version	Date	Author	Change
1.0	13 November 2026	Delivery team (documentation program)	First version of the role-specific documentation (master documentation prompt), generated from the repository and the published reference pages