TCS CORPORATE WEBSITE

Table — Authoring Guide

Role / audience	Authoring — Content authors, content managers, AEM authoring leads
Version	1.0
Status	Draft for review
Owner	Content Lead / AEM Authoring Lead (proposed)
Last validated	2026-11-13
Documents	1
Classification	INTERNAL — classification to be confirmed

Generated from the Markdown sources of docs/handover (branch migrated-page-content-edam); do not edit this PDF.

Contents

Table — Authoring Guide
- Where to see it
- For Content Authors
- Authorable Fields
- Screenshot-Based Authoring Steps
- Variations
- Complete Authoring Example
- Content and Asset Guidelines
- Troubleshooting
- Screenshots
- Known limitations
- Open items
- Change history

Table — Authoring Guide

Attribute	Value
Document ID	AUT-C-table
Audience	Content authors, content managers, AEM authoring leads
Purpose	How to add, fill in and check the Table component
Scope	—
Prerequisites	—
Owner	Content Lead / AEM Authoring Lead (proposed)
Approver	Product Owner (to be confirmed)
Version	1.0
Status	Draft for review
Last updated	13 November 2026
Last validated	13 November 2026
Source files	blocks/table/README.md, blocks/table/_table.json
Related documents	—
Related AEM paths	—

1. Where to see it

- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/table
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/table/table

2. For Content Authors

1. **Add the block.** Select a Section, a Columns Container column or a Tabs Container tab, choose Add (+) and pick **Table**.
2. **Open its properties.** Select the Table; the panel has the **Content** and **Additional** tabs.
3. **Choose Columns first.** Set **Columns** (1 to 5); it decides which Row the Add (+) of the Table offers. Changing it later affects only Rows added afterwards.
4. **Choose Options.** In **Options** select Striped and / or Bordered (Border group), No Header and / or First Column Header (Header group), or nothing.
5. **Add the Rows.** Select the Table, choose Add (+) and pick **Row**; fill Column 1 to Column N. Add the header Row first (unless No Header); reorder Rows by dragging them in the content tree.
6. **Name the table.** Put a heading (Title) as the last element right before the Table in the same section.
7. **Preview** at desktop, tablet and mobile widths; check that only the table scrolls on mobile.
8. **Publish** the page.
9. **Validate the published output:** header row, row headers and options look as intended; a screen reader announces the table with the heading's name.

Minimum required: at least one Row (an empty Table renders nothing visible). **Recommended:** a header Row, a heading right before the table, the right Columns before adding Rows. **Optional:** Options, the Additional tab.

3. Authorable Fields

Table (`table`)

Model `table`; template name "Table" (the block class AEM renders); children: `table-row`.

Content tab — Table

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Options	`classes`	multiselect	No	""	Border (`undefined`), Header (`undefined`)	—	—
Columns	`filter`	select	No	`table`	1 Column (`table`), 2 Columns (`table-2-columns`), 3 Columns (`table-3-columns`), 4 Columns (`table-4-columns`), 5 Columns (`table-5-columns`), 6 Columns (`table-6-columns`), 7 Columns (`table-7-columns`), 8 Columns (`table-8-columns`), 9 Columns (`table-9-columns`)	—	table-4-columns

Additional tab — Table

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	`classes_anchor`	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	A unique ID of the block on the page, starting with anchor-, e.g. anchor-our-services; link to it with #anchor-our-services. Delivered as a block class.	—
Hide block	`classes_hideblock`	boolean	No	false	on / off	Hides the whole block on the page until it is turned off (shown faded in the editor). Delivered as a block class.	—
Animation Type	`classes_animation`	select	No	""	None (""), Fade in (`motion-fade-in`), Fade up (`motion-fade-up`), Fade down (`motion-fade-down`), Fade left (`motion-fade-left`), Fade right (`motion-fade-right`), Slide up (`motion-slide-up`), Slide down (`motion-slide-down`), Slide left (`motion-slide-left`), Slide right (`motion-slide-right`), Scale in (`motion-scale-in`)	How the block's content appears; repeated items (cards, list items, accordion items, columns) appear one after another. None: shown as is. Not played in the editor or when the visitor prefers reduced motion. Delivered as a block class.	—
Motion Speed	`classes_animationspeed`	select	No	""	Medium (""), Fast (`motion-fast`), Slow (`motion-slow`)	How fast the animation runs: 0.3, 0.6 or 0.9 seconds. Shown when `classes_animation` is set and `classes_animation` is not empty. Delivered as a block class.	—
Animation Trigger	`classes_animationtrigger`	select	No	""	On Scroll / Viewport Entry (""), On Page Load (`motion-on-load`)	When the block's animations run. On Scroll: when the block comes into view (at once if it is in view when the page opens). On Page Load: as soon as the block is ready, wherever it is on the page. Shown when `classes_animation` is set and `classes_animation` is not empty. Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Padding left	classes_paddingleft	select	No	""	Default (""), 0 (none) (pl-0), 0.25rem (space-100) (pl-100), 0.5rem (space-200) (pl-200), 0.75rem (space-300) (pl-300), 1rem (space-400) (pl-400), 1.25rem (space-500) (pl-500), 1.5rem (space-600) (pl-600), 2rem (space-800) (pl-800), 2.5rem (space-1000) (pl-1000), 3rem (space-1200) (pl-1200), 4rem (space-1600) (pl-1600), 5rem (space-2000) (pl-2000), 6rem (space-2400) (pl-2400), 7.5rem (space-3000) (pl-3000)	Delivered as a block class.	—
Padding right	classes_paddingright	select	No	""	Default (""), 0 (none) (pr-0), 0.25rem (space-100) (pr-100), 0.5rem (space-200) (pr-200), 0.75rem (space-300) (pr-300), 1rem (space-400) (pr-400), 1.25rem (space-500) (pr-500), 1.5rem (space-600) (pr-600), 2rem (space-800) (pr-800), 2.5rem (space-1000) (pr-1000), 3rem (space-1200) (pr-1200), 4rem (space-1600) (pr-1600), 5rem (space-2000) (pr-2000), 6rem (space-2400) (pr-2400), 7.5rem (space-3000) (pr-3000)	Delivered as a block class.	—
Padding top	classes_paddingtop	select	No	""	Default (""), 0 (none) (pt-0), 0.25rem (space-100) (pt-100), 0.5rem (space-200) (pt-200), 0.75rem (space-300) (pt-300), 1rem (space-400) (pt-400), 1.25rem (space-500) (pt-500), 1.5rem (space-600) (pt-600), 2rem (space-800) (pt-800), 2.5rem (space-1000) (pt-1000), 3rem (space-1200) (pt-1200), 4rem (space-1600) (pt-1600), 5rem (space-2000) (pt-2000), 6rem (space-2400) (pt-2400), 7.5rem (space-3000) (pt-3000)	Delivered as a block class.	—
Padding bottom	classes_paddingbottom	select	No	""	Default (""), 0 (none) (pb-0), 0.25rem (space-100) (pb-100), 0.5rem (space-200) (pb-200), 0.75rem (space-300) (pb-300), 1rem (space-400) (pb-400), 1.25rem (space-500) (pb-500), 1.5rem (space-600) (pb-600), 2rem (space-800) (pb-800), 2.5rem (space-1000) (pb-1000), 3rem (space-1200) (pb-1200), 4rem (space-1600) (pb-1600), 5rem (space-2000) (pb-2000), 6rem (space-2400) (pb-2400), 7.5rem (space-3000) (pb-3000)	Delivered as a block class.	—
Margin left	classes_marginleft	select	No	""	Default (""), 0 (none) (ml-0), 0.25rem (space-100) (ml-100), 0.5rem (space-200) (ml-200), 0.75rem (space-300) (ml-300), 1rem (space-400) (ml-400), 1.25rem (space-500) (ml-500), 1.5rem (space-600) (ml-600), 2rem (space-800) (ml-800), 2.5rem (space-1000) (ml-1000), 3rem (space-1200) (ml-1200), 4rem (space-1600) (ml-1600), 5rem (space-2000) (ml-2000), 6rem (space-2400) (ml-2400), 7.5rem (space-3000) (ml-3000)	Delivered as a block class.	—
Margin right	classes_marginright	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Margin top	`classes_margintop`	select	No	""	Default (""), 0 (none) (`mt-0`), 0.25rem (space-100) (`mt-100`), 0.5rem (space-200) (`mt-200`), 0.75rem (space-300) (`mt-300`), 1rem (space-400) (`mt-400`), 1.25rem (space-500) (`mt-500`), 1.5rem (space-600) (`mt-600`), 2rem (space-800) (`mt-800`), 2.5rem (space-1000) (`mt-1000`), 3rem (space-1200) (`mt-1200`), 4rem (space-1600) (`mt-1600`), 5rem (space-2000) (`mt-2000`), 6rem (space-2400) (`mt-2400`), 7.5rem (space-3000) (`mt-3000`)	Delivered as a block class.	—
Margin bottom	`classes_marginbottom`	select	No	""	Default (""), 0 (none) (`mb-0`), 0.25rem (space-100) (`mb-100`), 0.5rem (space-200) (`mb-200`), 0.75rem (space-300) (`mb-300`), 1rem (space-400) (`mb-400`), 1.25rem (space-500) (`mb-500`), 1.5rem (space-600) (`mb-600`), 2rem (space-800) (`mb-800`), 2.5rem (space-1000) (`mb-1000`), 3rem (space-1200) (`mb-1200`), 4rem (space-1600) (`mb-1600`), 5rem (space-2000) (`mb-2000`), 6rem (space-2400) (`mb-2400`), 7.5rem (space-3000) (`mb-3000`)	Delivered as a block class.	—

Row (`table-row`)

Model `table-row`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—

Row (`table-col-2`)

Model `table-col-2`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—

Row (`table-col-3`)

Model `table-col-3`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—

Row (`table-col-4`)

Model `table-col-4`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—

Row (`table-col-5`)

Model `table-col-5`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—
Column 5	`column5text`	richtext	No	—	—	—	—

Row (`table-col-6`)

Model `table-col-6`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—
Column 5	`column5text`	richtext	No	—	—	—	—
Column 6	`column6text`	richtext	No	—	—	—	—

Row (`table-col-7`)

Model `table-col-7`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—
Column 5	`column5text`	richtext	No	—	—	—	—
Column 6	`column6text`	richtext	No	—	—	—	—
Column 7	`column7text`	richtext	No	—	—	—	—

Row (`table-col-8`)

Model `table-col-8`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—
Column 5	`column5text`	richtext	No	—	—	—	—
Column 6	`column6text`	richtext	No	—	—	—	—
Column 7	`column7text`	richtext	No	—	—	—	—
Column 8	`column8text`	richtext	No	—	—	—	—

Row (`table-col-9`)

Model `table-col-9`; template name "Row" (the block class AEM renders).

Fields — Row

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Column 1	`column1text`	richtext	No	—	—	—	—
Column 2	`column2text`	richtext	No	—	—	—	—
Column 3	`column3text`	richtext	No	—	—	—	—
Column 4	`column4text`	richtext	No	—	—	—	—
Column 5	`column5text`	richtext	No	—	—	—	—
Column 6	`column6text`	richtext	No	—	—	—	—
Column 7	`column7text`	richtext	No	—	—	—	—
Column 8	`column8text`	richtext	No	—	—	—	—
Column 9	`column9text`	richtext	No	—	—	—	—

What the tables don't show:

- **Options (`classes`)** is a grouped multiselect; its values become block classes: Striped (`striped`: odd body rows on `--color-bg-secondary`), Bordered (`bordered`: a 1px border on every cell), No Header (`no-header`: no `thead`; a 2px rule above the first body row), First Column Header (`row-header`: the first cell of each body row is a `th scope="row"`). They combine.

- **Columns (`filter`)** selects the component filter of the Table (`table`, `table-2-columns` … `table-5-columns`), i.e. which Row model Add offers; the code doesn't read it.
- **Row (Column 1 … Column 5)** are rich text; each Row becomes one `tr`, each column one cell, in authored order. Rows of different column counts are padded with empty cells to the widest row. New Rows are empty (no sample text in the templates).
- **Accessibility impact:** the header row and row headers become `th` with `scope`; the heading before the block names the table (`aria-labelledby`) and the scroll region.
- **Data-layer impact:** none of the fields adds tracking attributes; links in cells are tracked centrally.
- **Links in cells:** a link alone in its paragraph is turned into a link button by the content buttons decorator before the block is decorated (bold → primary, italic → secondary).
- **Legacy mapping:** none.
- **Additional tab:** as on every block (AGENTS.md "Additional tab"; Animation Type moves the block).

4. Screenshot-Based Authoring Steps

Authoring Step 1: Add the Table and set Columns

```
[Screenshot Placeholder]

File name:
table-authoring-step-1.png

Purpose:
The Table added to a section, the Columns select open on 4 Columns.

Annotations:
A = The Table in the content tree
B = Columns
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Component	Table	Adds the block	An empty Table
B	Columns	4 Columns	Quarter, Revenue, Growth, Margin	Add (+) offers Rows with Column 1 to Column 4

Author action: add the Table and set Columns before adding Rows. **Expected preview:** nothing visible yet. **Expected published result:** nothing until Rows exist. **Business rules:** Columns doesn't convert existing Rows. **Validation:** Add (+) on the Table shows a Row with four fields. **Common mistakes:** adding Rows with 1 Column first.

Authoring Step 2: Add the header Row and the data Rows

```
[Screenshot Placeholder]

File name:
table-authoring-step-2.png

Purpose:
The first Row filled with the column titles and a data Row selected in the content tree.

Annotations:
A = Header Row
B = Column 1 to Column 4 of a Row
C = The rendered header row on the canvas
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Row 1: Column 1 … Column 4	Quarter / Revenue / Growth / Margin	Column headers	Semibold header row on a 2px rule
B	Row 2: Column 1	Q1 FY26	First data row	A body row below the header

Author action: add Rows with Add (+) on the Table and fill them; drag to reorder. **Expected preview:** the header row, then the data rows with light separators. **Expected published result:** the same `table`. **Business rules:** the first Row is the header unless No Header is selected. **Validation:** count the cells of every row. **Common mistakes:** the header Row isn't first; units missing in the headers ("Revenue (USD bn)").

Authoring Step 3: Choose the Options

```
[Screenshot Placeholder]

File name:
table-authoring-step-3.png

Purpose:
The Options multiselect with Striped and First Column Header selected, and the result on the canvas.

Annotations:
A = Options
B = Striped rows
C = Row headers in the first column
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Options	Striped, First Column Header	Long table with row labels	Odd body rows grey; first cells semibold row headers

Author action: select the options. **Expected preview / published result:** as described. **Business rules:** Striped and Bordered combine with everything; No Header and First Column Header combine (label / value tables). **Validation:** inspect the first column in the accessibility tree (row headers). **Common mistakes:** No Header on data whose columns need names.

Authoring Step 4: Name the table

```
[Screenshot Placeholder]

File name:
table-authoring-step-4.png

Purpose:
A Title directly before the Table in the same section.

Annotations:
A = Title before the Table
B = The Table
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Title (component)	Quarterly results	Names the table for screen readers	The table is labelled "Quarterly results"

Author action: add a Title as the last element before the Table. **Expected result:** the heading gets an id and the table `aria-labelledby`; a scrolling table's region is named after it. **Common mistakes:** the heading is in another section or followed by a Text: the table is unnamed and the region is called "Table".

5. Variations

Standard (header row)

- **Purpose:** most tables. **Fields:** Rows, the first one the headers; no Options.
- **Rendering:** `thead` with the first row (`th scope="col"`), `tbody` with the others.
- **Accessibility:** column headers announced with each cell.

No Header

- **Purpose:** data whose meaning is obvious without column names. **Options:** No Header.
- **Rendering:** no `thead`; a 2px rule above the first body row; all cells `td` (unless First Column Header).

First Column Header

- **Purpose:** row labels (a matrix, specifications). **Options:** First Column Header.
- **Rendering:** the first cell of every body row is `th scope="row"` (semibold, start-aligned); the header row's first cell stays a column header.

Row headers only (No Header + First Column Header)

- **Purpose:** label / value tables (Founded 1968, Headquarters Mumbai, India).
- **Rendering:** no `thead`; semibold row headers in the first column.

Striped

- **Purpose:** long tables. **Rendering:** odd body rows (1st, 3rd, …) on `--color-bg-secondary`.

Bordered

- **Purpose:** dense numeric tables. **Rendering:** a 1px `--color-border-default` border on every cell.

1 to 9 Columns

- **Purpose:** the number of fields per Row (Row models `table-row`, `table-col-2` … `table-col-5`). **Dialog:** Columns, before adding Rows.

Scroll region (automatic)

- **Rendering:** while the table is wider than the block (`scrollWidth > clientWidth + 1`, watched with a ResizeObserver), the block gets `tabindex="0"`, `role="region"` and an `aria-label` (the heading's text, else the placeholder `table`, "Table"); removed when it fits. The block scrolls horizontally (`overflow-x: auto`) and shows a 2px brand focus outline.
- **Responsive:** typical on mobile from 4 columns.

```
[Screenshot Placeholder]

File name:
table-row-headers-only-mobile.png

Purpose:
A No Header + First Column Header table at 390 px.
```

```
Annotations:
A = Row headers
B = Values
```

Personalization and fallback: none for any variation; every visitor sees the authored rows.

6. Complete Authoring Example

Scenario: key facts on an About page as a label / value table.

Field	Example value	Guidance
Title before the block	Key facts	Names the table
Columns	2 Columns	Label and value
Options	No Header, First Column Header	Labels are row headers
Row 1	Founded / 1968	One fact per Row
Row 2	Headquarters / Mumbai, India	
Row 3	Employees / More than 600,000	
Row 4	Countries / 55	

Steps: add the Title, then the Table; set Columns and Options; add the four Rows; preview; publish.

Expected output: a 2-column table with a 2px rule above the first row, semibold labels and regular values, light separators.

Responsive: fits at every width; text `--body-font-size-s` below 900px, `--body-font-size-m` from 900px.

Accessibility: labels are `th scope="row"`; the table is labelled "Key facts".

Analytics / data layer: `tcs-corp/components/table` (`table-1`); no events unless cells hold links.

Personalization fallback: none.

Pre-publish checklist:

1. Columns matches every Row (no padded empty cells).
2. The header Row is first (or No Header is selected).
3. A heading is directly before the table.
4. Units are in the headers; numbers formatted for the locale.
5. Only the table scrolls at 390 px.
6. No empty header cells.

7. Content and Asset Guidelines

- **Headers:** short (units in the header); never leave header cells empty.
- **Cells:** short values; descriptive link text inside sentences (a link alone in a cell paragraph becomes a link button).
- **Images, icons, tags, metadata:** not part of the design; the block reads no tags or metadata.
- **Min / max items:** 1 to 9 columns (the Row models); no verified technical limit on the number of Rows was identified.
- **Localization:** translate every cell; check that translated text doesn't widen the table much; number and date formats aren't localised by the block.
- **Missing content:** a Table without Rows renders an empty `table` (nothing visible).

8. Troubleshooting

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
First data row shown as header	The first Row is the header unless No Header	Check Options	Add a header Row first, or select No Header	Header as intended
Add offers one-column Rows	Columns is 1 Column	Check Columns	Set Columns; recreate the Rows	New Rows have N fields
Empty cells at row ends	Rows of different column counts	Count fields per Row	Recreate short Rows with the right Columns	All rows equal
Page scrolls sideways on mobile	A wide element (long URL) or large margins	Device mode; find the overflowing element	Link text instead of URLs; reset margins	Only the table scrolls
Screen reader says "Table"	No heading directly before the block	Check `aria-labelledby` and the preceding element	Put the heading right before the Table	Region named after the heading
A cell link looks like a button	Link alone in its paragraph (content buttons decorator)	Check the cell's rich text	Write the link inside a sentence	Inline link
The first Row disappears	It is empty and has at most one cell (read as a tab row)	Check the first Row's content	Fill or delete the empty Row	The header row shows

Evidence to collect (no secrets): page URL, `.plain.html` of the block, a screenshot at the failing width, the block's classes and the accessibility tree of the table.

9. Screenshots




Figure: Table as published (block library) — desktop 1440 × 900 (/design-block-master/en/block-library/table/table, captured 2026-11-08).




Figure: Table as published (block library) — mobile 375 × 812 (/design-block-master/en/block-library/table/table, captured 2026-11-08).

> **Screenshot required**

> - Required screen: Table dialog in Universal Editor (every tab, including Additional)
> - Required role/access: AEM Sites author with Universal Editor (content author)
> - Required navigation steps: AEM Sites console > /content/tcs-corp/language-masters/en > open a page in Universal Editor
> - Reason unavailable: No AEM author access in the documentation program (access blocker AB-01)
> - Owner: Content Lead / AEM Authoring Lead (proposed)
> - Target completion date: To be confirmed

10. Known limitations

- Universal Editor screenshots are placeholders: no author access in this program.

11. Open items

- None.

12. Change history

Version	Date	Author	Change
1.0	13 November 2026	Delivery team (documentation program)	First version of the role-specific documentation (master documentation prompt), generated from the repository and the published reference pages