TCS CORPORATE WEBSITE

Tabs — Authoring Guide

Role / audience	Authoring — Content authors, content managers, AEM authoring leads
Version	1.0
Status	Draft for review
Owner	Content Lead / AEM Authoring Lead (proposed)
Last validated	2026-11-13
Documents	1
Classification	INTERNAL — classification to be confirmed

Generated from the Markdown sources of docs/handover (branch migrated-page-content-edam); do not edit this PDF.

Contents

Tabs — Authoring Guide
- Where to see it
- For Content Authors
- Authorable Fields
- Screenshot-Based Authoring Steps
- Variations
- Complete Authoring Example
- Content and Asset Guidelines
- Troubleshooting
- Screenshots
- Known limitations
- Open items
- Change history

Tabs — Authoring Guide

Attribute	Value
Document ID	AUT-C-tabs
Audience	Content authors, content managers, AEM authoring leads
Purpose	How to add, fill in and check the Tabs component
Scope	—
Prerequisites	—
Owner	Content Lead / AEM Authoring Lead (proposed)
Approver	Product Owner (to be confirmed)
Version	1.0
Status	Draft for review
Last updated	13 November 2026
Last validated	13 November 2026
Source files	blocks/tabs/README.md, blocks/tabs/_tabs.json
Related documents	—
Related AEM paths	—

1. Where to see it

- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments/cloud-overview
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments/consulting-overview
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments/security-overview
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments/tab-industries
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/fragments/tab-overview
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tab
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tab-deep-link
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tabs-block
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tabs-block-styles
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tabs-block-with-fragments
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tabs-fixed-width
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/tabs/tabs-section

2. For Content Authors

Tabs Container (tabs built on the page)

1. On the page, choose Add (+) where sections are added and pick **Tabs Container**.

2. Select the Tabs Container to open its properties. In **Content**, enter a **Label** that names the group for screen readers (for example "Our services"); optionally an **Anchor name** (the section id; also the prefix of tab ids without their own ID) and the **Width Type**.
3. In **Styles**, choose the **Style** (Underline, Boxed, Pills), **Alignment** (Left, Center, Full width (stretch)) and **Orientation** (Horizontal, Vertical).
4. Inside the Tabs Container, add a **Tab** and enter its **Title** (required: the tab label). Optionally enter an **ID** for links (`#consulting`) and turn on **Active tab** for the tab shown first. See Tab.
5. After the Tab, add the components of that tab (Text, Title, Image, Button, Teaser, Cards, a Tabs block, and the other components the container allows). Then add the next Tab and its components, and so on.
6. For columns inside a tab, add a **Column Break** after the Tab, then the components of the first column, another Column Break, then the components of the second column. Set **Columns per row** on the Tab. Content between the Tab and the first Column Break stays above the columns. See Column Break.
7. To reorder tabs, move a Tab and its components together in the content tree; a component belongs to the Tab above it.

Tabs block (tabs of fragment pages)

1. In a Section (or inside a Tabs Container or Columns Container), choose Add (+) and pick **Tabs**.
2. In its properties, enter the **Label** and optionally a **Tab ID prefix**; set Style, Alignment and Orientation in **Styles**; the **Additional** tab has the block options.
3. Inside the block, add a **Tab** item per tab. In its **Tab** tab enter the **Title**, optionally the **ID** and **Active tab**; in its **Fragment** tab choose the **Fragment** page whose content the tab shows.
4. Reorder the Tab items in the content tree to reorder the tabs.

Preview, publish and validate

1. Switch Universal Editor to Preview and click each tab; check the tab shown first.
2. Publish the page. For the Tabs block, publish the fragment pages too (a fragment that isn't published leaves its panel empty).
3. On the published page, check each tab, the keyboard (arrow keys), and any `#id` links to tabs.

Minimum required: a Tabs Container with at least one Tab with a Title and content after it; or a Tabs block with at least one Tab item with a Title and a Fragment. **Recommended:** a Label, a unique Title per tab, an ID on tabs that are linked to, and a heading at the start of each panel. **Optional:** Active tab, Style, Alignment, Orientation, Width Type, Column Breaks, the Additional tab.

3. Authorable Fields

Tabs Container (`tabs`)

Model `tabs`; template name "Tabs" (the block class AEM renders); children: `tab`, `column-break`, `text`, `image`, `button-block`, `title`, `hero`, `teaser`, `image-collage`, `quote`, `media-contacts`, `testimonial`, `anchor-list`, `accordion`, `table`, `table-list`, `list`, `separator`, `embed`, `video`, `modal`, `form-variations`, `filter-list`, `cards`, `fragment`, `tabs-block`.

Stored on a new component (definition template): `style` = `"tabs-section"`, `tabsStyle` = `"underline"`, `tabsAlignment` = `"left"`, `tabsOrientation` = `"horizontal"`.

Content tab — Tabs Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Component	`style`	select	No	`tabs-section`	Tabs (`tabs-section`)	—	`tabs-section`

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor name	anchorName	text	No	—	regExp: ^#?[a-z0-9][a-z0-9-]*$; customErrorMsg: Lower-case letters, digits and hyphens, e.g. our-offices.	The section id: #links and Anchor List links jump to it; also the prefix of tab ids without their own ID.	—
Width Type	sectionWidth	select	No	full-width	Full Width (full-width), Fixed Width (fixed-width)	—	full-width
Label	tabsAriaLabel	text	No	—	—	Names the tab list for screen readers (aria-label), e.g. Our services.	Our services

Styles tab — Tabs Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Style	tabsStyle	select	No	underline	Underline (underline), Boxed (boxed), Pills (pills)	—	underline
Alignment	tabsAlignment	select	No	left	Left (left), Center (center), Full width (stretch) (stretch)	—	left
Orientation	tabsOrientation	select	No	horizontal	Horizontal (horizontal), Vertical (vertical)	Vertical: the tab list is on the left of the content on desktop, above it on mobile.	horizontal

Additional tab — Tabs Container

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	containerAnchor	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	The id of the tabs block itself (start with anchor-). Use Anchor name for links to the section.	—
Hide block	containerHide	boolean	No	false	on / off	Hides the whole block on the page until it is turned off (shown faded in the editor).	—
Animation Type	containerAnimation	select	No	""	None (""), Fade in (motion-fade-in), Fade up (motion-fade-up), Fade down (motion-fade-down), Fade left (motion-fade-left), Fade right (motion-fade-right), Slide up (motion-slide-up), Slide down (motion-slide-down), Slide left (motion-slide-left), Slide right (motion-slide-right), Scale in (motion-scale-in)	How the block's content appears; repeated items (cards, list items, accordion items, columns) appear one after another. None: shown as is. Not played in the editor or when the visitor prefers reduced motion.	—
Motion Speed	containerAnimationSpeed	select	No	""	Medium (""), Fast (motion-fast), Slow (motion-slow)	How fast the animation runs: 0.3, 0.6 or 0.9 seconds. Shown when containerAnimation is set and containerAnimation is not empty.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Animation Trigger	containerAnimationTrigger	select	No	""	On Scroll / Viewport Entry (""), On Page Load (motion-on-load)	When the block's animations run. On Scroll: when the block comes into view (at once if it is in view when the page opens). On Page Load: as soon as the block is ready, wherever it is on the page. Shown when containerAnimation is set and containerAnimation is not empty.	—
Padding left	containerPaddingLeft	select	No	""	Default (""), 0 (none) (pl-0), 0.25rem (space-100) (pl-100), 0.5rem (space-200) (pl-200), 0.75rem (space-300) (pl-300), 1rem (space-400) (pl-400), 1.25rem (space-500) (pl-500), 1.5rem (space-600) (pl-600), 2rem (space-800) (pl-800), 2.5rem (space-1000) (pl-1000), 3rem (space-1200) (pl-1200), 4rem (space-1600) (pl-1600), 5rem (space-2000) (pl-2000), 6rem (space-2400) (pl-2400), 7.5rem (space-3000) (pl-3000)	—	—
Padding right	containerPaddingRight	select	No	""	Default (""), 0 (none) (pr-0), 0.25rem (space-100) (pr-100), 0.5rem (space-200) (pr-200), 0.75rem (space-300) (pr-300), 1rem (space-400) (pr-400), 1.25rem (space-500) (pr-500), 1.5rem (space-600) (pr-600), 2rem (space-800) (pr-800), 2.5rem (space-1000) (pr-1000), 3rem (space-1200) (pr-1200), 4rem (space-1600) (pr-1600), 5rem (space-2000) (pr-2000), 6rem (space-2400) (pr-2400), 7.5rem (space-3000) (pr-3000)	—	—
Padding top	containerPaddingTop	select	No	""	Default (""), 0 (none) (pt-0), 0.25rem (space-100) (pt-100), 0.5rem (space-200) (pt-200), 0.75rem (space-300) (pt-300), 1rem (space-400) (pt-400), 1.25rem (space-500) (pt-500), 1.5rem (space-600) (pt-600), 2rem (space-800) (pt-800), 2.5rem (space-1000) (pt-1000), 3rem (space-1200) (pt-1200), 4rem (space-1600) (pt-1600), 5rem (space-2000) (pt-2000), 6rem (space-2400) (pt-2400), 7.5rem (space-3000) (pt-3000)	—	—
Padding bottom	containerPaddingBottom	select	No	""	Default (""), 0 (none) (pb-0), 0.25rem (space-100) (pb-100), 0.5rem (space-200) (pb-200), 0.75rem (space-300) (pb-300), 1rem (space-400) (pb-400), 1.25rem (space-500) (pb-500), 1.5rem (space-600) (pb-600), 2rem (space-800) (pb-800), 2.5rem (space-1000) (pb-1000), 3rem (space-1200) (pb-1200), 4rem (space-1600) (pb-1600), 5rem (space-2000) (pb-2000), 6rem (space-2400) (pb-2400), 7.5rem (space-3000) (pb-3000)	—	—
Margin left	containerMarginLeft	select	No	""	Default (""), 0 (none) (ml-0), 0.25rem (space-100) (ml-100), 0.5rem (space-200) (ml-200), 0.75rem (space-300) (ml-300), 1rem (space-400) (ml-400), 1.25rem (space-500) (ml-500), 1.5rem (space-600) (ml-600), 2rem (space-800) (ml-800), 2.5rem (space-1000) (ml-1000), 3rem (space-1200) (ml-1200), 4rem (space-1600) (ml-1600), 5rem (space-2000) (ml-2000), 6rem (space-2400) (ml-2400), 7.5rem (space-3000) (ml-3000)	—	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Margin right	containerMarginRight	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	—	—
Margin top	containerMarginTop	select	No	""	Default (""), 0 (none) (mt-0), 0.25rem (space-100) (mt-100), 0.5rem (space-200) (mt-200), 0.75rem (space-300) (mt-300), 1rem (space-400) (mt-400), 1.25rem (space-500) (mt-500), 1.5rem (space-600) (mt-600), 2rem (space-800) (mt-800), 2.5rem (space-1000) (mt-1000), 3rem (space-1200) (mt-1200), 4rem (space-1600) (mt-1600), 5rem (space-2000) (mt-2000), 6rem (space-2400) (mt-2400), 7.5rem (space-3000) (mt-3000)	—	—
Margin bottom	containerMarginBottom	select	No	""	Default (""), 0 (none) (mb-0), 0.25rem (space-100) (mb-100), 0.5rem (space-200) (mb-200), 0.75rem (space-300) (mb-300), 1rem (space-400) (mb-400), 1.25rem (space-500) (mb-500), 1.5rem (space-600) (mb-600), 2rem (space-800) (mb-800), 2.5rem (space-1000) (mb-1000), 3rem (space-1200) (mb-1200), 4rem (space-1600) (mb-1600), 5rem (space-2000) (mb-2000), 6rem (space-2400) (mb-2400), 7.5rem (space-3000) (mb-3000)	—	—

Tabs (`tabs-block`)

Model `tabs-block`; template name "Tabs" (the block class AEM renders); key-value block (one row per property); children: `tabs-item`.

Stored on a new component (definition template): `tabsStyle` = `"underline"`, `tabsAlignment` = `"left"`, `tabsOrientation` = `"horizontal"`.

Content tab — Tabs

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Tab ID prefix	tabsId	text	No	—	—	Prefix of the tab ids (e.g. our-offerings-item-1); not an anchor: use Anchor ID for links.	our-offerings
Label	tabsAriaLabel	text	No	—	—	Names the tab list for screen readers (aria-label), e.g. Our services.	How we help

Styles tab — Tabs

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Style	tabsStyle	select	No	underline	Underline (underline), Boxed (boxed), Pills (pills)	—	underline
Alignment	tabsAlignment	select	No	left	Left (left), Center (center), Full width (stretch) (stretch)	—	left

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Orientation	`tabsOrientation`	select	No	`horizontal`	Horizontal (`horizontal`), Vertical (`vertical`)	Vertical: the tab list is on the left of the content on desktop, above it on mobile.	horizontal

Additional tab — Tabs

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	`classes_anchor`	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	A unique ID of the block on the page, starting with anchor-, e.g. anchor-our-services; link to it with #anchor-our-services. Delivered as a block class.	—
Hide block	`classes_hideblock`	boolean	No	`false`	on / off	Hides the whole block on the page until it is turned off (shown faded in the editor). Delivered as a block class.	—
Padding left	`classes_paddingleft`	select	No	""	Default (""), 0 (none) (`pl-0`), 0.25rem (space-100) (`pl-100`), 0.5rem (space-200) (`pl-200`), 0.75rem (space-300) (`pl-300`), 1rem (space-400) (`pl-400`), 1.25rem (space-500) (`pl-500`), 1.5rem (space-600) (`pl-600`), 2rem (space-800) (`pl-800`), 2.5rem (space-1000) (`pl-1000`), 3rem (space-1200) (`pl-1200`), 4rem (space-1600) (`pl-1600`), 5rem (space-2000) (`pl-2000`), 6rem (space-2400) (`pl-2400`), 7.5rem (space-3000) (`pl-3000`)	Delivered as a block class.	—
Padding right	`classes_paddingright`	select	No	""	Default (""), 0 (none) (`pr-0`), 0.25rem (space-100) (`pr-100`), 0.5rem (space-200) (`pr-200`), 0.75rem (space-300) (`pr-300`), 1rem (space-400) (`pr-400`), 1.25rem (space-500) (`pr-500`), 1.5rem (space-600) (`pr-600`), 2rem (space-800) (`pr-800`), 2.5rem (space-1000) (`pr-1000`), 3rem (space-1200) (`pr-1200`), 4rem (space-1600) (`pr-1600`), 5rem (space-2000) (`pr-2000`), 6rem (space-2400) (`pr-2400`), 7.5rem (space-3000) (`pr-3000`)	Delivered as a block class.	—
Padding top	`classes_paddingtop`	select	No	""	Default (""), 0 (none) (`pt-0`), 0.25rem (space-100) (`pt-100`), 0.5rem (space-200) (`pt-200`), 0.75rem (space-300) (`pt-300`), 1rem (space-400) (`pt-400`), 1.25rem (space-500) (`pt-500`), 1.5rem (space-600) (`pt-600`), 2rem (space-800) (`pt-800`), 2.5rem (space-1000) (`pt-1000`), 3rem (space-1200) (`pt-1200`), 4rem (space-1600) (`pt-1600`), 5rem (space-2000) (`pt-2000`), 6rem (space-2400) (`pt-2400`), 7.5rem (space-3000) (`pt-3000`)	Delivered as a block class.	—
Padding bottom	`classes_paddingbottom`	select	No	""	Default (""), 0 (none) (`pb-0`), 0.25rem (space-100) (`pb-100`), 0.5rem (space-200) (`pb-200`), 0.75rem (space-300) (`pb-300`), 1rem (space-400) (`pb-400`), 1.25rem (space-500) (`pb-500`), 1.5rem (space-600) (`pb-600`), 2rem (space-800) (`pb-800`), 2.5rem (space-1000) (`pb-1000`), 3rem (space-1200) (`pb-1200`), 4rem (space-1600) (`pb-1600`), 5rem (space-2000) (`pb-2000`), 6rem (space-2400) (`pb-2400`), 7.5rem (space-3000) (`pb-3000`)	Delivered as a block class.	—
Margin left	`classes_marginleft`	select	No	""	Default (""), 0 (none) (`ml-0`), 0.25rem (space-100) (`ml-100`), 0.5rem (space-200) (`ml-200`), 0.75rem (space-300) (`ml-300`), 1rem (space-400) (`ml-400`), 1.25rem (space-500) (`ml-500`), 1.5rem (space-600) (`ml-600`), 2rem (space-800) (`ml-800`), 2.5rem (space-1000) (`ml-1000`), 3rem (space-1200) (`ml-1200`), 4rem (space-1600) (`ml-1600`), 5rem (space-2000) (`ml-2000`), 6rem (space-2400) (`ml-2400`), 7.5rem (space-3000) (`ml-3000`)	Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Margin right	classes_marginright	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	Delivered as a block class.	—
Margin top	classes_margintop	select	No	""	Default (""), 0 (none) (mt-0), 0.25rem (space-100) (mt-100), 0.5rem (space-200) (mt-200), 0.75rem (space-300) (mt-300), 1rem (space-400) (mt-400), 1.25rem (space-500) (mt-500), 1.5rem (space-600) (mt-600), 2rem (space-800) (mt-800), 2.5rem (space-1000) (mt-1000), 3rem (space-1200) (mt-1200), 4rem (space-1600) (mt-1600), 5rem (space-2000) (mt-2000), 6rem (space-2400) (mt-2400), 7.5rem (space-3000) (mt-3000)	Delivered as a block class.	—
Margin bottom	classes_marginbottom	select	No	""	Default (""), 0 (none) (mb-0), 0.25rem (space-100) (mb-100), 0.5rem (space-200) (mb-200), 0.75rem (space-300) (mb-300), 1rem (space-400) (mb-400), 1.25rem (space-500) (mb-500), 1.5rem (space-600) (mb-600), 2rem (space-800) (mb-800), 2.5rem (space-1000) (mb-1000), 3rem (space-1200) (mb-1200), 4rem (space-1600) (mb-1600), 5rem (space-2000) (mb-2000), 6rem (space-2400) (mb-2400), 7.5rem (space-3000) (mb-3000)	Delivered as a block class.	—

Tab (`tabs-item`)

Model `tabs-item`; template name "Tab" (the block class AEM renders).

Tab tab — Tab

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Title	title	text	Yes	—	—	The label of the tab.	—
ID	tabId	text	No	—	regExp: ^#?[a-z0-9][a-z0-9-]*$; customErrorMsg: Lower-case letters, digits and hyphens, e.g. overview.	Links to #ID open this tab (deep link), e.g. overview (lowercase, no spaces). Leave empty for an id from the Tabs ID.	—
Active tab	activeTab	boolean	No	—	on / off	Shows this tab when the page loads (the first tab if no tab is active).	—

Fragment tab — Tab

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Fragment	fragment	aem-content	No	—	—	A page whose content (any components, e.g. Columns, Title, Text, Image, Button) is shown in the tab.	—

Notes on the fields (see the tables above for labels, values and defaults):

- **Component** (`style`, Tabs Container): its only value `tabs-section` makes the section a Tabs Container (`scripts.js` `buildTabsSections` looks for the class `tabs-section`). Keep it.
- **Label** (`tabsAriaLabel`): the tab list's `aria-label`; empty: the placeholder `tabs` ("Tabs"). Screen readers announce it with the tab list.

- **Anchor name** (`anchorName`, Tabs Container) and **Tab ID prefix** (`tabsId`, Tabs block): the base of the panel ids of tabs without an ID (`{base}-item-{n}`); without it the base is `tabs-{n}`. Anchor name is also the section id (`#our-services` scrolls to the section but doesn't change the tab).
- **Style**, **Alignment**, **Orientation** (`tabsStyle`, `tabsAlignment`, `tabsOrientation`): block classes (`underline` / `boxed` / `pills`, `left` / `center` / `stretch`, `horizontal` / `vertical`). The Tabs block accepts only these values (`pick`); the Tabs Container adds the delivered value as a class. Orientation Vertical also sets `aria-orientation="vertical"` on the tab list at every width; the layout is vertical only from 900px.
- **Width Type** (`sectionWidth`, Tabs Container): the section option (`fixed-width` class), as on sections.
- **Tab item Title / ID / Active tab** (`tabs-item`): the tab label (empty: placeholder `tabNumber`, "Tab {n}"), the panel id (normalized to lower case with hyphens; a taken id gets `-2`, `-3`) and the tab shown first (only the value `true` counts; the first active tab wins).
- **Fragment** (`tabs-item`): the page whose content the panel shows; it must be a site path (starting with `/`). The Tab of a Tabs Container has no Fragment.
- **Legacy mapping:** Tab items authored when the item had Content fields have more cells; the Fragment is read from the last cell. Tabs Containers holding built-in Columns blocks authored before keep rendering.
- **Additional tab:** see AGENTS.md "Additional tab". The Tabs block uses the `classes_*` fields (block classes; it has no animation fields). The Tabs Container uses the `container*` fields (AEM doesn't deliver a section's `classes_*` fields), which `scripts.js` `applySectionBlockOptions` turns into classes of the synthetic `tabs` block: Anchor ID, Hide block (hides the whole section on the page), Animation Type / Motion Speed / Animation Trigger (the whole block animates; Tabs is not in the motion decorator's `CONTENT_TARGETS`) and Padding / Margin.
- **Data layer:** each panel is a data-layer component (`tcs-corp/components/tabs/item`) whose title is the tab label; see Data Layer and Analytics.

4. Screenshot-Based Authoring Steps

Authoring Step 1: Add the Tabs Container

```
[Screenshot Placeholder]

File name:
tabs-authoring-step-1.png

Purpose:
The page's Add (+) menu with Tabs Container selected, and the new Tabs Container's Content tab.

Annotations:
A = Add (+) on the page
B = Tabs Container in the component list
C = Label field
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Add (+)	Tabs Container	Tabs Containers are added where sections are added	An empty Tabs Container; in edit mode it shows "Add a Tab, then the components of the tab after it."
C	Label	Our services	Names the tab list for screen readers	`aria-label="Our services"` on the tab list
—	Width Type	Full Width	Default section width	The tabs span the content width

Author action: add the Tabs Container, select it, enter the Label. Expected preview: the empty-state hint. Expected published result: nothing is shown until the container has a Tab. Business rule: keep Component

set to Tabs. Validation: the section has the class `tabs-section`. Common mistake: adding a Section instead (it shows the content one below another, without tabs); resolution: add a Tabs Container and move the components into it.

Authoring Step 2: Add the first Tab and its content

```
[Screenshot Placeholder]

File name:
tabs-authoring-step-2.png

Purpose:
A Tab added inside the Tabs Container with its Content tab open, and a Title and Text added after it.

Annotations:
A = Tab chip in the panel (edit mode)
B = Title field of the Tab
C = ID field
D = Components after the Tab
```

Values to Enter

Callout	Field	Value	Reason	Expected result
B	Title	Consulting	The tab label	A tab button "Consulting"
C	ID	consulting	Links to `#consulting` open this tab	Panel id `consulting`
—	Active tab	On	Shows this tab when the page loads	Consulting is selected on load
D	Title, Text after the Tab	Business and technology consulting; a short paragraph	The tab's content	Shown in the Consulting panel

Author action: inside the Tabs Container add a Tab, fill its fields, then add the components after it. Expected preview: the tab list with Consulting; in edit mode the dashed Tab chip at the top of the panel. Published: the chip is hidden; the content shows in the panel. Business rule: a component belongs to the Tab above it; content before the first Tab becomes an untitled first tab ("Tab 1"). Validation: the tab label matches the Title. Common mistake: components placed before the first Tab; resolution: move them after a Tab.

Authoring Step 3: Add more tabs

```
[Screenshot Placeholder]

File name:
tabs-authoring-step-3.png

Purpose:
The content tree of a Tabs Container with three Tabs (Consulting, Cloud, Cybersecurity), each followed
by its components.

Annotations:
A = Tab Consulting and its components
B = Tab Cloud and its components
C = Tab Cybersecurity and its components
```

Values to Enter

Callout	Field	Value	Reason	Expected result
B	Title / ID	Cloud / cloud	Second tab	Tab button "Cloud", panel id `cloud`
C	Title / ID	Cybersecurity / cybersecurity	Third tab	Tab button "Cybersecurity", panel id `cybersecurity`

Author action: add each Tab after the content of the previous tab. Expected preview: three tab buttons; selecting a component in the editor shows its tab. Published: one panel at a time. Business rule: keep Active tab on one Tab at most. Validation: each panel holds only its own content. Common mistake: a component dragged under the wrong Tab; resolution: move it in the content tree. Note: a change to a Tab's ID, Active tab, Columns per row or Hide block applies after a reload of the editor (the label updates at once).

Authoring Step 4: Lay out a tab in columns

```
[Screenshot Placeholder]

File name:
tabs-authoring-step-4.png

Purpose:
A tab with a heading, then two Column Breaks each followed by its components, and the Tab's Columns per
row set to 2.

Annotations:
A = Columns per row on the Tab
B = Heading above the columns
C = First Column Break and its column
D = Second Column Break and its column
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Columns per row (Tab)	2	Two columns side by side	`per-row-2` on the columns built in the panel
B	Title before the first Column Break	Business and technology consulting	Stays above the columns	A heading across the panel
C	Column name (Column Break)	Image	Tells the columns apart in the editor	Label "Image" in edit mode only
D	Column name (Column Break)	Text	—	Label "Text" in edit mode only

Author action: after the Tab and the heading, add a Column Break, an Image, a Column Break, a Text. Expected preview: two columns from 900px, stacked below. Published: the same; Column Break labels are hidden. Business rule: in a tab, Gap, Vertical alignment and Side by side from aren't offered (medium gap, top, from Desktop 900px). Validation: the columns sit side by side at desktop width. Common mistake: expecting the Columns Container's Layout fields on the Tab; resolution: use a Columns Container section when those options are needed.

Authoring Step 5: Style, preview and publish

```
[Screenshot Placeholder]

File name:
tabs-authoring-step-5.png

Purpose:
```

```
The Styles tab of the Tabs Container with Style Boxed, Alignment Center and Orientation Horizontal, and
the preview of the result.

Annotations:
A = Style
B = Alignment
C = Orientation
D = Preview of the tab list
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Style	Underline	The default, as the Anchor List chapter nav	Brand underline under the selected tab
B	Alignment	Left	Default	Tabs start at the left
C	Orientation	Horizontal	Default	Tab list above the panel

Author action: choose the styles, switch to Preview, click each tab, publish. Expected published result: the selected style at every width; tabs that don't fit scroll horizontally. Validation: arrow keys move between tabs; `#cloud` opens Cloud. Common mistake: Vertical tested in a narrow editor canvas (vertical only from 900px); resolution: check at desktop width.

5. Variations

Tabs Container (section mode)

Purpose: tabs whose content is authored on the page. **When to use:** content unique to this page. **When not to use:** content shared by several pages (use the Tabs block). **Required:** Component `tabs-section` (default), at least one Tab with a Title and content after it. **Optional:** Label, Anchor name, Width Type, Styles, Additional tab, Column Breaks. **Dialog:** model `tabs`. **Rendering:** `buildTabsSections` wraps the section content in a synthetic `tabs` block with `data-source="section"`; each Tab starts a group; the Tab wrappers stay in the panels (hidden on the page, shown in edit mode). **Desktop / tablet / mobile:** see Responsive Behavior. **Accessibility:** as below. **Data layer:** panels as components, `cmp:show` on change. **Personalization / fallback:** none; the authored content renders.

```
[Screenshot Placeholder]

File name:
tabs-container-desktop.png

Purpose:
A Tabs Container at desktop width with three tabs and the first panel's own content.

Annotations:
A = Tab list
B = Selected tab
C = Panel content authored after the Tab
```

Tabs block (fragment mode)

Purpose: tabs of reusable fragment pages. **When to use:** the same tabs on several pages. **When not to use:** content that exists only on this page. **Required:** at least one Tab item with a Title and a Fragment. **Optional:** Label, Tab ID prefix, Styles, Additional tab. **Dialog:** model `tabs-block`, items `tabs-item` (Tab / Fragment tabs). **Rendering:** each item's fragment is loaded (all in parallel) into a `.tabs-fragment` wrapper in its panel; each item's editor instrumentation moves to its panel. **Data layer / personalization:** as the container. A fragment that can't be loaded leaves its panel empty (no message on the page).

```
[Screenshot Placeholder]

File name:
tabs-block-fragments-desktop.png

Purpose:
A Tabs block whose panel shows the content of its fragment page.

Annotations:
A = Tab list
B = Panel with the fragment's sections
```

Style: Underline, Boxed, Pills

Underline (default): plain labels on a divider, the selected tab semibold with a brand bottom border. Boxed: grey boxes with rounded top corners; the selected one white with a border and brand text. Pills: outlined pills, no divider; the selected one filled with the brand colour. Available on both forms. **Accessibility:** state is shown by colour and border and by `aria-selected`. Choose the style that fits the surrounding design.

```
[Screenshot Placeholder]

File name:
tabs-styles-desktop.png

Purpose:
The three Styles side by side: Underline, Boxed, Pills.

Annotations:
A = Underline
B = Boxed
C = Pills
```

Alignment: Left, Center, Full width (stretch)

Left (default): tabs start at the left. Center: the tabs are centred (`justify-content: safe center`, so a list that overflows still scrolls from its start). Full width (stretch): the tabs share the width (`flex: 1 0 auto`). Use Full width for two to four short labels.

```
[Screenshot Placeholder]

File name:
tabs-alignment-desktop.png

Purpose:
Left, Center and Full width (stretch) alignment of the same tab list.

Annotations:
A = Left
B = Center
C = Full width (stretch)
```

Orientation: Horizontal, Vertical

Horizontal (default): the tab list above the panel. Vertical: from 900px a grid with the tab list on the left (`minmax(12.5rem, 1fr)`) and the panel on the right (`3fr`), labels wrapping; below 900px the list stays above the panel. Use Vertical for many or long labels (for example translated labels). `aria-orientation="vertical"` is set at every width, so Arrow Up / Down and Left / Right all work.

```
[Screenshot Placeholder]
```

```
File name:
tabs-vertical-tablet.png

Purpose:
Orientation Vertical below 900px: the tab list stays above the panel.

Annotations:
A = Tab list above the panel
B = Panel
```

Width Type: Full Width, Fixed Width (Tabs Container only)

The section option: Full Width (default) or Fixed Width (the `fixed-width` section, capped at the content width by `styles/styles.css`).

```
[Screenshot Placeholder]

File name:
tabs-width-fixed-desktop.png

Purpose:
A Fixed Width Tabs Container on a wide screen, centred at the content width.

Annotations:
A = Tabs and panel at the content width
```

Columns in a tab (Column Breaks)

Purpose: columns of components inside a tab (a section can't hold a Columns Container section). **Required:** a Column Break after the Tab, then that column's components; more Column Breaks for more columns. **Optional:** the Tab's Columns per row (Automatic: as many as there are Column Breaks, at most 4). **Rendering:** `columnsOf` builds a `columns-container` block in the panel (decorated while empty, then loaded with `loadBlock`); content before the first Column Break stays above it; the columns get the data-layer id `{panel id}-columns`. Gap, alignment and breakpoint are the Columns Container defaults (medium, top, side by side from 900px). See Columns Container and Column Break.

Nested Tabs

A Tabs block can be added inside a tab of a Tabs Container (the `tabs` filter allows `tabs-block`). The CSS uses child selectors, so the inner Tabs keep their own Style and Orientation. Selecting a component in the editor or following a deep link opens the outer and the inner tab.

6. Complete Authoring Example

Scenario: a services page shows three service lines in a Tabs Container; Cloud is linked from a campaign email as `#cloud`.

Field	Example value	Guidance
Label	Our services	Describe the group
Style / Alignment / Orientation	Underline / Left / Horizontal	Defaults
Tab 1 Title / ID	Consulting / consulting	1 to 3 words; lower-case ID
Tab 1 content	Title "Business and technology consulting", Text, Button "Explore consulting"	Start the panel with a heading
Tab 2 Title / ID / Active tab	Cloud / cloud / On	Shown first

Field	Example value	Guidance
Tab 2 content	Title, Column Break, Image (with alt text), Column Break, Text; Columns per row 2	Heading above two columns
Tab 3 Title / ID	Cybersecurity / cybersecurity	—

Steps: add the Tabs Container (Step 1), add the Tabs and their content (Steps 2–4), choose the styles (Step 5), preview, publish.

Expected output: three tab buttons, Cloud selected on load; `/page#consulting` opens Consulting and scrolls the Tabs below the fixed header. Responsive: the list scrolls horizontally if it doesn't fit; the Cloud columns sit side by side from 900px and stack below. Accessibility: tab list named "Our services", arrow keys move between tabs. Analytics: a tab change pushes `cmp:show` for its panel; clicks on the tab buttons push `cmp:click` (see below). Personalization fallback: none; the authored content shows.

Pre-publish checklist:

- Every Tab has a unique Title; at most one Active tab.
- Every panel starts with a heading; images have alt text.
- No component sits before the first Tab.
- IDs used in links match the Tab IDs exactly.
- Tabs block: every fragment page is published.

7. Content and Asset Guidelines

- **Tab titles:** short (the handover recommends 1 to 3 words); tabs that don't fit scroll horizontally (`white-space: nowrap` in horizontal lists). Translated labels may be longer: consider Vertical.
- **Label:** a few words naming the group.
- **IDs:** lower-case letters, digits and hyphens (the model validates `^#?[a-z0-9][a-z0-9-]*$`); keep them identical across locales for links.
- **Panel content:** a heading that matches the tab, then the content; keep panels of similar length so the page doesn't jump between tabs. Each component follows its own guidelines (images, alt text, buttons, CTAs).
- **CTAs:** don't place the page's main call to action only in a tab that isn't shown first.
- **Images:** limited to the panel width (`max-width: 100%`, `height: auto`); loading follows the component (Image, Teaser, ...).
- **Min / max items:** no verified technical limit was identified (the tab list scrolls).
- **Tags and metadata:** not used.
- **Missing content:** an empty Title becomes "Tab {n}"; a Tabs Container or Tabs block without tabs renders nothing on the page (a hint in edit mode); a missing fragment leaves its panel empty.

8. Troubleshooting

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
Content shown without tabs	A Section instead of a Tabs Container, or Component not `tabs-section`	Inspect the section for the class `tabs-section` and `div.tabs-wrapper`	Use a Tabs Container; keep Component Tabs	Tab list appears
An extra "Tab 1" first	A component before the first Tab	Check the content tree order	Move it after a Tab	Only titled tabs
Tabs block panel empty	No Fragment, fragment not published, not a site path	Open `{fragment}.plain.html` on the same host; check the network panel	Choose and publish the fragment	Panel shows the fragment

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
Deep link opens the first tab	ID differs (normalized), de-duplicated (`-2`), or the link targets the button or section id	Inspect the panel `id` / `data-tab-id`	Use the exact Tab ID after #	The tab opens
Wrong tab on load	Several Active tabs, a #hash, or the editor keeps the tab shown before a re-render	Check Active tab on every Tab; load without hash	One Active tab	Correct tab on a fresh load
Vertical tabs horizontal	Below 900px (by design) or value not delivered	Check width; inspect for the `vertical` class	Test at 900px or wider; re-save	Left column from 900px
Tab option change without effect in the editor	Tab ID, Active tab, Columns per row, Hide block apply after a re-render of the container (R-C-7)	Reload the editor	Reload	Option applied
Tab chip visible on the page	A Tab outside a Tabs Container	Check the section class	Move or delete the Tab	No chip

Evidence to collect (no secrets): page URL, viewport width, the section's classes and data attributes, the panel ids, console errors, the `adobeDataLayer` entries for the Tabs.

9. Screenshots




Figure: Tabs as published (block library) — desktop 1440 × 900 (/design-block-master/en/block-library/tabs/fragments, captured 2026-11-08).




Figure: Tabs as published (block library) — mobile 375 × 812 (/design-block-master/en/block-library/tabs/fragments, captured 2026-11-08).

> **Screenshot required**

> - Required screen: Tabs dialog in Universal Editor (every tab, including Additional)
> - Required role/access: AEM Sites author with Universal Editor (content author)
> - Required navigation steps: AEM Sites console > /content/tcs-corp/language-masters/en > open a page in Universal Editor
> - Reason unavailable: No AEM author access in the documentation program (access blocker AB-01)
> - Owner: Content Lead / AEM Authoring Lead (proposed)
> - Target completion date: To be confirmed

10. Known limitations

- Universal Editor screenshots are placeholders: no author access in this program.

11. Open items

- None.

12. Change history

Version	Date	Author	Change
1.0	13 November 2026	Delivery team (documentation program)	First version of the role-specific documentation (master documentation prompt), generated from the repository and the published reference pages