TCS CORPORATE WEBSITE

Fragment — Authoring Guide

Role / audience	Authoring — Content authors, content managers, AEM authoring leads
Version	1.0
Status	Draft for review
Owner	Content Lead / AEM Authoring Lead (proposed)
Last validated	2026-11-08
Documents	1
Classification	INTERNAL — classification to be confirmed

Generated from the Markdown sources of docs/handover (branch migrated-page-content-edam); do not edit this PDF.

Contents

Fragment — Authoring Guide
- Where to see it
- For Content Authors
- Authorable Fields
- Screenshot-Based Authoring Steps
- Variations
- Complete Authoring Example
- Content and Asset Guidelines
- Troubleshooting
- Screenshots
- Known limitations
- Open items
- Change history

Fragment — Authoring Guide

Attribute	Value
Document ID	AUT-C-fragment
Audience	Content authors, content managers, AEM authoring leads
Purpose	How to add, fill in and check the Fragment component
Scope	—
Prerequisites	—
Owner	Content Lead / AEM Authoring Lead (proposed)
Approver	Product Owner (to be confirmed)
Version	1.0
Status	Draft for review
Last updated	8 November 2026
Last validated	8 November 2026
Source files	blocks/fragment/README.md, blocks/fragment/_fragment.json
Related documents	—
Related AEM paths	—

1. Where to see it

- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/fragment
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/fragment/fragment-block
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/fragment/fragments
- https://main--tcs-corp--sradha-tcs.aem.live/design-block-master/en/block-library/fragment/fragments/cta-banner

2. For Content Authors

1. **Create the fragment page** in the locale's `references/` (for example `references/cta-banner`) and author its sections and blocks like any page; start its headings at H2.
2. **Publish the fragment page** (Preview for `.aem.page`, Publish for `.aem.live`).
3. **Add the block** to the host page: section (or Columns Container column, or Tab) › Add › **Fragment**.
4. **Open its properties** and pick the fragment page in **Reference** (content picker).
5. **Additional tab** (optional): Anchor ID, Hide block, padding and margin apply to the Fragment block on this page.
6. **Preview** the host page: the fragment's sections appear in the block. To change the content, edit the fragment page, not the host page.
7. **Publish** the host page.
8. **Validate** on the published site: the content shows, images load, headings fit the page's hierarchy, there is one H1.

Minimum required: Reference to a published page. Recommended: one self-contained unit per fragment (one to three sections), one fragment page per locale. Optional: the Additional tab.

3. Authorable Fields

Fragment (`fragment`)

Model `fragment`; template name "Fragment" (the block class AEM renders).

Content tab — Fragment

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Reference	`reference`	aem-content	No	—	—	—	/design-block-master/en/block-library/fragment/fragments/cta-banner

Additional tab — Fragment

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Anchor ID	`classes_anchor`	text	No	—	regExp: ^anchor-[a-z0-9][a-z0-9-]*$; customErrorMsg: Start with anchor-, then lower-case letters, digits and hyphens.	A unique ID of the block on the page, starting with anchor-, e.g. anchor-our-services; link to it with #anchor-our-services. Delivered as a block class.	—
Hide block	`classes_hideblock`	boolean	No	`false`	on / off	Hides the whole block on the page until it is turned off (shown faded in the editor). Delivered as a block class.	—
Padding left	`classes_paddingleft`	select	No	""	Default (""), 0 (none) (`pl-0`), 0.25rem (space-100) (`pl-100`), 0.5rem (space-200) (`pl-200`), 0.75rem (space-300) (`pl-300`), 1rem (space-400) (`pl-400`), 1.25rem (space-500) (`pl-500`), 1.5rem (space-600) (`pl-600`), 2rem (space-800) (`pl-800`), 2.5rem (space-1000) (`pl-1000`), 3rem (space-1200) (`pl-1200`), 4rem (space-1600) (`pl-1600`), 5rem (space-2000) (`pl-2000`), 6rem (space-2400) (`pl-2400`), 7.5rem (space-3000) (`pl-3000`)	Delivered as a block class.	—
Padding right	`classes_paddingright`	select	No	""	Default (""), 0 (none) (`pr-0`), 0.25rem (space-100) (`pr-100`), 0.5rem (space-200) (`pr-200`), 0.75rem (space-300) (`pr-300`), 1rem (space-400) (`pr-400`), 1.25rem (space-500) (`pr-500`), 1.5rem (space-600) (`pr-600`), 2rem (space-800) (`pr-800`), 2.5rem (space-1000) (`pr-1000`), 3rem (space-1200) (`pr-1200`), 4rem (space-1600) (`pr-1600`), 5rem (space-2000) (`pr-2000`), 6rem (space-2400) (`pr-2400`), 7.5rem (space-3000) (`pr-3000`)	Delivered as a block class.	—
Padding top	`classes_paddingtop`	select	No	""	Default (""), 0 (none) (`pt-0`), 0.25rem (space-100) (`pt-100`), 0.5rem (space-200) (`pt-200`), 0.75rem (space-300) (`pt-300`), 1rem (space-400) (`pt-400`), 1.25rem (space-500) (`pt-500`), 1.5rem (space-600) (`pt-600`), 2rem (space-800) (`pt-800`), 2.5rem (space-1000) (`pt-1000`), 3rem (space-1200) (`pt-1200`), 4rem (space-1600) (`pt-1600`), 5rem (space-2000) (`pt-2000`), 6rem (space-2400) (`pt-2400`), 7.5rem (space-3000) (`pt-3000`)	Delivered as a block class.	—
Padding bottom	`classes_paddingbottom`	select	No	""	Default (""), 0 (none) (`pb-0`), 0.25rem (space-100) (`pb-100`), 0.5rem (space-200) (`pb-200`), 0.75rem (space-300) (`pb-300`), 1rem (space-400) (`pb-400`), 1.25rem (space-500) (`pb-500`), 1.5rem (space-600) (`pb-600`), 2rem (space-800) (`pb-800`), 2.5rem (space-1000) (`pb-1000`), 3rem (space-1200) (`pb-1200`), 4rem (space-1600) (`pb-1600`), 5rem (space-2000) (`pb-2000`), 6rem (space-2400) (`pb-2400`), 7.5rem (space-3000) (`pb-3000`)	Delivered as a block class.	—

Field label	Property	Type	Required	Default	Allowed values	Author guidance	Example
Margin left	classes_marginleft	select	No	""	Default (""), 0 (none) (ml-0), 0.25rem (space-100) (ml-100), 0.5rem (space-200) (ml-200), 0.75rem (space-300) (ml-300), 1rem (space-400) (ml-400), 1.25rem (space-500) (ml-500), 1.5rem (space-600) (ml-600), 2rem (space-800) (ml-800), 2.5rem (space-1000) (ml-1000), 3rem (space-1200) (ml-1200), 4rem (space-1600) (ml-1600), 5rem (space-2000) (ml-2000), 6rem (space-2400) (ml-2400), 7.5rem (space-3000) (ml-3000)	Delivered as a block class.	—
Margin right	classes_marginright	select	No	""	Default (""), 0 (none) (mr-0), 0.25rem (space-100) (mr-100), 0.5rem (space-200) (mr-200), 0.75rem (space-300) (mr-300), 1rem (space-400) (mr-400), 1.25rem (space-500) (mr-500), 1.5rem (space-600) (mr-600), 2rem (space-800) (mr-800), 2.5rem (space-1000) (mr-1000), 3rem (space-1200) (mr-1200), 4rem (space-1600) (mr-1600), 5rem (space-2000) (mr-2000), 6rem (space-2400) (mr-2400), 7.5rem (space-3000) (mr-3000)	Delivered as a block class.	—
Margin top	classes_margintop	select	No	""	Default (""), 0 (none) (mt-0), 0.25rem (space-100) (mt-100), 0.5rem (space-200) (mt-200), 0.75rem (space-300) (mt-300), 1rem (space-400) (mt-400), 1.25rem (space-500) (mt-500), 1.5rem (space-600) (mt-600), 2rem (space-800) (mt-800), 2.5rem (space-1000) (mt-1000), 3rem (space-1200) (mt-1200), 4rem (space-1600) (mt-1600), 5rem (space-2000) (mt-2000), 6rem (space-2400) (mt-2400), 7.5rem (space-3000) (mt-3000)	Delivered as a block class.	—
Margin bottom	classes_marginbottom	select	No	""	Default (""), 0 (none) (mb-0), 0.25rem (space-100) (mb-100), 0.5rem (space-200) (mb-200), 0.75rem (space-300) (mb-300), 1rem (space-400) (mb-400), 1.25rem (space-500) (mb-500), 1.5rem (space-600) (mb-600), 2rem (space-800) (mb-800), 2.5rem (space-1000) (mb-1000), 3rem (space-1200) (mb-1200), 4rem (space-1600) (mb-1600), 5rem (space-2000) (mb-2000), 6rem (space-2400) (mb-2400), 7.5rem (space-3000) (mb-3000)	Delivered as a block class.	—

Notes:

- **Reference.** The block reads the first link's `href`, else its text. Only paths starting with `/` (not `//`) are loaded; full URLs and relative paths are ignored. `.html` / `.plain.html` endings are removed and `{path}.plain.html` is fetched (the AEM author path when editing in Universal Editor, the published path on the site). The path isn't localized: pick the page of the same locale.
- **Rendering result.** The block's content is replaced by the fragment's sections (`div.section`), decorated like a page (`decorateMain`: sections with their options, Columns Containers, Tabs, blocks, block options, buttons) and loaded (`loadSections`); images with `./media_` paths are rebased to the fragment page; the fragment's block animations are prepared (`prepareMotion`).
- **No content.** A path that can't load (not published, 404) leaves the authored content (the reference link); in Universal Editor edit mode the block shows the hint "Fragment: choose the page whose content it shows." (placeholder `fragmentEmpty`).
- **Recursion.** A fragment that includes itself, directly or through other fragments, or the page it is on, isn't loaded again; the same fragment twice side by side is fine.
- **Accessibility impact.** The fragment's headings become part of the host page's outline.
- **Data layer impact.** The Fragment block is a component; the fragment's blocks are its children (`parentId`).
- **Legacy mapping.** None.
- **Additional tab.** As every block (AGENTS.md "Additional tab"), without animation fields (the blocks inside keep their own animations); applies to the Fragment block on the host page.

4. Screenshot-Based Authoring Steps

Authoring Step 1: Create and publish the fragment page

```
[Screenshot Placeholder]

File name:
fragment-authoring-step-1.png

Purpose:
The fragment page (references/cta-banner) in Universal Editor with its sections.

Annotations:
A = Default content: H2 and intro
B = Columns Container with three columns
C = Button Block "Contact us"
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Title (H2)	`Talk to our experts`	The fragment starts at H2	Heading in the host page outline
B	Columns Container	Consulting, Cloud, Cybersecurity columns	Shared content	Columns in every host page
C	Button Block	`Contact us`	Shared call to action	Same CTA everywhere

Values from `block-library/fragment/fragments/cta-banner`. Author action: create the page, author, publish. Business rule: the fragment page must be published before the host page shows it. Validation: open `{path}.plain.html` on the site. Common mistake: an H1 in the fragment (two H1 on the page).

Authoring Step 2: Add the Fragment block

```
[Screenshot Placeholder]

File name:
fragment-authoring-step-2.png

Purpose:
The host page with the Add menu of a section and Fragment highlighted.

Annotations:
A = Section of the host page
B = Fragment in the component list
```

Values to Enter

Callout	Field	Value	Reason	Expected result
B	Component	Fragment	Includes the shared page	Empty block with the editor hint

Expected preview: "Fragment: choose the page whose content it shows." until a Reference is set. Common mistake: adding it in the first section of the page (slower LCP).

Authoring Step 3: Choose the Reference

```
[Screenshot Placeholder]

File name:
fragment-authoring-step-3.png
```

```
Purpose:
The Fragment properties, Content tab, with Reference picked.

Annotations:
A = Reference
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Reference	`/language-masters/en/block-library/fragment/fragments/cta-banner`	The shared page	The banner renders in the block

Business rule: only site paths are loaded (no full URLs). Validation: the content shows in the editor preview. Common mistake: a page of another locale (wrong language).

Authoring Step 4: Additional tab and publish

```
[Screenshot Placeholder]

File name:
fragment-authoring-step-4.png

Purpose:
The Additional tab of the Fragment with an Anchor ID and a margin.

Annotations:
A = Anchor ID
B = Margin top
```

Values to Enter

Callout	Field	Value	Reason	Expected result
A	Anchor ID	`anchor-g01b-fragment` (library sample)	Jump target	`id` on the block
B	Margin top	Default	Spacing comes from the fragment's sections	No extra space

Expected published result: the banner on the published host page. Validation: `#anchor-g01b-fragment` jumps to it. Common mistake: publishing only the host page.

5. Variations

Fragment block (default)

- **Purpose:** include one page's sections.
- **When to use / not:** shared content; not for page-specific or SEO-critical content.
- **Required fields:** Reference. **Optional:** Additional tab.
- **Rendering:** `div.fragment.block` containing the fragment's `div.section`s; no styles of its own (`fragment.css` is empty).
- **Desktop / tablet / mobile:** as the included sections and blocks.
- **Accessibility:** the included content's semantics.
- **Data layer:** `fragment-{n}` (or its Anchor ID) with the inner blocks as children.
- **Personalization / fallback:** none; an unpublished fragment leaves the reference link.

```
[Screenshot Placeholder]
```

```
File name:
fragment-block-desktop.png

Purpose:
A host page with the included CTA banner at 1440px.

Annotations:
A = Fragment block boundary
B = Included Columns Container
```

Nested fragments

- **Purpose:** a fragment page that itself contains a Fragment (or a Tabs block with tab fragments).
- **Rendering:** the inner fragment loads while the outer one is decorated; the chain of including fragments (`main[data-fragment-chain]`) stops a fragment from including itself or the host page.
- **Performance:** each level adds a sequential request.

```
[Screenshot Placeholder]

File name:
fragment-nested-desktop.png

Purpose:
A fragment containing another fragment, both rendered once.

Annotations:
A = Outer fragment
B = Inner fragment
```

Shared loader (header, footer, tabs, modal)

- **Purpose:** the same `loadFragment` loads the Navigation page (`blocks/header`), the footer page and its Canvas page (`blocks/footer`), a tab's Fragment (`blocks/tabs`, passing the tab row as `from`) and modal content (`blocks/modal`).
- **Rendering:** the caller places the decorated sections; see each block's README.

```
[Screenshot Placeholder]

File name:
fragment-in-tab-desktop.png

Purpose:
A Tabs block panel showing a tab fragment.

Annotations:
A = Tab
B = Panel with the fragment's content
```

6. Complete Authoring Example

Scenario: a "Talk to our experts" banner reused on the Consulting page.

Field	Example value	Guidance
Fragment page	`/content/tcs-corp/us/en/references/cta-banner`	In the locale's `references/`
Fragment page content	H2 `Talk to our experts`, intro, Columns Container (Consulting, Cloud, Cybersecurity, each with an "Explore …" Button Block), Button Block `Contact us`	Self-contained, starts at H2

Field	Example value	Guidance
Host page › Fragment › Reference	`/content/tcs-corp/us/en/references/cta-banner`	Same locale
Additional › Anchor ID	`anchor-contact`	Optional

Steps: author and publish the fragment page, add the Fragment to the host page, pick the Reference, publish the host page.

Expected output: the banner between the host page's sections. Responsive: the Columns Container's own behaviour. Accessibility: H2 / H3 inside the page's outline. Analytics: clicks on the banner's buttons report their Button Blocks (children of the fragment component); clicks on default-content links report the fragment. Personalization fallback: none.

Pre-publish checklist:

- [ ] Fragment page published and in the same locale.
- [ ] No H1 or Page Header in the fragment.
- [ ] The fragment doesn't include the host page or itself.
- [ ] Not in the page's first section.

7. Content and Asset Guidelines

- **Titles.** Start at H2; keep the fragment's outline valid in every host page.
- **CTAs and links.** Generic enough for every host page.
- **Images.** Select them with the image picker on the fragment page; `./media_` paths are rebased to the fragment page.
- **Tags and metadata.** Not used from the fragment page; give it a clear title for authors.
- **Min / max items.** No verified technical limit was identified.
- **Loading.** Fetched when the block's section loads; images load as their blocks define.
- **Missing assets / page.** An unpublished fragment page leaves the reference link on the page.

8. Troubleshooting

Symptom	Likely cause	Diagnostic steps	Resolution	Verification
The block shows a bare link	Fragment page not published (404) or a full URL	Network: `{path}.plain.html` status; the Reference value	Publish the page; pick it with the content picker	Content renders
Broken images in the fragment	Unpublished assets or non-`./media_` paths	Inspect `img src`	Re-select images on the fragment page and republish	Images load
Wrong language	Reference to another locale	Check the path's locale	Point to the locale's fragment page	Right language
Old content	Fragment page not republished, cache	Open its `.plain.html`	Publish the fragment page	New content
Two H1	H1 or Page Header in the fragment	Heading outline	Use H2	One H1
Fragment missing on one page only	It references that page itself (guard)	Compare Reference and host path	Reference another page	Content renders

Evidence to collect: host page URL, Reference value, network status of the `.plain.html` request, console errors, screenshot. No cookies or tokens.

9. Screenshots




Figure: Fragment as published (block library) — desktop 1440 × 900 (/design-block-master/en/block-library/fragment/fragment-block, captured 2026-11-08).




Figure: Fragment as published (block library) — mobile 375 × 812 (/design-block-master/en/block-library/fragment/fragment-block, captured 2026-11-08).

> **Screenshot required**
>
> - Required screen: Fragment dialog in Universal Editor (every tab, including Additional)
> - Required role/access: AEM Sites author with Universal Editor (content author)

> - Required navigation steps: AEM Sites console > /content/tcs-corp/language-masters/en > open a page in Universal Editor
> - Reason unavailable: No AEM author access in the documentation program (access blocker AB-01)
> - Owner: Content Lead / AEM Authoring Lead (proposed)
> - Target completion date: To be confirmed

10. Known limitations

- Universal Editor screenshots are placeholders: no author access in this program.

11. Open items

- None.

12. Change history

Version	Date	Author	Change
1.0	8 November 2026	Delivery team (documentation program)	First version of the role-specific documentation (master documentation prompt), generated from the repository and the published reference pages