# 네트워크

#### ■ GRE 터널링

- 물리적인 인터넷망을 쓰기 때문에 물리회선이 연결되어야 한다.

### 1. 가상 터널 만들기

인터페이스 번호가 같아야 하는것은 아니다.

R1(config)#interface tunnel 1

R1(config-if)#

\*Mar 1 00:11:56.411: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to down

R1(config-if)#ip add 172.16.10.1 255.255.255.252

R1(config-if)#no sh //해도 되지만 켜지지는 않는다. => 상대방이랑 연결되면 자동으로 켜 진다.

R1(config-if)#tunnel source serial 0/0 //외부 IP를 적어도 된다.

R1(config-if)#tunnel destination 10.10.20.1 //도착지는 네트워크가 연결된 외부 IP다. up이 안되면 라우팅 문제이다.

\*Mar 1 00:14:51.107: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel1, changed state to up

R1#show interfaces tunnel 1

Tunnel1 is up, line protocol is up

Hardware is Tunnel

Internet address is 172.16.10.1/30

MTU 1514 bytes, BW 9 Kbit/sec, DLY 500000 usec, reliability 255/255, txload 1/255, rxload 1/255

Encapsulation TUNNEL, loopback not set

Keepalive not set

Tunnel source 10.10.10.1 (SerialO/0), destination 10.10.20.1

Tunnel protocol/transport GRE/IP

Key disabled, sequencing disabled

Checksumming of packets disabled

Tunnel TTL 255

Fast tunneling enabled

Tunnel transmit bandwidth 8000 (kbps)

Tunnel receive bandwidth 8000 (kbps)

Last input never, output never, output hang never

Last clearing of "show interface" counters never

Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0

Queueing strategy: fifo

Output queue: 0/0 (size/max)

5 minute input rate 0 bits/sec, 0 packets/sec

5 minute output rate 0 bits/sec, 0 packets/sec

O packets input, O bytes, O no buffer

Received 0 broadcasts, 0 runts, 0 giants, 0 throttles

O input errors, O CRC, O frame, O overrun, O ignored, O abort

O packets output, O bytes, O underruns

O output errors, O collisions, O interface resets

O unknown protocol drops

O output buffer failures, O output buffers swapped out

### R3(config-if)#interface tunnel 3

\*Mar 1 00:16:15.243: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel3, changed state to down

R3(config-if)#ip add 172.16.10.2 255.255.255.252

R3(config-if)#tunnel source s0/1

R3(config-if)#tunnel destination 10.10.10.1

\*Mar 1 00:16:41.691: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnel3, changed state to up

## 2. GRE 내부라우팅(172, 192 경로만 설정)

R1(config)#router ospf 1

R1(config-router)#network 192.168.10.0 0.0.0.255 area 0

R1(config-router)#network 172.16.10.0 0.0.0.3 area 0

R3(config)#router ospf 3

R3(config-router)#network 172.16.10.0 0.0.0.3 area 0

R3(config-router)#network 192.168.20.0 0.0.0.255 area 0