


Lecture 1 - Introduction


Operating Systems 1

Warsaw University of Technology - Faculty of Mathematics and Information Science

There's no clear definition of the Operating System



Layers of the computer system





Users are running and using various programs running on the system


Programs are using services and interfaces exposed by the operating system

Operating system uses available hardware resources directly to do what is asked by the programs

Hardware resources managed by the OS



Hardware resources managed by the OS



Logical resources managed by the OS


Users, user groups, credentials, permissions

Files, file attributes

Clocks, timers

System configuration

...




Executing just a single task at a time is fairly simple for the OS (and wasteful)

A task might not need all the hardware

It may need to wait for I/O like:



- user input
- incoming network data
- data from a slow HDD



Allowing to run multiple tasks concurrently raises multiple issues


multiprogramming

There might be more tasks
than available CPUs!




the OS has to provide job scheduling

There might not be enough memory
for all tasks




the OS has to provide main memory management

Tasks might try to share resources,
in a conflicting way




the OS has to protect all shared resources and provide
a set of safe system calls to access them


Users request multiple tasks - it's up to the OS how to execute them



In batch mode jobs are queued and executed one-by-one




In an on-line system (also multitasking/timesharing) , the OS switches between tasks running concurrently creating interactive computing



The OS must be able to take the CPU from a running task and assign it to some other task
preemption


In a real time system, there exists an upper bound on the system's reaction time to an external event



This mode is desired in mission-critical applications, i. e. in the transportation industry.


Implementing such requires many restrictions. The OS must be aware of the precise characteristics of the running tasks - what resources would they ever need. This is unpredictable for a general purpose operating system.

In a time sharing system tasks do share a single CPU core.
This is a resource which requires protection!



How to do that considering how simple CPU is?

The CPU instruction cycle



1. read next instruction from memory

I got 5 bytes: b8 04 00 00 00

2. figure out what those bytes mean

Okay, 0xb8 means move next byte (0x04) to the register EAX

3. do what the instruction said to do

Configure the internal CPU buses, registers, switches, execute many small substeps ending with EAX = 4


- (4.) increment the Instruction Pointer (IP register)

This is all hardcoded in hardware!


It's what both OS code and user code only can do!

We need a way to execute something else from time to time.

CPUs have such a mechanism - the interrupts!



Each CPU has an Interrupt Controller attached which triggers the mode switch




OS code configures the timer to fire an interrupt in a few milliseconds with a special instruction before jumping to the user code.

The IC can enable, disable, queue and prioritize multiple interrupts occurring at the same time and deliver them to the CPU one-by-one.

Upon receiving an interrupt the CPU automatically:


1. saves the Instruction Pointer on the stack
2. sets the IP to the address of the first instruction of the interrupt handler code



How does the CPU know the address of the interrupt handler?


At a fixed address specified by the CPU the system (OS) keeps a table of interrupt handler addresses
- the interrupt vector!

```
No Addr Source Interrupt Definition
1 0x0000 RESET External pin, Power-on Reset
2 0x0002 INT0 External Interrupt Request 0
3 0x0004 INT1 External Interrupt Request 1
4 0x0006 INT2 External Interrupt Request 2
5 0x0008 INT3 External Interrupt Request 3
6 0x000A INT4 External Interrupt Request 4
7 0x000C INT5 External Interrupt Request 5
8 0x000E INT6 External Interrupt Request 6
8 0x0010 INT7 External Interrupt Request 7
9 0x0012 PCINT0 Pin Change Interrupt Request 0
10 0x0014 PCINT1 Pin Change Interrupt Request 1
11 0x0016 PCINT2 Pin Change Interrupt Request 2
12 0x0018 WDT Watchdog Time-out Interrupt
13 0x001A TIMER2_COMPA Timer/Counter2 Compare Match A
14 0x001C TIMER2_COMPB Timer/Counter2 Compare Match B
...
```




Interrupt handler code does not need to resume the interrupted program.

This is where OS can decide to resume some other task - do a context switch!




In a time-sharing system a userspace program cannot access any shared system resource directly.
It must do so via a system call!



How to disallow anything for the user code then?


We need a Mode Bit!



A single bit stored within the CPU core, set to 1 when running the OS code.

When $MB = 0$ some instructions are disallowed - in hardware.


A single bit stored within the CPU core, set to 1 when running the OS code.



How a program can enter the kernel mode then?

It triggers a software interrupt!

```
int main() {  
    exit(0);  
}  
  
_start:  
    mov eax, 0x1  
    mov ebx, 0  
    int 0x80
```



jump to interrupt
handler no. 128
and
set mode bit = 0

inspect eax to
determine syscall
type

validate params
and execute OS-
provided exit()
implementation

done by CPU automatically

the actual Operating System code running with MB = 0

The Linux syscall table

<https://filippo.io/linux-syscall-table/>

> man 2 syscalls

```
%rax Name Manual Entry point
0 read read(2) sys_read
1 write write(2) sys_write
2 open open(2) sys_open
3 close close(2) sys_close
4 stat stat(2) sys_newstat
5 fstat fstat(2) sys_newfstat
6 lstat lstat(2) sys_newlstat
7 poll poll(2) sys_poll
8 lseek lseek(2) sys_lseek
9 mmap mmap(2) sys_ksys_mmap_pgoff
...
...
```

There 456 distinct syscalls in Linux 6.7 kernel! - and we're gonna learn just a few