```
ply(e[i], n), r === !1) break
                  if (r = t.apply(e[i], n), r === 11) break
    } else if (a) {
        for (; o > i; i++)
             if (r = t.call(e[i], i, e[i]), r === !1) break
    } else
        for (i in e)
             if (r = t.call(e[i], i, e[i]), r === !1) break;
    return e
trim: b && !b.call("\ufeff\u00a0") ? function(e) {
    return null == e ? "" : b.call(e)
} : function(e) {
    return null == e ? "" : (e + "").rep
     rray: function(e, t) {
                                                    PARALLEL SOFTWARE
                                                    Dr. Steve Petruzza
                                                   Reference material for part of this presentation:
                                                   An Introduction to Parallel Programming by Peter Pacheco
                                                                                         UtahStateUniversity
                                                   Copyright © 2010, Elsevier Inc. All rights Reserved
```

### The burden is on software

- Hardware and compilers can keep up the pace needed.
- From now on...
  - In shared memory programs:
    - Start a single process and fork threads.
    - Threads carry out tasks.
  - In distributed memory programs:
    - Start multiple processes.
    - Processes carry out tasks.

## SPMD – single program multiple data

■ A SPMD programs consists of a single executable that can behave as if it were multiple different programs through the use of conditional branches.

```
if (I'm thread process i)
do this;
else
do that;
```

## Writing Parallel Programs

- Divide the work among the processes/threads
  - (a) so each process/thread gets roughly the same amount of work
  - (b) and communication is minimized.

double x[n], y[n];

• • •

- 2. Arrange for the processes/threads to synchronize.
- 3. Arrange for communication among processes/threads.

## **Shared Memory**

#### Dynamic threads

- Master thread waits for work, forks new threads, and when threads are done, they terminate
- Efficient use of resources, but thread creation and termination is time consuming.

#### Static threads

- Pool of threads created and are allocated work, but do not terminate until cleanup.
- Better performance, but potential waste of system resources.

## Nondeterminism

```
printf ("Thread %d > my_val = %d\n",
        my_rank, my_x);
                           Thread 0 > my val = 7
                           Thread 1 > my \ val = 19
```

Thread 1 > my\_val = 19 Thread 0 > my\_val = 7

See code example

## Nondeterminism

```
my_val = Compute_val ( my_rank );
x += my_val;
```

Time	Core 0	Core 1		
0	Finish assignment to my_val	In call to Compute_val		
1	Load $x = 0$ into register	Finish assignment to my_val		
2	Load my_val = 7 into register	Load $x = 0$ into register		
3	Add my_val = 7 to x	Load my_val = 19 into register		
4	Store $x = 7$	Add my_val to x		
5	Start other work	Store $x = 19$		

### Nondeterminism

- Race condition
- Critical section
- Mutually exclusive
- Mutual exclusion lock (mutex, or simply lock)

```
my_val = Compute_val ( my_rank );
Lock(&add_my_val_lock );
x += my_val;
Unlock(&add_my_val_lock );
```

## busy-waiting

```
my_val = Compute_val ( my_rank );
i f ( my_rank == 1)
  whi l e (! ok_for_l ); /* Busy-wait loop */
x += my_val; /* Critical section */
i f ( my_rank == 0)
  ok_for_l = true; /* Let thread l update x */
```

## Approaches to distributed memory access

- Message passing
- Partitioned Global Address Space (PGAS)

## message-passing

```
char message [100];
my_rank = Get_rank();
i f ( my_rank == 1) {
  sprintf (message, "Greetings from process 1");
   Send (message, MSG_CHAR, 100, 0);
\} elseif (my_rank == 0) {
   Receive (message, MSG_CHAR, 100, 1);
   printf ("Process 0 > \text{Received: } \% \text{s} \", message);
```

# Partitioned Global Address Space Languages

```
shared int n = \dots:
shared double x [n], y [n];
private int i , my_first_element , my_last_element ;
my_first_element = \dots;
my_last_element = \dots;
/ * Initialize x and y */
. . .
f or (i = my_first_element; i <= my_last_element; i++)
  x[i] += y[i];
```

## Input and Output

- In distributed memory programs, **only process 0** will access **stdin**. In shared memory programs, only the master thread or thread 0 will access **stdin**.
- In both distributed memory and shared memory programs all the processes/threads can access *stdout* and *stderr*.

## Input and Output

- However, because of the indeterminacy of the order of output to *stdout*, in most cases only a single process/thread will be used for all output to *stdout* other than debugging output.
- Debug output should always include the rank or id of the process/thread that's generating the output.



## Speedup

- Number of cores = p
- Serial run-time = T<sub>serial</sub>
- Parallel run-time = T<sub>parallel</sub>

$$_{iin}ear speedup$$
 $T_{parallel} = T_{serial} / p$ 

## Speedup of a parallel program

$$S = \frac{T_{\text{serial}}}{T_{\text{paralle}}}$$

## Efficiency of a parallel program

$$E = \frac{S}{p} = \frac{T_{parallel}}{T_{parallel}} = \frac{T_{serial}}{p \cdot T_{parallel}}$$

# Speedups and efficiencies of a parallel program

No Raight Cor. Jack

Speedup matrix vector multiplication

	Order of Matrix						
comm_sz	1024	2048	4096	8192	16,384		
1	1.0	1.0	1.0	1.0	1.0		
2	1.8	1.9	1.9	1.9	2.0 2		
4	2.1	3.1	3.6	3.9	3.9 <b>식</b>		
8	2.4	4.8	6.5	7.5	7.9		
16	2.4	6.2	10.8	14.2	15.5 📏		


Jan Cah

#### Speed up and efficiency

p	1	2	4	8	16	approach
S	1.0	1.9	3.6	6.5	10.8	A) John
E = S/p	1.0	0.95	0.90	0.81	0.68	

Why does the Speedy Po Met extrated by the Ethern's increasing

Because the working Per throbs Proportional




Consider Fallities Unless of time

---


# Speedups and efficiencies of parallel program on different problem sizes

	p	1	2	4	8	16
Half	S	1.0	1.9	3.1	4.8	6.2
	E	1.0	0.95	0.78	0.60	0.39
Original	S	1.0	1.9	3.6	6.5	10.8
	E	1.0	0.95	0.90	0.81	0.68
Double	S	1.0	1.9	3.9	7.5	14.2
	$\boldsymbol{E}$	1.0	0.95	0.98	0.94	0.89

## Speedup




## Efficiency



## Effect of overhead


$$T_{parallel} = T_{serial} / p + T_{overhead}$$

## **Execution time**



Which one has better performance?

## Throughput/bandwidth performance



Which one has better performance?

## Amdahl's Law

Unless virtually all of a serial program is parallelized, the possible speedup is going to be very limited — regardless of the number of cores available.

Example, can we parallelize this serial program?

$$a = x + y$$

$$c = b + a$$

$$d = c + a$$

## Example

- We can parallelize 90% of a serial program.
- Parallelization is "perfect" regardless of the number of cores *p* we use.
- $T_{\text{serial}} = 20 \text{ seconds}$
- Runtime of parallelizable part is

$$0.9 \times T_{\text{serial}} / p = 18 / p$$

## Example (cont.)

■ Runtime of "unparallelizable" part is

$$0.1 \times T_{\text{serial}} = 2$$

Overall parallel run-time is

$$T_{parallel} = 0.9 \text{ x } T_{serial} / p + 0.1 \text{ x } T_{serial} = 18 / p + 2$$

## Example (cont.)


Speed up


$$S = \frac{T_{\text{serial}}}{0.9 \text{ x T}_{\text{serial}} / \text{ p + 0.1 x T}_{\text{serial}}} = \frac{20}{18 / \text{ p + 2}}$$

## Scalability

- In general, a problem is scalable if it can handle ever increasing problem sizes.
- If we increase the number of processes/threads and keep the efficiency fixed without increasing problem size, the problem is strongly scalable.
- If we keep the efficiency fixed by increasing the problem size at the same rate as we increase the number of processes/threads, the problem is weakly scalable.

## Weak and strong scalability, which is which? (assuming both scale well)





Α

B

## Taking Timings

- What is the run-time of a program?
- Start to finish?
- A program segment of interest?
- CPU time? (*clock*() function, does not include the time when the program was idle)
- Wall clock time? (beginning to end of execution)
- time linux command:
  - real: wall clock time
  - user: code running in user mode
  - sys: code running in kernel mode (e.g., file I/O, start process)

## Taking Timings

```
theoretical
double start, finish;
function

start = Get_current_time();
/* Code that we want to time */
...
finish = Get_current_time();
printf("The elapsed time = %e seconds\n", finish-start);
```

MPI\_Wtime

omp get wtime

## Taking Timings in a parallel environment

```
private double start, finish;
. . .
start = Get_current_time();
/* Code that we want to time */
. . .
finish = Get_current_time();
printf("The elapsed time = %e seconds\n", finish-start);
```

## Taking Timings in a parallel environment

```
shared double global_elapsed;
private double my_start, my_finish, my_elapsed;
/* Synchronize all processes/threads */
Barrier();
my_start = Get_current_time();
/* Code that we want to time */
. . .
my_finish = Get_current_time();
my_elapsed = my_finish - my_start;
/* Find the max across all processes/threads */
global_elapsed = Global_max(my_elapsed);
if (my_rank == 0)
   printf("The elapsed time = %e seconds\n", global_elapsed);
```

## Superlinear speed-up

- Is it possible?
- Yes.

Because of: caching, particular memory hit patterns, search algorithms



# PARALLEL PROGRAM DESIGN

1. Partitioning: divide the computation to be performed and the data operated on by the computation into small tasks.

The focus here should be on identifying tasks that can be executed in parallel.

2. Communication: determine what communication needs to be carried out among the tasks identified in the previous step.

3. Agglomeration or aggregation: combine tasks and communications identified in the first step into larger tasks.


For example, if task A must be executed before task B can be executed, it may make sense to aggregate them into a single composite task.

4. Mapping: assign the composite tasks identified in the previous step to processes/threads.

This should be done so that communication is minimized, and each process/thread gets roughly the same amount of work.

## Example - histogram

■ 1.3,2.9,0.4,0.3,1.3,4.4,1.7,0.4,3.2,0.3,4.9,2.4,3.1,4.4,3.9,0.4,4.2,4.5,4.9,0.9




## Serial program - input

- 1. The number of measurements: data\_count
- 2. An array of data\_count floats: data
- 3. The minimum value for the bin containing the smallest values: min\_meas
- 4. The maximum value for the bin containing the largest values: max\_meas
- 5. The number of bins: bin\_count


## Serial program - output

- 1. bin\_maxes : an array of bin\_count floats
- 2. bin\_counts : an array of bin\_count ints

## First two stages of Foster's Methodology



## Alternative definition of tasks and communication



Each core updates its local bins (arrays)

## Adding the local arrays

