Properties of spin operators

In formulating NRQED for general spin particles, we need to consider all the possible operators might show up in the Lagrangian. The state-space of a spin-s particle is the direct product of its spin-state and all the other state information. Because the spaces are orthogonal, we can treat separately operators in the two spaces. The operators and fields which exist in position space are the same for a particle of any spin, but unsurpsingly the operators allowed in spin space do depend upon the spin of the particle. As the spin of the particle is increased, and thus its spin degrees of freedom rise, there are more ways to mix these components, and thus a greater number of spin operators to consider.

For a particular representation, we can always write a bilinear as the spin operators and other operators acting between two spinors:

$$\Psi^{\dagger} \mathcal{O}_S \mathcal{O}_X \Psi \tag{0.0.1}$$

The two types of operators will always commute, since they act on orthogonal spaces, so it doesn't matter what order they're written in. All such bilinears must be Galilean invariant, but individual operators might not be. The non-spin operators we consider, such as \mathbf{D} , \mathbf{B} or contractions with the tensor ϵ_{ijk} are already all written as 3-vectors or (in combination) as higher rank tensors. Therefore, it will be most convenient to write spin-operators with well defined properties under Galilean transformations. In that way, writing Galilean-invariant combinations of the two types of operators is done just by contracting indices.

Even though the number of spin operators does depend upon the spin of the particle, it is still possible to proceed in such a way that the same notation may be used no matter the spin. There are a few requirements:

- We write all high spin operators in terms of combinations of S_i , since these have universal properties regardless of the representation they are written in.
- If an operator exists and is non-zero in the representation of spin-s, it also exists in spin-s+1

• All operators introduced to account for the additional degrees of freedom in higher spin representations vanish when written in a lower spin theory. (As an example of the last point, the operator $S_iS_j + S_jS_i - \delta_{ij}S^2$ is needed to account for the degrees of freedom in a spin-1 theory, but vanishes in spin-1/2.)

If these requirements are met a consistent spin-agnostic notation can be adopted. Now we attempt to construct operators that meet these conditions.

The spinors Ψ are written with 2s+1 independent components. The spin operators will be isomorphic to matrices acting on these components, which for a spin-s particle would be $(2s+1)\times(2s+1)$ matrices. The combined operator $\mathcal{O}_S\mathcal{O}_X$ must be Hermitian, but without loss of generality we can require any \mathcal{O}_S , \mathcal{O}_X to be Hermitian separately. So there is the additional constraint that these matrices be Hermitian, and this means a total of $(2s+1)^2$ degrees of freedom.

For spin-0 there is only one component to the spinor, so the only possible operator is equivalent to the identity.

For spin-1/2 we have, in addition to the identity, the spin matrices $s_i = \frac{1}{2}\sigma_i$. This is a set of four independent matrices, and since the space has $(2s+1)^2 = 4$ degrees of freedom, exactly spans the space of all spin-operators. If we try to construct terms which are bilinear in spin matrices, they just reduce through the identity $\sigma_i \sigma_j = \delta_{ij} + \epsilon_{ijk} \sigma_k$, which we can already construct through combinations of the four operators we already have. Since those four operators form a basis for the space, independent bilinears were forbidden even without an explicit form for the equation.

What about spin-1? We need 9 independent operators to span the space. All the operators that exist in spin-1/2 will work here as well, though the spin matrices will have a different representation. That leaves 5 operators to construct. It is natural to try to construct these from bilinear combinations of spin matrices. Naively S_iS_j would itself be 9 independent structures, but clearly some of these are expressible in terms of the lower order operators. (By the order of a spin operator we mean its greatest degree in S_i)

Regardless of their representation, the spin operators always fulfill certain identities

based on their Lie group. Namely

$$S_i S_j \delta_{ij} \sim I, \ [S_i, S_j] = \epsilon_{ijk} S_k \tag{0.0.2}$$

and it is these identities which allow certain combinations of S_iS_j to be related to lower order operators.

If instead of general spin bilinears we consider only combinations which are

- Symmetric in i, j
- Traceless

then such a structure will be independent of the set of operators $\{I, S_1, S_2, S_3\}$. Because it is symmetric no combination may be related using the commutator, and because it is traceless there is no combination that reduces due to the other identity.

This conditions form a set of 4 constraints, so from the original 9 degrees of freedom possessed by combinations of S_iS_j are left only 5. Together with the 4 lower order operators this is exactly enough to span the space.

We can explicitly write this symmetric, traceless structure as

$$S_i S_j + S_j S_i - \frac{2}{3} \delta_{ij} S^2 \tag{0.0.3}$$

Having explored how the procedure works for spin-1, move on to consider the general spin case. The idea is to proceed inductively using the same rough attack as for the case of spin-1. In addition to all the "lower order" operators which were used for lower spin representations introduce new operators which are of higher degree in the spin matrices and guaranteed to be independent of the lower spin operators.

So suppose that for a spin-s-1 particle we have a set of operators written as \bar{S}^0 , \bar{S}^1 ... $\bar{S}^{(s-1)}$, where a structure \bar{S}^n carries n Galilean indices and is symmetric and traceless between any pair of indices, that is:

$$\bar{S}_{..i..j..}^{n} = \bar{S}_{..j..i..}^{n}, \ \delta_{ij}\bar{S}_{..i..j..}^{n} = 0$$
(0.0.4)

(From above, $\bar{S}^0 = I$, $\bar{S}_i^1 = S_i$, and $\bar{S}^2 = S_i S_j + S_j S_i - \frac{2}{3} \delta_{ij} S^2$.)

The objects \bar{S}^n are built as follows: start with all combinations involving the product of exactly n spin matrices. (There are 3^n such structures.) Form them into combinations which are symmetric in all indices. Each index has three possible values, so we can label each structure by how many indices are equal to 1 and 2. If a is the number of indices equal to 1, and b the number of indices equal to 2, then for a given a there are n+1-a possible choices for b. The total number of symmetric structures is then

$$\sum_{a=0}^{n} (n-a+1) = \frac{1}{2}(n+1)(n+2)$$
 (0.0.5)

We want to apply the additional constraint that the \bar{S}^n be traceless in all indices. This will involve subtracting all the lower order structures which result when the trace of the completely symmetric combinations is taken.

It introduces an additional constraint on \overline{S}^n for each pair of indices, and there are n(n-1)/2 distinct pairs of indices. The total degrees of freedom left are

$$\frac{1}{2}(n+1)(n+2) - \frac{1}{2}n(n-1) = \frac{1}{2}(n^2 + 3n + 2 - n^2 + n) = 2n + 1$$
 (0.0.6)

In combination with the lower order spin operators, this is exactly the number of independent operators we need to span the space. Combined with the lower order operators this is a complete basis, so we know we haven't missed any terms. Because they are constructed to be independent from all the lower order operators, it must necessarily be true that they will vanish in lower spin representations.

Using this notation we can write down terms in the Lagrangian that are valid for particles of any spin. By writing all spin operators in terms of S_i they are representation agnostic, and by construction they will vanish for low spin particles where they do not "fit".

