



# Create bootable MacOS USB installer from Windows


- Download and install TransMac. <https://www.acutesystems.com/tmsetup.zip>
- Run TransMac and select "Settings" from the "Tools" menu.
- Make sure "Show hidden and system files" is selected.




- Download a version of MacOS installer from the Apple site: <https://support.apple.com/en-us/102662#browser>  
Your choices are: *Sierra 10.12, El Capitan 10.11, Yosemite 10.10, Mountain Lion 10.8, Lion 10.7*
- Open the installer dmg in TransMac. Click on the dmg in the left pane and click the next folder.
- You will see a file called "**InstallOS.pkg**" or "**InstallMacOSX.pkg**" in the right pane. Right-click this file and select "**Copy to**". Save the file to a folder on your PC.




- Rename the file with a ".dmg" extension (**InstallMacOSX.pkg.dmg**).
- Open this file in TransMac. Click on the dmg file and click the next folder.
- You should see files and folders in the right pane including a "**BaseSystem.dmg**" file and "**Packages**" folder. Right click these two items and "**Copy to**" to copy to your PC.




- Close TransMac and attach your USB drive. Run TransMac as Administrator by right-clicking its icon and select "Run as Administrator".
- Your drive should show in the left pane. Right-click the USB drive and select "**Restore with Disk Image**".




- Make sure you want to restore this drive. Existing data will be overwritten. Click OK.
- Select the "**BaseSystem.dmg**" file you saved before by clicking the button in the edit box and click OK.




- The next window has an "**Enlarge volume to drive size**" checkbox. Select that box. Click OK to start the restore. This may take some time depending on the speed of the USB drive.




- After restore is done, click the drive in the left pane and click the next folder. Find "System" in the left pane and click it, then click "Installation".
- You should see a "Packages" file in the right pane. This is a broken link to the "Packages" folder we saved before. Delete the "Packages" file by right-clicking and selecting "Delete".



- Right-click the right pane and select "Copy Here". Select the "Packages" folder you copied before. This copy may take a while depending on the speed of the USB drive.





- Close TransMac and eject the USB drive. You should now have a working bootable MacOS installation USB drive.
- Put the drive in your Mac and power on while holding the Alt/Option key.
- Your Mac may have trouble booting from a MacOS version that is too old or too new. Try a different version if you run into trouble.