

Post Graduate Program in DevOps

Source: https://kubernetes.io/docs/





Caltech Center for Technology & Management Education

CKA - Certified Kubernetes Administrator



Storage

Learning Objectives

By the end of this lesson, you will be able to:

- Discuss Storage in Kubernetes
- State the different types of Volumes
- Present an overview of Storage Classes
- Discuss Dynamic Volume Provisioning
- List the different types of Ephemeral Volumes




Overview of Storage in Kubernetes

Persistent Storage

Kubernetes gained importance as a method for hosting microservice-based processes and data storage owing to its Persistent Storage.

Users can create databases and access them too. This can also be done for data for various applications.

By using StorageClass, administrators can assign "classes" of various storage-to-map service quality levels.








Kubernetes and Persistent Storage

Kubernetes helps in Persistent Storage as it does not have any association with volatile Containers.

Information cannot be shared among applications of a wheelhouse if there is deletion of localized data.

Applications need to remain functional and be in their unaltered state.



Kubernetes helps to store data outside the Container, where it can be assessed without interruption.





Requirements for Persistent Storage

Container



Data to put in the Container, in that location

Place to persistently store information





Backend

Kubernetes Persistent Storage hides the data from applications and the users. It includes protocols such as NFS, iSCSI, and SMB.



Storage services and systems on cloud providers give more people access to user information.




Third-party cloud storage builds environments where users have full access to data, which they can integrate.



Storage providers such as Amazon S3 or LINBIT offer a selection of tools and applications, and help in Persistent Storage.









Overview

Kubernetes Volume Abstraction helps business-critical applications running in Containers solve problems.







Background

A Pod can have several simultaneous Volumes and Volume types while using Kubernetes. Volumes cannot have higher positions over other Volumes or be connected with hard links to other Volumes.



A Volume's lifespan is greater than any Container running within the Pod. Data preservation is done across the Container.



For a Volume's use, it should be specified to provide for the Pod in .spec.volumes and it should declare the Containers for mounting those Volumes in .spec.containers[*].volumeMounts.



Types of Volumes

Kubernetes supports many types of Volumes:

awsElasticBlockStor e

azureDisk

azureFile

cephfs

cinder

configMap

downwardAPI

emptyDir

fibre channel

gcePersistentDisk


glusterfs

hostPath





Types of Volumes



scaleIO (deprecated)


storageOS

vsphereVolume



awsElasticBlockStore

awsElasticBlockStore Volume is a part of the Amazon Web Services (AWS) EBS Volume.







azureDisk

Microsoft's Azure Data Disk gets mounted onto a pod with azureDisk Volume type.





cephfs

A cephfs Volume allows the mounting of an existing cephfs Volume to your Pod.



A cephfs Volume is unmounted and its contents are preserved.



cephfs Volume can be prepopulated with data.



Multiple writers can simultaneously mount onto a cephfs Volume.





configMap

ConfigMaps are used to inject configuration data into Pods.

It is possible to configure the path that is to be used for a specific entry in the configMap.

Data that is stored in a configMap can be referenced in a Volume of type **configMap.** It can then be consumed by a pod's containerized applications.





emptyDir

An emptyDir volume gets made when a Pod is assigned to a Node. It exists for the duration that the Pod runs on that Node.

Uses of emptyDir:



Scratch space, e.g., a disk-based merge sort



Checkpointing a long computation for recovery from crashes



Holding files fetched by a content-manager Container while data is served by a web server Container





gcePersistentDisk and iscsi

A **gcePersistentDisk** Volume is used to mount a Google Compute Engine (GCE) Persistent Disk (PD) onto the Pod.

An **iscsi** Volume allows an existing iSCSI (SCSI over IP) Volume to be mounted onto the Pod.

Persistent disks can be populated in advance with data. It is possible to share this data between Pods.

Iscsi can be mounted as read-only simultaneously by multiple consumers.



nfs and secret



An existing NFS (Network File System) share can be mounted onto a Pod using an nfs Volume.




Sensitive information, such as passwords, can be passed to Pods using a secret Volume.



storageOS

An existing storageOS volume can be mounted onto a Pod using a storageOS volume. StorageOS runs as a Container with Kubernetes environment, and results in local or attached storage being accessible from any Node within the Kubernetes Cluster.


StorageOS can be used to replicate data and create protection against node failure.



StorageOS provides
block storage to
Containers accessible
from a file system.








Introduction

Users and administrators get an API from the PersistentVolume sub-system in the Kubernetes orchestration system. This API abstracts storage related details.


Kubernetes technology introduces two new API resources:





Life cycle of Volume and Claim

The life cycle of interaction between PVs and PVCs:








Types of Persistent Volumes


Some of the non-deprecated plugins that Kubernetes currently supports are:







Types of Persistent Volumes



Spec for Persistent Volumes

Capacity

Volume Mode

Access Mode

Class

Reclaim Policy

Mount Options

Node Affinity

Phase




Persistent Volumes

Each PersistentVolume (PV) contains a spec and status — the Volume's specification and status.

```
Kind: PersistantVolume
  name: pv0003
  volumeMode: Filesystem
    - ReadWrireOnce
  persistentVolemReclainPolicy: Recycle
  storeageClassName: slow
    - hard
    - nfsvers=4.1
     path; /tmp
     server: 172.17.0.2
```



Spec for PersistentVolumeClaim





PersistentVolumeClaim

Each PersistentVolumeClaim (PVC) contains a spec and status — the Claim's specification and status.

```
apiVersion: v1
  Kind: PersistentVolumeClaim
   name: myclaim
      - ReadWriteOnce
                 Folesystem
        stoage: Bgi
    storageClassName : slow
        relase: " stable"
environment, operator : In, values:[dev]}
```







Claim as Volumes

Pods access storage by utilizing Claims as Volumes.

Claims must remain in the same namespace as the Pod that uses the Claim.



Clusters use the Claim in the Pod's namespace to get the PersistentVolume that backs the Claim.







Raw Block Volume Support

Raw block materials are supported by these Volume plugins:

AWSElasticBlockStore AzureDisk CSI FC (Fibre Channel)

GCEPersistentDisk iSCSI Local volume OpenStack Cinder

RBD (Ceph Block Device)

VsphereVolume





PersistentVolume Using a Raw Block Volume

Here is how to configure a PersistentVolume that uses a Raw Block Volume for an accessMode of ReadWriteOnce:

```
apiVersion: v1
Kind: PersistentVolume
  name; block-pv
     storage:10Gi
     - ReaderWriteOnce
  volumeMode: Block
  persistentVolumeclaimPolicy: Retain
                     { "50060e801049cfd1"}
     lun: 0
     rreadOnly: false
```



PersistentVolumeClaim Requesting a Raw Block Volume

Given below is how a PersistentVolumeClaim that requests for a Raw Block Volume for an accessMode of ReadWriteOnce may be configured:

```
apiVersion: v1
      PersistentVolumeClaim
  name: block-pvc
      - ReadWriteOnce
  volumeMode: Block
         storage: 10Gi
```





Pod Specification Adding Raw Block Device Path in Container

```
apiVersion: v1
Kind: Pod
  name : pod-with-block-volume
    - name: fc-container
      image: fedora:26
     Command: ["/bin/sh", " -c"]
      args: [ " tall -f /dev/null" ]
                  data
           devicesaPath: /dev/xvda
      - name; data
            claimName: block-pvc
```



©Simplilearn. All rights reserved.

Binding Block Volumes

PV volumeMode	PVC volumeMode	Result
Unspecified	Unspecified	BIND
Unspecified	Block	NO BIND
Unspecified	Filesystem	BIND
Unspecified	Unspecified	NO BIND
Block	Block	BIND
Block	Filesystem	NO BIND
Filesystem	Filesystem	BIND
Filesystem	Block	NO BIND
Filesystem	Unspecified	BIND





Assisted Practice

Understanding the Working of Persistent Volumes

Duration: 10 mins

Problem Statement:

Understand the working of Persistent Volumes in Kubernetes.



Assisted Practice: Guidelines

Steps to demonstrate Persistent Volumes in Kubernetes:

- 1. Create a basic PersistentVolume
- 2. Create a PersistentVolumeClaim
- 3. Create a Pod using PersistentVolumeClaim





OSimplilearn. All rights reserved.

Introduction

VolumeSnapshotContent and VolumeSnapshot API resources enable the creation of Volume Snapshots for users and administrators.

A VolumeSnapshotContent is a snapshot originating from a Volume in the Cluster that has been provisioned by an administrator.

A VolumeSnapshot is a user's request for a snapshot of a Volume. This snapshot is similar to a PersistentVolumeClaim.

The VolumeSnapshotClass allows the specification of different attributes of a VolumeSnapshot.





Simplilearn. All rights reserved.

Lifecycle of VolumeSnapshot and VolumeSnapshot Content

Provision VolumeSnapshot

A snapshot can be preprovisioned or dynamically provisioned. Creation of Preprovisioned VolumeSnapshot Content

A Cluster administrator creates several VolumeSnapshotContents.

Dynamic use of VolumeSnapshot

The VolumeSnapshotClass specifies storage provider-specific parameters to use when taking a snapshot.

Deletion of a VolumeSnapshot

Deletion is caused by deleting the VolumeSnapshot object.
After deletion, the DeletionPolicy will be followed.

PersistentVolumeClaim

This is done to ensure that in-use
PersistentVolumeClaim API objects are not removed from the system while a snapshot is being taken.

Binding VolumeSnapshot Object

The Snapshot Controller handles the binding of a VolumeSnapshot object with an appropriate VolumeSnapshotContent object.





Volume Snapshots

A spec and a status are parts of a VolumeSnapshot.

```
Demo
apiVersion: snapshot.storage.k8s.io/v1
       VolumeSNnapshot-
           new-snapshot-test
   volumeSnapshotClassName: csi-hostpath-snapclass
       persistentVolumeClaimName: pvc-test
```



Volume Snapshots

The volumeSnapshotContentName source field is required for pre-provisioned snapshots.

```
Demo
            snapshor.storage.k8s.io/v1
      VolumeSnapshot
           test-snapshot
       volumeSnapshotContentName: test-contest
```



VolumeSnapshot Contents

In Dynamic Provisioning, the Snapshot Common Controller creates a VolumeSnapshotContent object.

```
apiVersion: snapshor.storage.k8s.io/v1
       VolumeSnapshot
 name: snapcontent- 72d9a349-aacd-42d2-a248-d77560d2455
 deletionPolicy: Delete
 driver: hostpath.csi.k8s.io
     volumeHandle: ee0cfb94-f8d4-11e9-b2d8-0242ac1110002
 volumeSnapshotClassName: csi-hostpath-snapclass
     name: new-snapshot-test
     namespace: default
     vid: 72d9a349-aacd-42d2-a240-d775650d2455
```





VolumeSnapshot Contents

For pre-provisioned snapshots, the Cluster Administrator creates the VolumeSnapshotContent object.

```
apiVersion: snapshor.storage.k8s.io/v1
          VolumeSnapshot
            new-snapshot-content-test
      deletionPolicy: Delete
      driver: hostpath.csi.k8s.io
          snapshotHandle: 7bdd0de3-aaeb-9aae-
0242ac110002
          name: new-snapshot-test
          namespace: default
```





OSimplilearn. All rights reserved.

Provisioning Volumes from Snapshots



New volume, populated in advance with data from a snapshot, can be provisioned with a datasource field in the Persistentvolumeclaim.



Assisted Practice

Understanding the Working of Volume Snapshots

Duration: 10 mins

Problem Statement:

Understand the working of Volume Snapshots.




Assisted Practice: Guidelines

Steps to demonstrate Volume Snapshots in Kubernetes:

- 1. Clone the VolumeSnapshot from the existing PersistentVolumeClaim
- 2. Create a VolumeSnapshot configuration file
- 3. Create the resource
- 4. View the PersistentVolumeClaim





OSimplilearn. All rights reserved.

Introduction

The CSI Volume Cloning feature adds support for specifying existing PVCs in the dataSource field. This indicates that a user wants to clone a Volume.



A Clone is defined as a duplicate of an existing Kubernetes Volume that can be consumed like any standard Volume.



From the perspective of the Kubernetes API, cloning adds the ability to specify an existing PVC as a dataSource during new PVC creation.





Provisioning

Clones are provisioned like any other PVC except that a dataSource that references an existing PVC in the same namespace is added.

```
apiVersion: v1
Kind: PersistentVolumeClaim
  name: clone-of-pvc-1
  namespace: myns
      - ReadWriteOnce
 storageClassName: cloning
         storage: 5Gi
     kind: PersistentVolumeClaim
     name: pvc-1
```






Simplilearn. All rights reserved.

Usage of PVC

When a new PVC is available, the cloned PVC is consumed like any other PVC.







Assisted Practice

Understanding CSI Volume Cloning

Duration: 10 mins

Problem Statement:

Learn how to clone a CSI volume in Kubernetes.




Assisted Practice: Guidelines

Steps to demonstrate CSI Volume Cloning in Kubernetes:

- 1. Create a cloned PersistentVolume
- 2. Create a VolumeSnapshot configuration file
- 3. Create the resource
- 4. View the Volume
- 5. View the PersistentVolumeClaim





Simplilearn. All rights reserved.

Introduction

A StorageClass is used by administrators to describe the "classes" of storage that they offer.



Kubernetes has no opinion about what classes represent.



StorageClass Resource

A StorageClass helps administrators describe various storage classes. Administrators can specify a default StorageClass for PVCs that are not bound to a particular class.

```
apiVersion: storage.k8s.io/v1
       StorageClass
 name: standard
provisioner: kubernetes.io/aws-ebc
 type: gp2
reclaimPolicy: Retain
allowVolumeExpamsion: true
       - debug
volumeBindingMode: Immediate
```





OSimplilearn. All rights reserved.


Provisioner

Each StorageClass has a Provisioner that determines what Volume plugin is used for provisioning PVs.

Authors of external Provisioners have full discretion over how their code lives:









©Simplilearn. All rights reserved.

StorageClass Resource: Fields

Reclaim Policy

Persistent Volumes created dynamically by a StorageClass will have the Reclaim Policy specifics mentioned in the Reclaim Policy field of the class. It can be either Delete or Retain.

Volume Expansion

Configuration of Persistent Volumes can make them expandable.

Mount Options

Persistent Volumes that are dynamically created by a StorageClass will have the mount options specified in the mount Options field of the class.

Volume Binding Mode

Volume Binding Mode controls when Volume Binding and Dynamic Provisioning should occur.





Allowed Topologies

When the WaitForFirstConsumer Volume Binding Mode is specified by a Cluster operator, provisioning to specific topologies need not be restricted. The code snippet below demonstrates the manner of restriction of topology of provisioned Volumes to specific zones:

```
apiVersion: storage.k8s.io/v1
Kind: StorageClass
Metadata"
    name: standard
provisioner: kubernetes.io/gce-pd
parameters:
    type: pd-standard
volumeBindingMode: WaitForFirstCustomer
allowedTopologies:
    -matchLabelExpressions:
    - key; failure-domain.beta.kubernetes.io/zone
    values
    - vs-central-a
    - vs- central-b
```






Simplilearn. All rights reserved.

Parameters

Storage classes have parameters that describe Volumes belonging to the StorageClass. A maximum of 512 parameters may be defined for a StorageClass.

The Provisioners include the following providers:








©Simplilearn. All rights reserved.

Parameters



Assisted Practice

Understanding Storage Classes

Duration: 10 mins

Problem Statement:

Understand the working of Storage Classes in Kubernetes.




Assisted Practice: Guidelines

Steps to demonstrate Storage Classes in Kubernetes:

- 1. Create a StorageClass
- 2. Create the resource
- 3. View the StorageClass







Simplilearn. All rights reserved.

Introduction

VolumeSnapshotClass can be used to describe the "classes" of storage when provisioning a VolumeSnapshot.



VolumeSnapshot Class Resource

Each VolumeSnapshotClass has fields for driver, Deletion Policy, and parameters.

Name and other parameters of a class can be finalized during the creation of VolumeSnapshotClass objects. Updating is not possible after creation.

```
apiVersion: snapshor.storage.k8s.io/v1
Kind: VolumeSnapshot
Metadata"
   name: csi-hostpath-snapclass
   driver: hostpath.csi.k8s.io
   deletionPolicy: Delete
   parameters
```





VolumeSnapshot Class Resource

Default VolumeSnapshotClass can be specified for VolumeSnapshots that do not request any particular class to bind by adding the snapshot.storage.kubernetes.io/is-default-class: "true" annotation, as can be seen in the snippet below:

```
apiVersion: snapshor.storage.k8s.io/v1
Kind: VolumeSnapshot
Metadata"
name: csi-hostpath-snapclass
annotations:
snapshot.storage.kubernetes.io/is-default-class: "true"
driver: hostpath.csi.k8s.io
deletionPolicy: Delete
parameters
```





Simplilearn. All rights reserved.

VolumeSnapshot Class Resource

Driver

VolumeSnapshot classes have a driver to determine which CSI Volume plugin is used for provisioning VolumeSnapshots.

Deletion Policy

It enables configuration of a VolumeSnapshotContent when the VolumeSnapshot object it is bound to is to be deleted.



OSimplilearn. All rights reserved.

Parameters

VolumeSnapshot classes have parameters, which describe Volume Snapshots that belong to them.

Different parameters may be accepted, depending on the driver.



Assisted Practice

Understanding VolumeSnapshot Classes

Duration: 10 mins

Problem Statement:

Understand the working of Volume Snapshots classes in Kubernetes.



Assisted Practice: Guidelines

Steps to demonstrate VolumeSnapshot Classes in Kubernetes:

- 1. Create a VolumeSnapshot class
- 2. Create the configuration
- 3. Create the resource
- 4. View the VolumeSnapshot classes




Dynamic Volume Provisioning

Overview

Dynamic Volume Provisioning allows Storage Volumes to be created on-demand.

A Cluster Administrator can define StorageClass objects as per the need.

The dynamic provisioning feature does away with the need for Cluster Administrators to provision storage in advance.



Automatic storage provision is done upon user request.





Enabling Dynamic Provisioning

To enable Dynamic Provisioning, a Cluster Administrator needs to create, in advance, one or more StorageClass objects.

Here are two storage classes being created: provisions standard disk-like persistent disks and SSD-like persistent disks.

```
apiVersion: storage.k8s.io/v1
Kind: StorageClass
Metadata"
   name: slow
provisioner: kubernetes.io/gce-pd
parameters:
   type: pd-standard
```

```
apiVersion: storage.k8s.io/v1
Kind: StorageClass
Metadata"
    name: fast
provisioner: kubernetes.io/gce-pd
parameters:
    type: pd-ssd
```





Usage of Dynamic Provisioning

Before Kubernetes v1.6, volume.beta.kubernetes.io/storage-class annotation was used. For "fast" StorageClass, a user would create the PersistentVolumeClaim as shown here:


```
apiVersion: v1
Kind: PersistentVolumeClaim
Metadata:
   name: claim1
Spec:
   accessModes:
   - ReadWriteOnce
   storageClassName: fast
   resources:
    requests:
        storage: 30Gi
```





Defaulting Behavior

This is how a Cluster administrator enables Defaulting Behavior.



Ensuring that the Default StorageClass Admission Controller is enabled on the API server





Topology Awareness

In Multi-zone Clusters, Pods can be spread across Zones in a Region.



Single-zone storage backends should be provisioned in the Zones where Pods are scheduled.





Assisted Practice

Understanding the Working of Dynamic Volume Provisioning

Duration: 10 mins

Problem Statement:

Understanding the working of dynamic volume provisioning in Kubernetes.




Assisted Practice: Guidelines

Steps to demonstrate Dynamic Volume Provisioning in Kubernetes:

- 1. Enable Dynamic Provisioning in StorageClass
- 2. Use Dynamic Provisioning in PersistentVolumeClaim







Storage Capacity

Storage Capacity is limited and may vary, depending on the Node on which a Pod runs.




Tracking Storage Capacity is supported for Container Storage Interface (CSI) drivers and should to be enabled when a CSI driver is installed.





API

There are two API extensions for this feature:









Criteria Scheduling

Scenarios when Storage Capacity information is used by the Kubernetes Scheduler:



The CSIStorageCapacity feature gate is true



A Pod uses a Volume that has not been created



Volume uses a StorageClass which references a CSI driver and uses WaitForFirstConsumer Volume Binding Mode



The CSIDriver object for the driver has StorageCapacity is set to true





Scheduling

It compares the size of the volume against the capacity listed in CSI Storage Capacity objects with a topology that includes the Node.

For Volumes with Immediate Volume Binding Mode, the Volume creation location is decided by the Storage Driver.

For CSI Ephemeral Volumes, scheduling does not take Storage Capacity into consideration.



Rescheduling

After a Node is selected for a Pod with WaitForFirstConsumer Volumes, the CSI Storage Driver is asked to create the Volume with a specification that the Volume should be available on the selected Node.

Storage Capacity tracking increases the chance of scheduling working on the first try.


When a Pod uses multiple volumes, scheduling can fail permanently.





Enable Storage Capacity Tracking

Storage Capacity tracking is an alpha feature. It functions only when the CSIStorageCapacity feature gate and the storage.k8s.io/v1alpha1 API groups are enabled. The code snippet given here may be used to list CSIStorageCapacity objects.







Assisted Practice

Tracking Storage Capacity

Duration: 5 mins

Problem Statement:

Learn how to track the storage capacity in Kubernetes.




Assisted Practice: Guidelines

Steps to demonstrate Storage Capacity in Kubernetes:

- 1. Track storage capacity
- 2. Type kubectl get csistoragecapacities -A







Overview

Caching services often have limited memory size. They can shift infrequently-used data into Storage.


Ephemeral Volumes are designed for specific use cases.

They are specified inline in the Pod spec. This makes application deployment and management simple.





Types of Ephemeral Volumes



Third-party CSI Storage Drivers must provide Ephemeral Volumes.





Ephemeral Volumes

Third-party CSI Storage Drivers and other Storage Drivers that support Dynamic Provisioning may provide Generic Ephemeral Volumes.

Third-party drivers offer some functionality that is not supported by Kubernetes.

Some CSI drivers are written specifically for CSI Ephemeral Volumes and do not support Dynamic Provisioning.



They cannot be used for Generic Ephemeral Volumes.





CSI Ephemeral Volumes

CSI Ephemeral Volumes are managed locally on each Node. They are created along with other local resources after a Pod is scheduled on a Node. Here is an example manifest for a Pod that uses CSI Ephemeral Storage:

```
Kind: Pod
apiVersion: v1
name: my-csi-app
  Containers: kubernetes.io/gce-pd
    - name: my-frontend
      image: busybox
        - mountPath: "/data"
          name: my-csi-inline-vol
      command: [ "sleep","1000000" ]
   - name: my-csi-inline-vol
       driver: inline.storage.kubernetes.io
        foo: bar
```





Generic Ephemeral Volumes

Generic Ephemeral Volumes are just like emptyDir volumes. Here is a manifest of a Generic Ephemeral Volume:

```
Pod
apiVersion: v1
name: my-app
 - name: my-frontend
      image: busybox
        - mountPath: "/scratch"
          name: scratch-volume
      command: [ "sleep","1000000" ]
   - name: scratch-volume
```

```
type: my-frontend-volume
             spec: inline.storage.kubernetes.io
               accessModes: [ "ReadWriteOnce" ]
               storageClassName: "scratch-storage-
class"
                    Storage: 1Gib
```






Life cycle and PersistentVolumeClaim

The key design idea is that the parameters for a Volume Claim are allowed inside a Volume source of the Pod.

In terms of resource ownership, a Pod that has Generic Ephemeral Storage is the owner of the PersistentVolumeClaim(s) that provide(s) the Ephemeral Storage.



The Kubernetes Garbage
Collector deletes the PVC
when the Pod is deleted. This
action triggers deletion of the
Volume. The default Reclaim
Policy of Storage Classes is to
delete Volumes.





PersistentVolumeClaim Naming

Names of the automatically created PVCs are a combination of Pod name and Volume name, joined with a hyphen (-).

PVC is used for an Ephemeral Volume only if it was created for the Pod.

The deterministic naming could result in a potential conflict between Pods, and between Pods and manually created PVCs.



Security

Enabling the GenericEphemeralVolume feature allows users to create PVCs indirectly if they can create Pods, even if they do not have permission to create PVCs directly.

Two choices, if this does not fit the security model, are:

Explicitly disable the feature through the feature gate



Assisted Practice

Understanding Ephemeral Volumes

Duration: 5 mins

Problem Statement:

Understand the working of Ephemeral Volumes in Kubernetes.



Assisted Practice: Guidelines

Steps to demonstrate Ephemeral Volumes in Kubernetes:

- 1. Create a Pod for CSI Ephemeral Volumes
- 2. Create the configuration
- 3. Create the resource
- 4. View the VolumeSnapshot classes




Node-Specific Volume Limits

©Simplilearn. All rights reserved.

Introduction

Cloud providers like Google, Amazon, and Microsoft typically have a limit on how many Volumes can be attached to a Node.





Kubernetes Default Limits

The Kubernetes Scheduler has default limits on the number of Volumes that can be attached to a Node.

Cloud service	Maximum Volumes per Node
Amazon Elastic Block Store (EBS)	39
Google Persistent Disk	16
Microsoft Azure Disk Storage	16



Custom Limits

Limits can be changed by setting the value of the KUBE_MAX_PD_VOLS environment variable, and then starting the Scheduler.




Use caution if you set a limit that is higher than the default limit.



Dynamic Volume Limits

Dynamic Volume Limits are supported for the following:





Assisted Practice

Understanding the Working of Node-specific Volume Limits

Duration: 5 mins

Problem Statement:

Understanding the working of Node-specific volume limits in Kubernetes.



Assisted Practice: Guidelines

Steps to demonstrate Node-Specific Volume Limits in Kubernetes:

- 1. Create a persistent disk
- 2. Click Disks under Compute Engine
- 3. View the disk in the list





Key Takeaways

- A Pod can use any number of Volumes and Volume types simultaneously while working with Kubernetes.
- A StorageClass provides a way for administrators to describe the "classes" of storage that they offer.
- The CSI Volume Cloning feature adds support for specifying existing PVCs in the dataSource field to indicate that a user would like to clone a Volume.
- Tracking Storage Capacity is supported for Container Storage Interface (CSI) drivers and needs to be enabled when installing a CSI driver.



