Jeffrey Woo

MSDS, University of Virginia

2 Worked Example

Choosing Number of PCs

PCA is a dimension reduction method, as it seeks to produce a low(er)-dimensional representation of the data.

- Take a large set of correlated variables and replace them with a smaller number of (uncorrelated) variables that collectively can explain most of the variability in the variables.
- The uncorrelated variables are the principal components (PCs), which are directions in the variable space along which the original data are most variable.

PCA seeks a small number of variables that can explain most of the variation in the variables. Each dimension will be a linear combination of the k variables.

#### Finding the first PC

The first PC of a set of variables  $X_1, \dots, X_k$  is the **normalized** linear combination of the variables

$$Z_1 = \phi_{11}X_1 + \phi_{21}X_2 + \dots + \phi_{k1}X_k \tag{1}$$

that has the largest variance, subject to the constraint  $\sum_{j=1}^k \phi_{j1}^2 = 1$ .

#### Finding the First PC

- The elements  $\phi_{11}, \dots, \phi_{k1}$  in (1) are called the **loadings** of the first PC.
- The loadings make up the principal component loading **vector**  $\phi_1 = (\phi_{11}, \phi_{21}, \dots, \phi_{k1})^T$ .

#### Computing the First PC

- Let X denote a n × k set of k variables, where each variable has been centered to have mean 0.
- Look for the linear combination of the variables of the form

$$z_{i1} = \phi_{11}x_{i1} + \phi_{21}x_{i2} + \dots + \phi_{k1}x_{ik}$$
 (2)

for  $i=1,\cdots,n$  that has the largest sample variance, subject to the constraint  $\sum_{j=1}^k \phi_{j1}^2 = 1$ .

- Since the variables are centered,  $z_{i1}$  has mean 0, for any values of  $\phi_{j1}$ .
- Hence, the sample variance of  $z_{i1}$  can be written as  $\frac{1}{n} \sum_{i=1}^{n} z_{i1}^{2}$ .

#### Computing the First PC

Thus, the first principal component loading vector solves the following optimization problem: maximize

$$\frac{1}{n}\sum_{i=1}^{n}\left(\sum_{j=1}^{k}\phi_{j1}x_{ij}\right)^{2}\tag{3}$$

subject to  $\sum_{j=1}^{k} \phi_{j1}^2 = 1$ .

#### Computing the First PC

The optimization problem can be solved using standard techniques in linear algebra (singular-value decomposition).

- $Z_1$  is called the first principal component,
- $z_{11}, \dots, z_{n1}$  are scores of the first PC for each observation.

#### Geometric Interpretation of the First PC

- The loading vector  $\phi_1$  defines a direction in the variable space along which the variables vary the most.
- If we project the *n* observations onto this direction, the projected values are the scores  $z_{11}, \dots, z_{n1}$ .

#### Geometric Interpretation of the First PC




Figure 1: Data Simulated from Bivariate Normal

- The second PC is the linear combination of  $X_1, \dots, X_k$  that has maximum variance among all linear combinations that are **uncorrelated** with  $Z_1$ .
- The 2nd PC takes the form

$$z_{i2} = \phi_{12}x_{i1} + \phi_{22}x_{i2} + \dots + \phi_{k2}x_{ik}$$

where  $\phi_2$  is the second principal component loading vector and  $\sum_{j=1}^k \phi_{j2}^2 = 1$ .

- Constraining Z<sub>2</sub> to be uncorrelated to Z<sub>1</sub> is equivalent to constraining the direction φ<sub>2</sub> to be **orthogonal** to the direction of φ<sub>1</sub>.
- Subsequent PCs are constructed similarly: they are orthogonal to all previous PCs and the sum of the squared loadings equal to 1.
- There are at most min(n-1, k) PCs.

#### Geometric Interpretation of the PCs




Figure 2: Data Simulated from Bivariate Normal

#### Alternate Interpretation of PCs

 The first principal component loading vector has another nice property: it defines the line in a k-dimensional space that is closest to the n observations (using average squared Euclidean distance).

**Question:** Does this sound a little like the least squares criterion in ordinary least squares regression?

#### Geometric Interpretation of the First PC




Figure 3: Data Simulated from Bivariate Normal

#### Practical Considerations

- Each variable should be standardized so they each have mean 0 and standard deviation 1. This is to prevent any variable from dominating the direction of the loading vectors.
- If the variables are measured on the same units, standardizing may not be needed.
- PCA should only be applied to quantitative variables.

Worked Example

Choosing Number of PCs

## Worked Example: Gas Mileage

We will use the mtcars data set that is available in R. The data set contains information about fuel consumption and 10 aspects of automobile design and performance for 32 classic vehicles.

#### Worked Example: Gas Mileage

#### > head(mtcars, 8)

```
mpg cyl disp hp drat wt qsec vs am gear carb
Mazda RX4
                 21.0
                         6 160.0 110 3.90 2.620 16.46
Mazda RX4 Wag
                 21.0
                         6 160.0 110 3.90 2.875 17.02
Datsun 710
                 22.8
                         4 108.0 93 3.85 2.320 18.61
Hornet 4 Drive
                  21.4
                         6 258.0 110 3.08 3.215 19.44
Hornet Sportabout 18.7
                         8 360.0 175 3.15 3.440 17.02
Valiant
                 18.1
                         6 225.0 105 2.76 3.460 20.22
Duster 360
                 14.3
                         8 360.0 245 3.21 3.570 15.84
Merc 240D
                 24.4
                         4 146.7 62 3.69 3.190 20.00
```

am:

# Worked Example: Gas Mileage

```
mpg: Miles/(US) gallon
cyl: Number of cylinders
disp: Displacement (cu.in.)
hp: Gross horsepower
drat: Rear axle ratio
wt: Weight (1000 lbs)
qsec: 1/4 mile time
vs: Engine (0 = V-shaped, 1 = straight)
```

gear: Number of forward gears
carb: Number of carburetors

Transmission (0 = automatic, 1 = manual)

#### Worked Example: mtcars

Below, we have the loadings for the PCs.

```
> round(pr.out$rotation,3)
```

```
PC1
               PC2
                      PC3
                              PC4
                                     PC5
                                            PC6
                                                    PC7
                                                                  PC9
                                                           PC8
     -0.393
             0.028 -0.221 -0.006 -0.321
                                          0.720 - 0.381 - 0.125
                                                                0.115
mpg
cyl
     0.403
             0.016 -0.252
                            0.041
                                   0.117
                                          0.224 - 0.159
                                                                0.163
                                                         0.810
disp 0.397 -0.089 -0.078
                           0.339 -0.487 -0.020 -0.182 -0.064 -0.662
hp
      0.367
             0.269 -0.017
                            0.068 - 0.295
                                          0.354
                                                 0.696 - 0.166
                                                                0.252
drat -0.312
             0.342
                    0.150
                            0.846
                                  0.162 - 0.015
                                                 0.048
                                                         0.135
                                                                0.038
wt.
      0.373 -0.172 0.454
                            0.191 -0.187 -0.084 -0.428 -0.198
                                                                0.569
gsec -0.224 -0.484 0.628 -0.030 -0.148
                                          0.258
                                                 0.276 \quad 0.356 \quad -0.169
gear -0.209
             0.551
                    0.207 -0.282 -0.562 -0.323 -0.086
                                                         0.316
                                                                0.047
carb
      0.245
             0.484
                    0.464 - 0.214 0.400
                                          0.357 - 0.206 - 0.108 - 0.320
```

#### Worked Example: Interpreting Loading Vectors

- The first loading vector places slightly higher weights on mpg, cyl, disp, hp, wt.
- PC1 roughly corresponds to a measure of size of engines.
- The 2nd loading vector places more weight on drat, qsec, gear, carb.
- PC2 roughly corresponds to how powerful a car is.
- Interpreting later PCs is often challenging.

#### Worked Example: Biplot

A biplot displays the principal component scores and principal component loadings.




Figure 4: Biplot of mtcars Data

#### Worked Example: Interpreting Biplot

- The center of the car's name corresponds to the scores of PC1 and PC2 for the car. For example, the Maserati Bora has a score of 2.9 and 4.00 for PC1 and PC2 respectively, indicating a large engine and a powerful car.
- Scores of 0 correspond to the average.
- By contrast, the Valiant has a score of 0.00 and -2.50 for PC1 and PC2 respectively, indicating average size of engine and having small engine power.

#### Worked Example: mtcars

Below, we have the scores for the Valiant and the Maserati Bora

```
> rbind(round(pr.out$x[6,],3), round(pr.out$x[31,],3))

PC1 PC2 PC3 PC4 PC5 PC6 PC7 PC8 PC9

[1,] 0.050 -2.447 0.112 -0.872 -0.126 -0.230 0.225 0.099 -0.004

[2,] 2.963 3.999 0.703 -0.730 -0.228 0.656 0.494 -0.082 -0.053
```

#### Worked Example: Interpreting Biplot

Notice the values on the axes opposite the horizontal and vertical axes. These give the loadings each feature has on PC1 and PC2 respectively.

 For example, the loading of Carb on PC1 and PC2 is about 0.2 and 0.5 respectively (actually 0.245 and 0.484).

2 Worked Example

Choosing Number of PCs

#### Proportion of Variance Explained

Note how each PC is found by finding the linear combination of features that have the largest variance, subject to

- the constraint  $\sum_{j=1}^k \phi_{jm}^2 = 1$  for  $m = 1, 2, \dots, min(n-1, k)$
- every PC being orthogonal to each other.

To evaluate the strength of each PC, we can compute the **proportion of variance** in the variable space that is explained by each PC, called PVE.

#### Proportion of Variance Explained

The total variance in the variable space (assuming variables have been centered to have mean 0) is

$$\sum_{j=1}^{k} Var(X_j) = \sum_{j=1}^{k} \frac{1}{n} \sum_{i=1}^{n} x_{ij}^{2}.$$
 (4)

The variance explained by the mth PC is

$$Var(Z_m) = \frac{1}{n} \sum_{i=1}^{n} z_{im}^2$$
 (5)

#### Proportion of Variance Explained

Therefore, the PVE is just simply (5) divided by (4):

$$PVE(m) = \frac{\sum_{i=1}^{n} z_{im}^{2}}{\sum_{j=1}^{k} \sum_{i=1}^{n} x_{ij}^{2}}$$
(6)

Typically, a scree plot is produced. A scree plot has the PVE on the vertical axis and the number of PCs on the horizontal axis.

## Worked Example




Figure 5: Scree Plot mtcars Data