# CS540 - Chapter 02 - Summary

- CS540 Chapter 02 Summary
  - LAN Switching
    - Ethernet [L2]
      - Definitions
      - Ethernet Frame (802.3 MAC frame) Format
    - Hub, Bridge, Switch
      - Hub
      - Bridge
      - Switch
    - Frame Forwarding Algorithm
    - Misc
  - SPT (Spanning Tree Protocol)
    - Definitions
    - Spanning Tree Algorithm
    - Port States & Timers
    - Misc
  - Virtual LAN
    - Definitions
    - VLAN
      - VLAN Tagging (Trunk) 802.1q

# 1. LAN Switching

# 1.1. Ethernet [L2]

#### 1.1.1. Definitions

 Ethernet (802.3) includes bottom 2 layers: Physical, Data Link Layer (something just the MAC) in OSI Model.


Standard Ethernet: 10 MbpsFast Ethernet: 100 Mbps

Gigabit Ethernet: 1Gbps

Ten-Gigabit Ethernet: 10Gbps


- Ethernet provides connectionless service
  - no handshake
  - no sequence or order
  - o frame has no relation to others
- and thus unreliable service to network layer, no ACK/NAK.

## 1.1.2. Ethernet Frame (802.3 MAC frame) Format



## **Description**

- Frame Structure
  - Preamble: 8 bytes (DIX) or 7 bytes (802.3 frame)
    - SOF/SFD: 1 byte (802.3 frame) of start frame delimiter, 10101011
  - Destination Address / Source Address: 6 bytes (= 48 bits) of MAC address MM:MM:MM:SS:SS:SS



- First 3 bytes specify the vendor, last 3 bytes is unique inside the company.
- Categories:
  - Unicast (1 recipient): 2nd digit is even. Eg: 4A:30:10:21:10:1A
  - Multicast (group of recipients): 2nd digit is odd. Eg: 47:20:1B:2E:08:EE
  - Broadcast (all stations): all 1s or Fs.
- Type or Length (2 bytes)
  - Type: in DIX Ethernet, when its value ≥ 0x600
  - Length: in 802.3 MAC frame,) when its value < 0x600. Indicates number of butes in data field.
- Data: packet content
- Pad: Zeros are added if data length is less than 46 bytes
- FCS: or CRC, check at receiver, if error, discard frame.
- Frame length should be between 64 bytes to 1518 bytes. Otherwise, it will be dropped.
  - Minus off 18 bytes of header and trailer, the data size should be 46 bytes to 1500 bytes.


# 1.2. Hub, Bridge, Switch

### 1.2.1. Hub

- L1 device as it just receives packet and floods it out to all ports except the incoming.
  - Notes: L2 device checks MAC address. L3 device checks IP address.
- Same functionality as a multiport repeater.
- Fast, but no brain and thus causing data collision and wasting bandwidth.

## 1.2.2. Bridge

- L2 device
- Is a hub with an **additional check which side the flooding should go out**. Thus it does records the originator's port (source MAC+port).



• Use broadcast/flood if it does not know where to forward to (usually when it first starts)

### 1.2.3. Switch

- L2 device.
- A <u>multi-ports bridge</u>, it also records the originator's ports (source MAC+port) into the forwarding table for future broadcasting/forwarding.
- Use broadcast/flood if it does not know where to forward to (usually when it first starts)

# 1.3. Frame Forwarding Algorithm

When a frame arrives:

- 1. Record the source MAC address + port into forwarding table.
  - Set the expiry timer.
- 2. Search its forwarding table for the dest MAC address
- 3. If dest MAC address is found, forward to the corresponding port (if port not blocked).
- 4. If NOT, broadcat to all ports (except incoming).

### 1.4. Misc


- Wireless is 802.11
- · Switch modes

- Store and forward: entire frame is received before sent out.
- Cut through: as soon as the dest MAC addr is received, the frame is sent without waiting for entire frame. -> no CRC check (as CRC is in the MAC trailer)

# 2. SPT (Spanning Tree Protocol)

## 2.1. Definitions

- Redundancy design in LAN is good for failover, however it creates loops.
  - Loops cause broadcast storm, multiple frame transmission and inconsistent switch tables.
- So people invtented STP (Spanning Tree Protocol) (IEEE 802.1d), to eliminate loops but still keep redundancy.
- SPT: a tree topology with
  - NO loops
  - NO device left out




· All switches run STP by default.

# 2.2. Spanning Tree Algorithm

- Select & nominate "Root Bridge/Switch". Priority given to lower bridge ID by exchanging BPDUs (Bridge Protocol Data Unit) or by manual configuration.
  - Bridge ID contains priority, VLAN ID, and MAC address
    - Priority ranges [1-65536], default to 32768, change in multiple of 4096.
  - Process
    - BPDU frames (switch BID and root ID) are sent out every 2 seconds when a switch starts. A switch identifies itself as root at first.

- By comparing the BID and Root ID, all bridges come to agreement of the root BID.
- Default MAC address for BPDU is 01:80:C2:00:00:00 (or 01:80:C2::)
- 2. On each bridge/switch (except the root one), select 1 "root port", which has the lowest cost path to the root bridge.
  - Cost is inversely proportional to link speed, i.e. lower cost for faster link speed.
  - If same cost, use port (higher) priority and (lower) port number.
- 3. On each segment (link), select 1 "designated port", which has the lowest cost path to the root bridge.
  - If same cost, use the one with (lower) bridge ID.
- 4. Close down other ports.




### 2.3. Port States & Timers

- Port states in STP: Blocking (closed port), Listening (listen for BPDUs), Learning (learning MAC addresses), Forwarding (in operation), Disabled.
- **Timers**: up to <u>50 secs</u> for a broken link to become alive. Blocking 20 sec, Listening 15 sec, Learning 15 secs.
- Cisco use PortFast to quickly revive a port from blocking to forwarding.

### 2.4. Misc

- Notation F0/0, F0/1 meaning
  - F: media type. F (Fa) is Fast Ethernet, G (Gi) is Gigabit Ethernet, T (Ten) is Ten Gigabit Ethernet.
  - Slot #: the slot number
  - Port #: the port number of the specified slot.



- Initial enhancement of SPT: PVST+: is to separate STP for each VLAN.
- Ultimate enhancement of STP: **RSTP**: faster SPT, same BPDU structure but different port states and timers. Faster to heal (6 seconds).


# 3. Virtual LAN

## 3.1. Definitions

- Broadcast Domain: is a network segment in which any device can transmit data directly to each other without going through a router.
- A router (L3 device) breaks up a broadcast domain.
- A VLAN is a group of hosts with a common set of requirements that communicate as if they were attached to the same broadcast domain regardless of their physical location.
- VLAN = Subnet

### 3.2. **VLAN**

VLAN are assigned on the switch port (port number + VLAN number)




- VLAN assignment:
  - Connect the host to a correct port on the switch.

- Assign the host the correct IP of the VLAN.
- Main benefits of VLAN: Security, Ease of Management. In detail:
  - Security
  - Cost Reduction
  - Higher Performance
  - Broadcast Storm Mitigation
  - Improved IT Staff Efficiency
  - Simpler project or application management
- VLAN number ranges 1-4094 (12 bits)

## 3.2.1. VLAN Tagging (Trunk) 802.1q


Tagging is a technique to allow a single connection between 2 switches to serve multiple VLANs.

### No VLAN Tagging




• (802.1g beader (TAG) is added for the recipient to detect this is a tagging VLAN packet. FCS is also recalculated.

### Original Ethernet Frame



- The recipient switch strips off the header and forwards the packet to the corresponding VLAN.
- The 802.1g header is 4 bytes long:



- Trunk link does not belong to a specific VLAN.
- Native VLAN: is the untagged VLAN on an 802.1q trunked switchport. For any switch, native VLAN is default to VLAN 1.