

IP address map

Authoritative, fully-instantiated device inventory for the whole network — every physical and virtual device, with its real IP. This is the source of truth; other docs reference this file rather than repeating addresses.

Uplink VLANs (Cloud Gateway transit networks — WAN side of each theatre's GL-iNet)

These transit subnets are a proposal — tags and ranges can be changed freely before deployment. They exist purely so each of the 4 physical VLAN groups has a working transit subnet; GL-iNet WAN ports don't need a predictable static address, DHCP is fine, since Tailscale rides over whatever address they get.

VLAN	802.1Q tag	Subnet	Cloud Gateway address	Serves
Uplink 1	101	10.10.1.0/24	10.10.1.1	Theatre 1–3 + VMix Node 1 GL-iNet WAN ports
Uplink 2	102	10.10.2.0/24	10.10.2.1	Theatre 4–6 + VMix Node 2 GL-iNet WAN ports
Uplink 3	103	10.10.3.0/24	10.10.3.1	Theatre 7–9 GL-iNet WAN ports
Uplink 4	104	10.10.4.0/24	10.10.4.1	Theatre 10–12 GL-iNet WAN ports

Mothership LAN — 192.168.1.0/24

Device	IP	Notes
Cloud Gateway (LAN gateway)	192.168.1.1	
Unraid server (host management IP)	192.168.1.2	Tailscale subnet router container shares this IP (host networking)
BirdDog Central	192.168.1.12	Windows VM — the design's only VM (the mothership VMix instance VM at .11 was removed, see docs/open-questions.md #10; .11 is left unassigned)
Nextcloud	192.168.1.13	Docker container, macvlan
Restreamer	192.168.1.14	Docker container, macvlan
NDI Discovery Server	192.168.1.15	Docker container, macvlan, port 5959
DERP server	192.168.1.16	Docker container, macvlan, port 443 + STUN 3478/udp — see docs/tailscale.md
ATEM ISO Ingest	192.168.1.17	Docker container, macvlan — pulls all 12 theatres' ATEM ISO recordings via FTP, see docs/atem-iso-ingest.md
VMix Record Ingest	192.168.1.18	Docker container, macvlan — pulls all 4 VMix PCs' recordings via SMB, see docs/vmix-record-ingest.md
UniFi Controller	192.168.1.19	Docker container, macvlan, port 8443 (UI) + 8080 (device inform) — self-hosted UniFi Network Application, independent of cloud.ui.com
GLKVM-Cloud (rttys)	192.168.1.20	Docker container, macvlan, port 443 (UI) + 5912 (device) + 10443 (WebSocket) — self-hosted remote administration for the 14 GL-iNet routers, see docs/glkvm-cloud.md

Device	IP	Notes
ATEM Overseer	192.168.1.21	Docker container, macvlan — fleet monitoring/tally dashboard for all 12 theatres' ATEMs, receives each theatre's monitoring stream (see <code>docs/bandwidth-analysis.md</code>)
GLKVM-Cloud (<code>coturn</code>)	192.168.1.22	Docker container, macvlan, port 3478 tcp+udp — TURN relay for the above
ATEM Fleet Admin	192.168.1.23	Docker container, macvlan — bulk ATEM provisioning (model-aware config forms → live network apply via <code>atem-connection</code> , or XML+media folder export)
Flock	192.168.1.24	Docker container, macvlan — BirdDog Play fleet manager (LAN discovery, tag-based grouping, BirdUI-parity settings, batch edits); receives each theatre's BirdDog Play preview stream, see <code>docs/bandwidth-analysis.md</code>
Ready Room PC 1	192.168.1.30	
Ready Room PC 2	192.168.1.31	
Ready Room PC 3	192.168.1.32	
Ready Room PC 4	192.168.1.33	

Theatres 1-12

Same 8-device pattern in every theatre; only the subnet octet (X) changes. GL-iNet Slate AX LAN 1 goes directly to the ATEM Mini Extreme ISO, LAN 2 feeds the Netgear switch carrying the rest (including BirdDog Play) — see `docs/topology.md` for the physical wiring.

Theatre 1 — 192.168.2.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.2.1
BirdDog Play	192.168.2.20
ATEM Mini Extreme ISO	192.168.2.2
PowerPoint Main	192.168.2.5
PowerPoint Backup	192.168.2.6
VT Main	192.168.2.7
VT Backup	192.168.2.8
Control laptop	192.168.2.10

Theatre 2 — 192.168.3.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.3.1
BirdDog Play	192.168.3.20
ATEM Mini Extreme ISO	192.168.3.2
PowerPoint Main	192.168.3.5
PowerPoint Backup	192.168.3.6
VT Main	192.168.3.7
VT Backup	192.168.3.8
Control laptop	192.168.3.10

Theatre 3 — 192.168.4.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.4.1
BirdDog Play	192.168.4.20
ATEM Mini Extreme ISO	192.168.4.2
PowerPoint Main	192.168.4.5
PowerPoint Backup	192.168.4.6
VT Main	192.168.4.7
VT Backup	192.168.4.8
Control laptop	192.168.4.10

Theatre 4 — 192.168.5.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.5.1
BirdDog Play	192.168.5.20
ATEM Mini Extreme ISO	192.168.5.2
PowerPoint Main	192.168.5.5
PowerPoint Backup	192.168.5.6
VT Main	192.168.5.7
VT Backup	192.168.5.8
Control laptop	192.168.5.10

Theatre 5 — 192.168.6.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.6.1
BirdDog Play	192.168.6.20
ATEM Mini Extreme ISO	192.168.6.2
PowerPoint Main	192.168.6.5
PowerPoint Backup	192.168.6.6
VT Main	192.168.6.7
VT Backup	192.168.6.8
Control laptop	192.168.6.10

Theatre 6 — 192.168.7.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.7.1
BirdDog Play	192.168.7.20
ATEM Mini Extreme ISO	192.168.7.2
PowerPoint Main	192.168.7.5
PowerPoint Backup	192.168.7.6

Device	IP
VT Main	192.168.7.7
VT Backup	192.168.7.8
Control laptop	192.168.7.10

Theatre 7 — 192.168.8.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.8.1
BirdDog Play	192.168.8.20
ATEM Mini Extreme ISO	192.168.8.2
PowerPoint Main	192.168.8.5
PowerPoint Backup	192.168.8.6
VT Main	192.168.8.7
VT Backup	192.168.8.8
Control laptop	192.168.8.10

Theatre 8 — 192.168.9.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.9.1
BirdDog Play	192.168.9.20
ATEM Mini Extreme ISO	192.168.9.2
PowerPoint Main	192.168.9.5
PowerPoint Backup	192.168.9.6
VT Main	192.168.9.7
VT Backup	192.168.9.8
Control laptop	192.168.9.10

Theatre 9 — 192.168.10.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.10.1
BirdDog Play	192.168.10.20
ATEM Mini Extreme ISO	192.168.10.2
PowerPoint Main	192.168.10.5
PowerPoint Backup	192.168.10.6
VT Main	192.168.10.7
VT Backup	192.168.10.8
Control laptop	192.168.10.10

Theatre 10 — 192.168.11.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.11.1
BirdDog Play	192.168.11.20
ATEM Mini Extreme ISO	192.168.11.2
PowerPoint Main	192.168.11.5
PowerPoint Backup	192.168.11.6
VT Main	192.168.11.7
VT Backup	192.168.11.8
Control laptop	192.168.11.10

Theatre 11 — 192.168.12.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.12.1
BirdDog Play	192.168.12.20
ATEM Mini Extreme ISO	192.168.12.2
PowerPoint Main	192.168.12.5
PowerPoint Backup	192.168.12.6
VT Main	192.168.12.7
VT Backup	192.168.12.8
Control laptop	192.168.12.10

Theatre 12 — 192.168.13.0/24

Device	IP
GL-iNet Slate AX (LAN gateway)	192.168.13.1
BirdDog Play	192.168.13.20
ATEM Mini Extreme ISO	192.168.13.2
PowerPoint Main	192.168.13.5
PowerPoint Backup	192.168.13.6
VT Main	192.168.13.7
VT Backup	192.168.13.8
Control laptop	192.168.13.10

VMix nodes

Each has its own router — GL-iNet Slate AX (GL-AXT1800), same model as the theatre routers — and its own Tailscale connection, not part of the theatre it physically sits next to.

VMix Node 1 — 192.168.20.0/24 (off Theatre 1)

Device	IP
Node 1 router (GL-iNet Slate AX)	192.168.20.1
BirdDog P400 Camera 1	192.168.20.11
BirdDog P400 Camera 2	192.168.20.12
BirdDog P400 Camera 3	192.168.20.13
BirdDog P400 Camera 4	192.168.20.14
VMix PC 1	192.168.20.21
VMix PC 2	192.168.20.22

VMix Node 2 — 192.168.21.0/24 (off Theatre 4)

Device	IP
Node 2 router (GL-iNet Slate AX)	192.168.21.1
BirdDog P400 Camera 1	192.168.21.11
BirdDog P400 Camera 2	192.168.21.12
BirdDog P400 Camera 3	192.168.21.13
BirdDog P400 Camera 4	192.168.21.14
VMix PC 1	192.168.21.21
VMix PC 2	192.168.21.22

Edit suite — 192.168.22.0/24

Post-production subsystem at the mothership — dedicated 10GbE LAN, not part of the Tailscale mesh (same room as the mothership, no reason to route it over the tailnet). See `docs/live-editing.md` for the full design.

Device	IP	Notes
Edit suite NAS	192.168.22.2	Blackmagic Cloud Store or generic 10GbE NAS — see <code>docs/live-editing.md</code> Decision 1
MacBook Pro — Editor 1	192.168.22.11	10GbE via Thunderbolt adapter/dock
MacBook Pro — Editor 2	192.168.22.12	10GbE via Thunderbolt adapter/dock
Mac mini — Project Server + Remote Render	192.168.22.20	Dedicated always-on machine, never an editor's own laptop — see <code>docs/live-editing.md</code> Decision 2

Device count

- Mothership: 19 devices (1 gateway + 1 server host + 1 VM + 12 containers + 4 ready-room PCs)
- Theatres: 12×8 devices = 96
- VMix nodes: 2×7 devices = 14
- Edit suite: 4 devices (NAS + 2 MacBook Pros + Mac mini Project Server/Remote Render node), see `docs/live-editing.md` Decision 2
- **Total: 133 devices** across the network (excluding the 4 uplink VLAN transit addresses, which aren't per-device).