# A sort of potted geometry of three-dimensional space

With a view to the big picture, this is a quick look back at some—but only some—of what is really important for Calculus III. Specifically, it is a kind of catalog of the four possible kinds of object that you can have when objects are distinguished in terms of their dimensionality.

### **Points**

Of the four basic objects, the simplest is a point. It has dimension zero, or no degrees of freedom.\* A generic point has Cartesian coordinates (x, y, z) and hence position vector  $\boldsymbol{\rho} = x\mathbf{i} + y\mathbf{j} + z\mathbf{k}$ . A specific point typically has Cartesian coordinates  $(x_l, y_l, z_l)$  and hence position vector  $\boldsymbol{\rho} = \boldsymbol{\rho}_l = x_l\mathbf{i} + y_l\mathbf{j} + z_l\mathbf{k}$  where the subscript l is used to distinguish different fixed points. (If there is only one point, then we will likely use l = 0; if there are two points, then we may use l = 0 and l = 1 or l = 1 and l = 2, as the whim takes us; and so on.)

### The equation of a point

The equation of a point is very simple. It is just

$$\rho = \rho_0$$

in vector form or  $(x, y, z) = (x_0, y_0, z_0)$  or  $x = x_0, y = y_0, z = z_0$  in terms of components.

#### Curves

A curve—or "space" curve—has dimension one, or one degree of freedom.

#### The vector equation of a curve

As discussed in Lectures 8 and 14, the vector equation of a curve has the form

$$\rho = \rho(t) = x(t)\mathbf{i} + y(t)\mathbf{j} + z(t)\mathbf{k}, \quad t_{\min} \le t \le t_{\max}$$

where t is the parameter with the one degree of freedom to roam between  $t = t_{\min}$  (typically 0) and  $t = t_{\max}$  (not atypically 1). An equivalent component or "parametric" form is

$$x = x(t), y = y(t), z = z(t), t_{\min} \le t \le t_{\max}.$$

#### The scalar equations for a curve

Two surfaces, say those with equations  $\phi_1(x, y, z) = d_l$  for l = 1, 2, typically intersect in a curve, in which case, that curve is equivalently defined by the pair of scalar equations:

$$\phi_1(x, y, z) = d_1, \qquad \phi_2(x, y, z) = d_2.$$

<sup>\*</sup>To be sure, there are infinitely many of them, but that freedom lies entirely in the grand collection or ensemble of them, as opposed to in a point per se.

<sup>†</sup>By analogy with the scalar equations for a curve or surface (see below), you could also in principle implicitly define a point as the intersection of three surfaces that just happen to meet in that point, in which case, the point would have three equations of the form  $\phi_l(x, y, z) = d_l$  for l = 1, 2, 3—but rarely if ever would you want to do this in practice.

## Direction of a curve whose vector equation is known

At the point  $\rho_0 = \rho(t_0) = x(t_0)\mathbf{i} + y(t_0)\mathbf{j} + z(t_0)\mathbf{k}$ , the curve has direction  $\mathbf{T} = \hat{\mathbf{w}}$  where

$$\mathbf{w} = \dot{\boldsymbol{\rho}}(t_0) = \dot{x}(t_0)\mathbf{i} + \dot{y}(t_0)\mathbf{j} + \dot{z}(t_0)\mathbf{k}$$

and an overdot denotes differentiation; see Lecture 14.

#### Direction of a curve whose scalar equations are known

Because a curve of intersection between two surfaces must lie in both surfaces, at the point with position vector  $\boldsymbol{\rho}_0 = x_0 \mathbf{i} + y_0 \mathbf{j} + z_0 \mathbf{k}$  its direction must be parallel to the tangent plane of each surface, and hence must be normal to the normal to each tangent plane.<sup>‡</sup> So the curve has direction  $\hat{\mathbf{w}}$  where

$$\mathbf{w} = \pm \nabla \phi_1 \times \nabla \phi_2$$

(by Lecture 8).

#### The special case of a line

An important special case of a curve is a line. The line through  $\rho_0 = x_0 \mathbf{i} + y_0 \mathbf{j} + z_0 \mathbf{k}$  has vector equation

$$\rho = \rho_0 + t\mathbf{w}, \quad -\infty < t < \infty$$

(Lecture 3). Correspondingly, the line segment between any two points, say those with position vectors  $\boldsymbol{\rho}_1 = \boldsymbol{\rho}_0 + t_1 \mathbf{w}$  and  $\boldsymbol{\rho}_2 = \boldsymbol{\rho}_0 + t_2 \mathbf{w}$ , has vector equation

$$\rho = \rho_0 + t\mathbf{w}, \quad t_1 \le t \le t_2.$$

An equivalent component or "parametric" form is

$$x = x_0 + w_1 t$$
,  $y = y_0 + w_2 t$ ,  $z = z_0 + w_3 t$ ,  $t_1 \le t \le t_2$ 

where  $\mathbf{w} = w_1 \mathbf{i} + w_2 \mathbf{j} = w_3 \mathbf{k}$ .

The line may also be regarded as the intersection of two planes, which are surfaces having equations of the form  $\phi_l(x, y, z) = d_l$  for l = 1, 2, where  $\phi_l(x, y, z) = a_l x + b_l y + c_l z$ . Then the line has scalar equations of the form

$$a_1x + b_1y + c_1z = d_1, \qquad a_2x + b_2y + c_2z = d_2$$

and hence direction  $\hat{\mathbf{w}}$  for  $\mathbf{w} = \pm \nabla \phi_1 \times \nabla \phi_2 = \pm \{a_1 \mathbf{i} + b_1 \mathbf{j} + c_1 \mathbf{k}\} \times \{a_2 \mathbf{i} + b_2 \mathbf{j} + c_2 \mathbf{k}\}.$ 

#### Surfaces

A surface has dimension two, or two degrees of freedom.

<sup>&</sup>lt;sup>‡</sup>Which, don't forget, is also what we mean by the normal to the surface at that point.

## The vector equation of a surface

The vector equation of a surface has the form

$$\boldsymbol{\rho} = \boldsymbol{\rho}(u,v) = x(u,v)\mathbf{i} + y(u,v)\mathbf{j} + z(u,v)\mathbf{k}, \quad u_{\min} \le u \le u_{\max}, \quad v_{\min} \le v \le v_{\max}$$

where u and v are the parameters with the two degrees of freedom, allowing them to roam where  $u_{\min} \leq u \leq u_{\max}$ ,  $v_{\min} \leq v \leq v_{\max}$  (Lecture 17). Possibly either  $u_{\min}$  and  $u_{\max}$  depend on v or  $v_{\min}$  and  $v_{\max}$  depend on v (but not both at the same time), although not atypically  $u_{\min}$ ,  $u_{\max}$ ,  $v_{\min}$  and  $v_{\max}$  are all constant.

### The scalar equation for a surface

The scalar equation of a surface has the form

$$\phi(x, y, z) = d.$$

### Direction of normal to a surface whose vector equation is known

At the point parameterized by u and v, the surface has normal  $\rho_u \times \rho_v$ , hence unit normal

$$\mathbf{n} = \pm \widehat{oldsymbol{
ho}_u imes oldsymbol{
ho}_v} = \pm \frac{oldsymbol{
ho}_u imes oldsymbol{
ho}_v}{|oldsymbol{
ho}_u imes oldsymbol{
ho}_v|}$$

(Lecture 17).

#### Direction of normal to a surface whose whose scalar equation is known

The surface has normal  $\nabla \phi$  (Lecture 8) and hence unit normal

$$\mathbf{n} = \pm \widehat{\nabla \phi} = \pm \frac{\nabla \phi}{|\nabla \phi|}.$$

#### The special case of a triangular region

An important special case of a planar region is a triangular with corners having position vectors  $\mathbf{a}$ ,  $\mathbf{b}$  and  $\mathbf{c}$ , for which

$$\rho = \rho(u, v) = \mathbf{a} + u(\mathbf{b} - \mathbf{a}) + v(\mathbf{c} - \mathbf{b}), \quad 0 \le v \le u, \quad 0 \le u \le 1$$

by Lecture 18. Here  $v_{\text{max}} = u$  depends on u (whereas  $v_{\text{min}} = 0$ ,  $u_{\text{min}} = 0$  and  $u_{\text{max}} = 1$  are constant). Correspondingly,

$$\rho(u, v) = \mathbf{a} + u(\mathbf{b} - \mathbf{a}) + v(\mathbf{c} - \mathbf{b}), \quad 0 < v < 1, \quad 0 < u < 1$$

yields the parallelogram whose corners have position vectors  $\mathbf{a}$ ,  $\mathbf{b}$ ,  $\mathbf{c}$  and  $\mathbf{a} - \mathbf{b} + \mathbf{c}$ , and

$$\rho(u, v) = \mathbf{a} + u(\mathbf{b} - \mathbf{a}) + v(\mathbf{c} - \mathbf{b}), \quad -\infty < v < \infty, \quad -\infty < u < \infty$$

yields the entire plane through the same four points. This surface has normal

$$\mathbf{m} \triangleq \boldsymbol{\rho}_u \times \boldsymbol{\rho}_v = (\mathbf{b} - \mathbf{a}) \times (\mathbf{c} - \mathbf{b}) = \mathbf{a} \times \mathbf{b} + \mathbf{b} \times \mathbf{c} + \mathbf{c} \times \mathbf{a}$$

and hence (by Lecture 4) scalar equation

$$\mathbf{m} \cdot \boldsymbol{\rho} = \mathbf{m} \cdot \mathbf{a} = \mathbf{m} \cdot \mathbf{b} = \mathbf{m} \cdot \mathbf{c}$$

or

$$m_1x + m_2y + m_3z = \mathbf{m} \cdot \mathbf{a} = \mathbf{m} \cdot \mathbf{b} = \mathbf{m} \cdot \mathbf{c}$$

where, of course,  $\rho = \rho = x\mathbf{i} + y\mathbf{j} + z\mathbf{k}$  and  $\mathbf{m} = m_1\mathbf{i} + m_2\mathbf{j} = m_3\mathbf{k}$ . (See "The vector and scalar equations of a plane" under Supplementary Materials.)

## Volumetric regions

A volumetric region  $E^{\S}$ —such as the interior of a sphere, ellipsoid or cylinder—has dimension three, or three degrees of freedom. Such a region has vector equation

$$\boldsymbol{\rho} = \boldsymbol{\rho}(u, v, w) = x(u, v, w)\mathbf{i} + y(u, v, w)\mathbf{j} + z(u, v, w)\mathbf{k},$$
$$u_{\min} \le u \le u_{\max}, \ v_{\min} \le v \le v_{\max}, \ w_{\min} \le w \le w_{\max}$$

where u, v and w are the parameters with the three degrees of freedom, allowing them to roam where  $u_{\min} \leq u \leq u_{\max}$ ,  $v_{\min} \leq v \leq v_{\max}$  and  $w_{\min} \leq w \leq w_{\max}$  (Lectures 12, 13 and 20). Possibly one—but at most one—of the three pairs of coordinate limits (namely,  $u_{\min}$  and  $u_{\max}$ ,  $v_{\min}$  and  $v_{\max}$ ,  $w_{\min}$  and  $w_{\max}$ ) depends on the parameters associated with the other two; and possibly one—but at most one—of the two pairs that remain depends on the parameter associated with the third; but at least one of the three pairs is a pair of constants (and in natural coordinates all six limits may be constant).

Finally, don't forget what the above implies for volume-integral calculation. For the sake of argument, let us suppose that  $w_{\min}$  and  $w_{\max}$  depend upon u and v, and that  $v_{\min}$  and  $v_{\max}$  depend upon u, so that  $v_{\min}$  and  $v_{\max}$  are—of necessity—constant. Then any integral over E must be calculated with w as the innermost variable of integration and v as the outermost. That is, if v is the (trivariate) function to be integrated, then we must calculate

$$\iiint\limits_E f\,dx\,dy\,dz \ = \ \int\limits_{u_{\min}}^{u_{\max}} \int\limits_{v_{\min}}^{v_{\max}} \int\limits_{w_{\min}}^{w_{\max}} |J|\,dw\,dv\,du$$

where

$$J(u, v, w) = (\boldsymbol{\rho}_u \times \boldsymbol{\rho}_v) \cdot \boldsymbol{\rho}_w = \begin{vmatrix} \frac{\partial x}{\partial u} & \frac{\partial y}{\partial u} & \frac{\partial z}{\partial u} \\ \frac{\partial z}{\partial v} & \frac{\partial y}{\partial v} & \frac{\partial z}{\partial v} \\ \frac{\partial z}{\partial w} & \frac{\partial y}{\partial w} & \frac{\partial z}{\partial w} \end{vmatrix}$$

is the Jacobian determinant.

<sup>§</sup>In everyday speech, a volumetric region is called a volume, and we are arguably being a bit pedantic here; however, in mathematics it is sometimes necessary to be more careful about distinguishing between the number that measures the size of a three-dimensional region and the region itself.