PROFESSIONAL APPLICATION / GEL SYSTEM

Super-Pigmented Gel Polish Application Guide

BLOM Cosmetics Gel Polishes are beautifully buttery and highly pigmented. Their rich colour payoff means **very thin, even coats** are essential for a smooth finish and correct curing. Follow our professional application sequence below.

01 REMOVE EXISTING PRODUCT & PREPARE THE CUTICLES

- Completely remove old nail product using a suitable removal method. Do not apply over lifting or compromised product.
- Gently push back the cuticles and carefully remove non-living tissue from the nail plate.

02 GENTLY REMOVE THE NATURAL SHINE

- Using a sanding band, gently remove the natural shine from the nail plate.
- Our preferred sanding band is **150 grit**; use very light pressure and minimal passes. Choose a finer abrasive if needed to protect the natural nail. Never thin or damage the nail plate.

03 CLEANSE THE NAIL PLATE

- Remove all dust and thoroughly cleanse the nail plate with **BLOM Cosmetics Cleanser**. Let the surface dry.

04 APPLY NAIL PREP / DEHYDRATOR

- Apply **BLOM Cosmetics Prep** to temporarily dehydrate the nail plate and remove surface oils. Allow it to evaporate fully.

05 APPLY A VERY THIN LAYER OF PRIMER

- Apply **ONE exceptionally thin layer** of BLOM Cosmetics Ultimate Primer or **Super Bond Vitamin Primer**. The Super Bond formula is vitamin-infused.
- A little goes a long way. Do not flood the cuticles or sidewalls. Allow the primer to settle/dry as directed.

> **PRIMER REMINDER**
> Our vitamin-infused Super Bond Primer has a thicker consistency. Only **one very thin layer** is needed - using more does not improve retention.

06 APPLY ULTRA BOND BASE GEL

- Apply a thin, even layer of **BLOM Cosmetics Ultra Bond Base Gel** - identifiable by its **blue-and-white-striped bottle**. Avoid contact with the skin.
- Cure for **60 seconds** in a compatible, verified nail lamp. Then proceed with your chosen service.

THE MOST IMPORTANT APPLICATION RULE

Thin Layers. Complete Cure.

Because BLOM gel colours are so highly pigmented, a thick application can block effective light penetration and lead to wrinkling or incomplete curing. **Never try to achieve full coverage in one thick coat.**



CORRECT: VERY THIN

Even coat • fully cure each layer



INCORRECT: TOO THICK

May wrinkle • risk of incomplete cure

07 CHOOSE YOUR APPLICATION PATH

- **Option A - Rubber Base Enhancement:** After curing the Ultra Bond Base Gel, build your Rubber Base Enhancement as needed and fully cure it according to the BLOM Rubber Base application instructions before applying colour.
- **Option B - Gel Colour Overlay or Toes:** After curing the Ultra Bond Base Gel, proceed directly to BLOM Cosmetics Gel Polish colour.

08 APPLY THE SUPER-PIGMENTED GEL COLOUR

- Load your brush sparingly. Apply the **first coat VERY THINLY**, distributing colour evenly without pooling at the cuticles or sidewalls.
- **Fully cure every layer** for the verified time specified for that gel colour and compatible lamp. Repeat with another very thin coat if more coverage is needed.
- Keep gel off the surrounding skin. Never leave a coat thick in order to gain instant opacity.

CRITICAL - WHY GEL POLISH WRINKLES

If gel polish is applied too thick, the surface may wrinkle or ripple and the product underneath may remain uncured. **Do not seal wrinkled or undercured gel with top coat.** Remove the affected product, confirm lamp suitability, and reapply in very thin layers.

09 FINISH WITH TOP COAT

- Once colour layers are fully cured, apply an even layer of BLOM Cosmetics Top Coat without flooding the skin.
- Cure according to the **specific top coat instructions** with a compatible lamp. Finish as required by the top coat formulation.

LAMP PERFORMANCE IS ESSENTIAL

Use a properly functioning, well-maintained lamp suitable for the BLOM gel system. Check lamp compatibility, correct hand/foot placement, cleanliness and performance; replace ageing or underperforming lamps as needed. **Wattage alone does not guarantee a proper cure.** The 60-second instruction above refers to Ultra Bond Base Gel - gel colour, Rubber Base and Top Coat require their own validated curing instructions.

Beautiful, richly pigmented colour starts with controlled application - **thin coats and thorough curing are non-negotiable.**