BLOM

COSMETICS

PROFESSIONAL TECHNIQUE GUIDE

RUBBER BASE GEL SYSTEM

Natural Nail Overlay

Preparation • Adhesion • Structure • Finish

Beautiful application starts with correct preparation.

An easy-to-follow, detailed procedure for working with the BLOM Rubber Base Gel System and highly pigmented gel colours.

THE BLOM METHOD

Before you begin

Our self-levelling Rubber Base Gel is designed for natural nail overlays. Correct preparation, thin primer application, appropriate structure and validated curing are essential for reliable results.

APPLICATION SEQUENCE: Remove old product → Cuticle prep → De-shine → Cleanse → BLOM Prep → Vitamin Superbond Primer → Optional Ultimate Base Gel → Rubber Base slip layer & structured overlay → Cure → Refine → Optional gel colour → Top coat → Cuticle oil

STEPS 01–06

01 Prepare the natural nail

01 REMOVE EXISTING PRODUCT

Safely remove the previous nail product and begin with a completely clean nail plate.

- Remove remaining product, visible lifting and residue.
- Inspect the nail for damage, discoloration or signs of infection.
- Only proceed on a healthy, suitable natural nail.

BLOM TIP: Never apply fresh product over lifting or a compromised nail area.

02 CUTICLE PREPARATION

Complete a thorough, professional cuticle service.

- Gently push back the proximal nail fold.
- Carefully remove non-living cuticle from the nail plate.
- Pay special attention to the sidewalls and cuticle area.

BLOM TIP: Cuticle residue can interfere with adhesion. Never cut or damage living skin.

03 REMOVE NAIL PLATE SHINE

Use a fine-grit sanding band to gently remove the surface shine.

- Work with light, controlled pressure across the entire nail.
- Prepare close to the sidewalls without touching the skin.
- Do not over-file, heat or thin the natural nail.

BLOM TIP: Remove only the surface shine - not layers of the natural nail.

04 CLEAN THE NAIL PLATE

Remove all filing dust, oil and debris before chemical preparation.

- Dust nails with a clean nail brush.
- Wipe with suitable nail cleanser and a lint-free wipe.
- Allow nails to dry completely; do not touch the prepared plate.

05 APPLY BLOM PREP

Apply BLOM Prep to the prepared natural nail.

- Use a controlled, even application.
- Allow the product to evaporate or dry as indicated in its directions.
- Avoid touching the nail plate afterward.

06 APPLY VITAMIN SUPERBOND PRIMER

Our vitamin-infused BLOM primer has a thicker consistency than many conventional primers. Application control is extremely important.

- Remove excess primer from the brush before application.
- **Apply ONE exceptionally thin layer** to the natural nail plate.
- Spread evenly; leave no thick patches or pools.
- Do not flood the nail plate or touch surrounding skin.
- Allow the primer to settle or dry as directed.

> **VERY IMPORTANT: More primer does NOT mean better adhesion.** One thin, controlled layer is all you need.

STEPS 07–10

02 Build a balanced overlay

Work with a controlled slip layer and gently float the self-levelling gel to achieve an even, properly structured surface.

07 OPTIONAL: ULTIMATE BASE GEL

BLOM Ultimate Base Gel may be added before the Rubber Base overlay when desired.

- Apply one thin, even layer over the prepared and primed nail.
- Keep the base gel away from surrounding skin.
- Cure thoroughly according to validated product and lamp instructions.
- Then continue with BLOM Rubber Base Gel.

> **BLOM TIP:** This step is optional; it is not a compulsory part of the standard Rubber Base overlay.

08 APPLY THE SLIP LAYER

Apply a very thin slip layer of your chosen BLOM Rubber Base Gel.

- Coat the full nail plate evenly, including the sidewalls.
- Work neatly near the cuticle without touching the skin.
- **Leave the slip layer uncured** before positioning your structure bead.

> **BLOM TIP:** The uncured slip layer helps you float and direct the building bead smoothly.

09 FLOAT & STRUCTURE THE RUBBER BASE

Place an appropriately sized bead where the overlay needs structure.

- Float the bead gently across the uncured slip layer with light brush movements.
- Allow the self-levelling formula to create a smooth surface.
- Develop an appropriate apex and balanced structure for the nail length and shape.
- Keep the cuticle and sidewalls refined; prevent excessive bulk.
- Cover the free edge appropriately.

If helpful, briefly turn the hand palm-up to support product levelling before curing.

> **SKIN-CONTACT SAFETY:** Never cure uncured gel that has touched the skin. Remove all skin contact before the hand enters the lamp.

10 CURE THE RUBBER BASE

BLOM recommends a 120-second cure for this thick-consistency Rubber Base Gel, using a suitable compatible lamp.

- Position the hand correctly to allow full nail exposure.
- Keep the product within the validated maximum thickness.
- Check the gel and lamp combination against manufacturer curing specifications.

> **CURING NOTE:** 120 seconds alone does not guarantee a complete cure with an incompatible lamp or an excessively thick overlay. Use validated curing parameters.

STEPS 11, 13–14

03 Refine & finish

Choose a natural Rubber Base finish or add BLOM Gel Polish before applying top coat.

11 FILE, SHAPE & PERFECT

After the gel is fully cured, refine the overlay as needed.

- Remove the inhibition layer with a suitable cleanser before filing if required.
- Shape the free edge and refine the sidewalls.
- Smooth uneven areas; assess balance and apex placement.
- Remove all filing dust before moving on.

> **BLOM TIP:** For a natural Rubber Base finish, proceed directly to top coat. For colour, follow the optional gel polish instructions next.

COLOUR APPLICATION — STEP 12

Optional: BLOM Gel Polish

Our buttery, highly pigmented gel polishes require precise, **thin** application to support proper curing.

12 APPLY BLOM GEL POLISH

Apply colour over the cured, refined and cleaned Rubber Base overlay, before top coat.

- Apply the first coat as a **very thin, even layer**.
- Keep product away from cuticles and surrounding skin.
- Cure that layer using a compatible lamp and the validated instructions for the specific shade.
- If needed, apply a second thin layer and cure it separately and thoroughly.

> **EXTREMELY IMPORTANT: TWO THIN LAYERS are better than ONE THICK LAYER.** Highly pigmented colour applied too thickly may not cure adequately, even if the surface seems hard.

13 APPLY BLOM TOP COAT

Finish your Rubber Base-only or gel polish application with BLOM Top Coat.

- Apply a smooth, even layer without flooding the skin.
- Cover the nail and seal the free edge when appropriate.
- Cure according to the top coat's product-specific curing instructions.

14 FINISH WITH CUTICLE OIL

After all layers are fully cured and your service is complete, apply cuticle oil around the nail and massage it gently into the skin.

SAVE & SHARE WITH YOUR TEAM

The BLOM golden application rules

PREPARATION IS EVERYTHING
Begin with a thoroughly clean, correctly prepared natural nail plate.

LESS IS MORE WITH OUR PRIMER
Only one exceptionally thin layer of thicker Vitamin Superbond Primer is needed.

FLOAT, DON'T FLOOD
Use gentle strokes and controlled product placement to guide the Rubber Base.

KEEP GEL OFF THE SKIN
Do not cure uncured gel that has touched the cuticles or surrounding skin.

CURE CORRECTLY
Follow validated product curing times, application thicknesses and lamp specifications.

KEEP GEL POLISH THIN
Highly pigmented colours must be applied in thin, individually cured coats.

PERFECT THE STRUCTURE
Balanced application supports strength, appearance and durability.

A NOTE FROM BLOM COSMETICS
Outstanding results come from quality products and correct techniques. Our primer, Rubber Base and highly pigmented gel colours each have their own consistency and handling needs. We encourage every nail technician to learn our system rather than assuming all brands apply in the same way.

Correct application makes all the difference.
With love, BLOM COSMETICS | Where Beauty Blooms

Technical reminder: Before sharing this as a manufacturer-approved curing guide, confirm the 120-second Rubber Base cure and all product-specific cure times against the manufacturer's validated lamp wavelength, irradiance and maximum layer thickness.