Viewing Privilege and Role Information

To access information about grants of privileges and roles, you can query the following data dictionary views:

View	Description
DBA_COL_PRIVS	DBA view describes all column object grants in the database. ALL view describes all column object grants
ALL_COL_PRIVS	for which the current user or PUBLIC is the object owner, grantor, or grantee. USER view describes column object grants for which the current user is the object owner, grantor, or grantee.
USER_COL_PRIVS	
ALL_COL_PRIVS_MADE	ALL view lists column object grants for which the current user is object owner or grantor. USER view
USER_COL_PRIVS_MADE	describes column object grants for which the current user is the grantor.
ALL_COL_PRIVS_RECD	ALL view describes column object grants for which the current user or PUBLIC is the grantee. USER view
USER_COL_PRIVS_RECD	describes column object grants for which the current user is the grantee.
DBA_TAB_PRIVS	DBA view lists all grants on all objects in the database. ALL view lists the grants on objects where the user
ALL_TAB_PRIVS	or PUBLIC is the grantee. USER view lists grants on all objects where the current user is the grantee.
USER_TAB_PRIVS	
ALL_TAB_PRIVS_MADE	ALL view lists the all object grants made by the current user or made on the objects owned by the current
USER_TAB_PRIVS_MADE	user. USER view lists grants on all objects owned by the current user.
ALL_TAB_PRIVS_RECD	ALL view lists object grants for which the user or PUBLIC is the grantee. USER view lists object grants for
USER_TAB_PRIVS_RECD	which the current user is the grantee.
DBA_ROLES	This view lists all roles that exist in the database.
DBA_ROLE_PRIVS	DBA view lists roles granted to users and roles. USER view lists roles granted to the current user.
USER_ROLE_PRIVS	

View	Description
DBA_SYS_PRIVS	DBA view lists system privileges granted to users and roles. USER view lists system privileges granted to
USER_SYS_PRIVS	the current user.
ROLE_ROLE_PRIVS	This view describes roles granted to other roles. Information is provided only about roles to which the user has access.
ROLE_SYS_PRIVS	This view contains information about system privileges granted to roles. Information is provided only about roles to which the user has access.
ROLE_TAB_PRIVS	This view contains information about object privileges granted to roles. Information is provided only about roles to which the user has access.
SESSION_PRIVS	This view lists the privileges that are currently enabled for the user.
SESSION_ROLES	This view lists the roles that are currently enabled to the user.

Some examples of using these views follow. For these examples, assume the following statements have been issued:

```
CREATE ROLE security_admin IDENTIFIED BY honcho;

GRANT CREATE PROFILE, ALTER PROFILE, DROP PROFILE,
CREATE ROLE, DROP ANY ROLE, GRANT ANY ROLE, AUDIT ANY,
AUDIT SYSTEM, CREATE USER, BECOME USER, ALTER USER, DROP USER
TO security_admin WITH ADMIN OPTION;

GRANT SELECT, DELETE ON SYS.AUD$ TO security_admin;

GRANT security_admin, CREATE SESSION TO swilliams;

GRANT security_admin TO system_administrator;

GRANT CREATE SESSION TO jward;

GRANT SELECT, DELETE ON emp TO jward;

GRANT INSERT (ename, job) ON emp TO swilliams, jward;
```