PostgreSQL 14 to 16 Upgrade - Step-by-Step Guide

Author: Subrahmanyeswarao Karri

Designation: Database Architect

Email: subrahmanyeswaraokarri@example.com

```
PostgreSQL 14 to 16 Upgrade Step-by-Step
This guide outlines the full procedure to upgrade PostgreSQL 14 to 16 on Ubuntu with a
custom data directory.
## Step 1: Install PostgreSQL 16
```bash
sudo apt install wget ca-certificates -y
wget --quiet -O - https://www.postgresql.org/media/keys/ACCC4CF8.asc | sudo apt-key add
echo "deb http://apt.postgresql.org/pub/repos/apt $(lsb_release -cs)-pgdg main" | sudo
tee /etc/apt/sources.list.d/pgdg.list
sudo apt update
sudo apt install postgresql-16 postgresql-client-16 -y
Step 2: Backup PostgreSQL 14
```bash
pg_dumpall > /tmp/pg14_full_backup.sql
## Step 3: Stop PostgreSQL 14
```bash
sudo systemctl stop postgresql@14-main
Step 4: Set Permissions
```bash
sudo chown -R postgres:postgres /postgresql
sudo chmod 700 /postgresql
. . .
## Step 5: Initialize PostgreSQL 16
```

```
```bash
sudo -u postgres /usr/lib/postgresql/16/bin/initdb -D /postgresql/data16
Step 6: Perform the Upgrade
```bash
sudo -i -u postgres
/usr/lib/postgresql/16/bin/pg_upgrade \
  --old-datadir=/postgresql/data \
  --new-datadir=/postgresql/data16 \
 --old-bindir=/usr/lib/postgresql/14/bin \
  --new-bindir=/usr/lib/postgresql/16/bin \
 > /postgresql/logs/pg_upgrade_final.log 2>&1
## Step 7: Start PostgreSQL 16
```bash
sudo systemctl start postgresql@16-main
sudo -u postgres psql -c "SELECT version();"
Step 8: Cleanup PostgreSQL 14
```bash
sudo systemctl stop postgresql@14-main
sudo apt purge postgresql-14 postgresql-client-14 -y
sudo apt autoremove --purge -y
sudo rm -rf /postgresql/data
. . .
---
```

PostgreSQL 16 is now fully operational!